PyMSES Documentation

Release 4.0.0

Thomas GUILLET, Damien CHAPON, Marc LABADENS

CONTENTS

1	1 User's guide				
	1.1	PyMSES: Python modules for RAMSES	3		
	1.2	Installing PyMSES	4		
	1.3	Get a RAMSES output into PyMSES			
	1.4	Reading particles			
	1.5	AMR data access			
	1.6	RAMSES AMR file formats	1(
	1.7	Dealing with units	11		
	1.8	Data filtering	13		
	1.9		15		
	1.10	Visualization tools	19		
2	ce documentation	4]			
	2.1	Data structures and containers	41		
	2.2	Sources module	45		
	2.3	Filters module	46		
	2.4	Analysis module	48		
	2.5	Utilities package	61		
Ру	thon I	Module Index	67		
In	dex		69		

This is the up-to-date (version 4.0.0) online PyMSES manual.

All the examples presented in this manual are based on RAMSES data available here : data_dl.

CONTENTS 1

2 CONTENTS

USER'S GUIDE

1.1 PyMSES: Python modules for RAMSES

1.1.1 Introduction

PyMSES is a set of Python modules originally written for the RAMSES astrophysical fluid dynamics AMR code.

Its purpose:

- provide a clean and easy way of **getting the data** out of RAMSES simulation outputs.
- help you analyse/manipulate very large simulations transparently, without worrying more than needed about domain decompositions, memory management, etc.,
- interface with a lot of powerful Python libraries (Numpy/Scipy, Matplotlib, PIL, HDF5/PyTables) and existing code (like your own).
- be a post-processing toolbox for your own data analysis.

What PyMSES is NOT

It is **not an interactive environment** by itself, but:

- it provides modules which can be used interactively, for example with IPython.
- it also provides an *AMRViewer* graphical user intergace (GUI) module that allows you to get a quick and easy look at your AMR data.

1.1.2 Downloads

• downloads

1.1.3 Documentation

• Documentation (HTML)

1.1.4 Contacts

Authors Thomas GUILLET, Damien CHAPON, Marc LABADENS

Contact PyMSES-users@googlegroups.com

Organization Service d'astrophysique, CEA/Saclay

Address Gif-Sur-Yvette, F91190, France

Date January 30, 2014

1.1.5 Indices and tables

- genindex
- modindex
- search

1.2 Installing PyMSES

1.2.1 Requirements

PyMSES has some *Core dependencies* plus some *Recommended dependencies* you might need to install to enable all PyMSES features.

The development team strongly recommends the user to install the EPD (Enthought Python Distribution) which wraps all these dependencies into a single, highly-portable package.

Core dependencies

These packages are mandatory to use the basic functionality of PyMSES:

- a gcc-compatible C compiler,
- GNU make and friends,
- Python, version 2.x (not 3.x), including development headers (Python.h and such), python 2.6.x or later is recommended to use some multiprocessing speed up.
- · Python packages:
 - numpy, version 1.2 or later
 - scipy
- iPython is not strictly required, but it makes the interactive experience so much better you will certainly want to install it.

Recommended dependencies

Those packages are recommended for general use (plotting, easy input and output, image processing, GUI, ...). Some PyMSES features may be unavailable without them:

- matplotlib for plotting
- the Python Imaging Library (PIL) for Image processing

- HDF5 and PyTables for Python HDF5 support
- · wxPython for the AMRViewer GUI
- mpi4py if you want to use the MPI library on a large parallel system.

Delevoper dependencies

You will need this if you intend to work on the source code, or if you obtained PyMSES for an unpackaged version (i.e. a tarball of the mercurial repository, or hg clone)

- · mercurial for source code management
- Cython
- sphinx for generating the documentation

1.2.2 Installation instructions

For now, the easiest way to install PyMSES from a tarball is:

- 1. Extract the tarball into a directory, say ~/codes/pymses
- 2. Run make in the directory
- 3. Add the make directory to your PYTHONPATH
- 4. Optional: Add the pymses/bin to your PATH, to quickly start the GUI with the amrviewer command or to launch basic scripts.

For example, using the bash shell:

```
$ cd ~/codes
$ tar -xvfz pymses-3.0.0.tar.gz
$ cd pymses_3.0.0
$ make
$ export PYTHONPATH=~/codes/pymses_3.0.0:$PYTHONPATH
$ export PATH=$PATH:~/codes/pymses_3.0.0/bin
```

Note that you will need to place the export statements in your ~/.bashrc or equivalent to set your PYTHONPATH and PATH for all future shell sessions.

1.3 Get a RAMSES output into PyMSES

Use case

You want to select a specific RAMSES output directory and get somme basic information about it

1.3.1 RAMSES output selection

First, you need to select the snapshot of your RAMSES simulation you would like to read by creating a RamsesOutput object:

```
import pymses
ro = pymses.RamsesOutput("/data/Aquarius/outputs", 193)
```

In this example, you are intersted in the files contained in /data/Aquarius/output/ouput_00193/

1.3.2 Ouput information

To get some details about this specific output/simulation. Everything you need is in the *info* parameter:

```
ro.info
Out:{'H0': 73.0,
    'aexp': 1.0000620502295701,
    'boxlen': 1.0,
    'dom_decomp': <pymses.sources.ramses.hilbert.HilbertDomainDecomp object at 0x3305e10>,
    'levelmax': 18,
    'levelmin': 7,
    'ncpu': 64,
    'ndim': 3,
    'ngridmax': 800000,
    'nstep_coarse': 9578,
    'omega_b': 0.03999999105930301,
    'omega_k': 0.0,
    'omega_1': 0.75,
    'omega_m': 0.25,
    'time': 6.2446534480863097e-05,
    'unit_density': (2.50416381926e-27 m^-3.kg),
    'unit_length': (4.21943976727e+24 m),
    'unit_mass': (1.88116596007e+47 kg),
    'unit_pressure': (2.50385294276e-13 m^-1.kg.s^-2),
    'unit_temperature': (12021826243.9 K),
    'unit_time': (4.21970170037e+17 s),
    'unit_velocity': (9999379.26156 m.s^-1)}
ro.info["ncpu"]
Out:64
ro.info["boxlen"] / 2**ro.info["levelmax"]
Out:3.814697265625e-06
```

This way, you can easily find the units of your data (see Dealing with units).

1.4 Reading particles

1.4.1 Particle data source

If you want to look at the particles, you need to create a RamsesParticleSource. To do so, call the particle_source() method of your RamsesOutput object with a list of the different fields you might need in your analysis.

The available fields are:

- "vel": the velocities of the particles
- "mass": the mass of the particles
- "id": the id number of the particles
- "level": the AMR level of refinement of the cell each particle belongs to
- "epoch": the birth time of the particles (0.0 for ic particles, >0.0 for star formation particles)

• "metal": the metallicities of the particles

```
ro = pymses.RamsesOutput("/data/Aquarius/output", 193)
part = ro.particle_source(["vel", "mass"])
```

Warning

The data source you just created does not contain data. It is designed to provide an *on-demand* access to the data. To be memory-friendly, nothing is read from the disk yet at this point. All the part_00193.out_* files are only linked to the data source for further processing.

1.4.2 PointDataset

At the opposite, a PointDataset is an actual data container.

Single CPU particle dataset

If you want to read all the particles of the cpu number 3 (written in part_00193.out_00003), use the get_domain_dset() method:

```
dset3 = part.get_domain_dset(3)
Out:Reading particles : /data/Aquarius/output/output_00193/part_00193.out00003
```

Number of particles

Every PointDataset has a npoints int parameter which gives you the number of particles in this dataset:

```
print "CPU 3 has %i particles"%dset3.npoints
Out:CPU 3 has 157976 particles
```

Particle coordinates

The *points* parameter of the PointDataset contains the coordinates of the particles:

Particle fields

You also have an easy access to the different fields:

1.4.3 Whole point data source concatenation

To read all the particles from all the ncpus part_00193.out * files and concatenate them into a single (but maybe not memory-friendly) dataset, call the flatten() method of your *part* object:

```
dset_all = part.flatten()
Out:Reading particles : /data/Aquarius/output/output_00193/part_00193.out00001
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00002
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00003
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00004

[...]

Reading particles : /data/Aquarius/output/output_00193/part_00193.out00062
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00063
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00064

print "Domain has %i particles"%dset_all.npoints
Out:Domain has 10000000 particles
```

1.4.4 CPU-by-CPU particles

In most cases, you won't have enough memory to load all the particles of your simulation domain into a single dataset. You have two different options:

- Filter your particles (see *Data filtering*).
- Your analysis can be done on a cpu-by-cpu basis. The RamsesParticleSource provides a iter_dsets() iterator yielding cpu-by-cpu datasets:

```
for dset in part.iter_dsets():
    print dset.npoints

Out:Reading particles : /data/Aquarius/output/output_00193/part_00193.out00001
    254210
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00002
    214330
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00003
    359648
    [...]
    Reading particles : /data/Aquarius/output/output_00193/part_00193.out00064
    351203
```

1.5 AMR data access

1.5.1 AMR data source

If you want to deal with the AMR data, you need to call the amr_source() method of your RamsesOutput object with a single argument which is a list of the different fields you might need in your analysis.

When calling the amr_source(), the fields you have access to are:

- "rho": the gas density field
- "vel": the gas velocity field

- "P": the gas pressurre field
- "g": the gravitational acceleration field

To modify the list of available data fields, see RAMSES AMR file formats.

```
ro = pymses.RamsesOutput("/data/Aquarius/output", 193)
amr = ro.amr_source(["rho", "vel", "P", "g"])
```

Warning

The data source you just created does not contain data. It is designed to provide an *on-demand* access to the data. To be memory-friendly, nothing is read from the disk yet at this point. All the amr_00193.out_*, hydro_00193.out_* and grav_00193.out_* files are only linked to the data source for further processing.

1.5.2 AMR data handling

AMR data is a bit more complicated to handle than particle data. To perform various analysis, PyMSES provides you with two different tools to get your AMR data:

- AMR grid to cell list conversion
- AMR field point-sampling

AMR grid to cell list conversion

The CellsToPoints filter converts the AMR tree structure into a IsotropicExtPointDataset containing a list of the AMR grid *leaf envelope* cells:

- The *points* parameter of the datasets coming from the generated data source will contain the coordinates of the cell centers.
- These datasets will have an additional get_sizes() method giving you the size of each cell.

```
from pymses.filters import CellsToPoints
cell_source = CellsToPoints(amr)
cells = cell_source.flatten()
[...]
# Cell centers
ccenters = cells.points
# Cell sizes
dx = cells.get_sizes()
```

Warning

As a Filter, the *cell_source* object you first created is another data provider, it doesn't contain actual data. To read the data, use <code>get_domain_dset()</code>, <code>iter_dsets()</code> or <code>flatten()</code> method as described in *Reading particles*.

AMR field point-sampling

Another way to read the AMR data is to perform a sampling of the AMR fields with a set of sampling points coordinates of your choice. In PyMSES, this is done quite easily with the sample_points() function:

1.5. AMR data access 9

```
from pymses.analysis import sample_points
sample_dset = sample_points(amr, points)
```

The returned *sample_dset* will be a PointDataset containing all your sampling points and the corresponding value of the different AMR fields you selected.

Note

In backstage, the point sampling is performed with a *tree search* algorithm, which makes this particular process of AMR data access both **user-friendly** and **efficient**.

For example, this method can be used:

- for visualization purposes (see *Slices*).
- when computing profiles (see *Profile computing*)

1.6 RAMSES AMR file formats

1.6.1 Default

The default settings for the AMR data file formats is as follow:

which means that in the hydro_*.out* files:

- the first read variable corresponds to the scalar gas density field
- the next 3 read variables corresponds to the gas 3D velocity field
- the fifth read variable corresponds to the scalar gas **pressure** field

and in the grav_*.out* files:

• the 3 read variables corresponds to the 3D gravitational acceleration field

1.6.2 User-defined

If you use a nD (nnotequalto3) or a non-standard version of RAMSES, you might want to redefine this AMR file format to:

- make additional tracers available to your reader
- read nD (nnotequalto3) data

1.6.3 User-defined output file

In order to have user defined variables updated automatically by PyMSES when an output is opened, you can create a "pymses_field_descrs.py" in your current directory with this structure :

1.7 Dealing with units

Need

Okay, I have read my data quite easily. What are the units of these data? How do I convert them into human-readable units?

Example: From a RAMSES hydro simulation, I want to convert my density field unit into the H/cc unit.

1.7.1 Dimensional physical constants

In pymses, a specific module has been designed for this purpose: constants.

It contains a bunch of useful dimensional physical constants (expressed in ISU) which you can use for unit conversion factors computation, adimensionality tests, etc.

```
from pymses.utils import constants as C
print C.kpc
Out:(3.085677e+19 m)
print C.Msun
Out:(1.9889e+30 kg)
```

Each constant is an Unit instance, on which you can call the express() method to convert this constant into another dimension-compatible constant. If the dimensions are not compatible, a ValueError will be raised

```
factor = C.kpc.express(C.ly)
print "1 kpc = %f ly"%factor
Out:1 kpc = 3261.563163 ly

print C.Msun.express(C.km)
Out:ValueError: Incompatible dimensions between (1.9889e+30 kg) and (1000.0 m)
```

Basic operations between these constants are enabled

```
unit_density = 1.0E9 * C.Msun / C.kpc**3
print "1Msun/kpc**3 = %f H/cc"%unit_density.express(C.H_cc)
Out:1Msun/kpc**3 = 30.993246 H/cc
```

1.7.2 RAMSES data units

The units of each RAMSES output data are read from the output info file. You can manipulate the values of these units by using the *info* parameter (see *RAMSES output selection*)

```
ro = RamsesOutput("/data/simu/outputs", 10)
ro.info
Out:{'H0': 1.0,
    'aexp': 1.0,
    'boxlen': 200.0,
    'dom_decomp': <pymses.sources.ramses.hilbert.HilbertDomainDecomp object at 0x9df0aac>,
    'levelmax': 14,
    'levelmin': 7,
    'ncpu': 64,
    'ndim': 3,
    'ngridmax': 1000000,
    'nstep_coarse': 1200,
    'omega_b': 0.0,
    'omega_k': 0.0,
    'omega_1': 0.0,
    'omega_m': 1.0,
    'time': 10.724764558171801,
    'unit_density': (6.77025430199e-20 m^-3.kg),
    'unit_length': (6.17135516256e+21 m),
    'unit_mass': (1.9891e+39 kg),
    'unit_pressure': (2.91283226304e-10 m^-1.kg.s^-2),
    'unit_temperature': (517290.92492 K),
```

```
'unit_time': (4.70430312424e+14 s),
'unit_velocity': (65592.6605874 m.s^-1)}
```

Assuming you already have sampled the AMR density field of this output into a *pdset* PointDataset containing all your sampling points (see *AMR field point-sampling*), you can convert your density field (in code unit) into the unit of your choice:

```
rho_field_H_cc = pdset["rho"] * ro.info["unit_density"].express(C.H_cc)
```

Warning

You must take care of manipulating RAMSES data in an unit-coherent way !!!

• Good:

info = ro.info

Density

```
rho_H_cc = rho_ramses * info["unit_density"].express(C.H_cc)
 # Mass
 part_mass_Msun = part_mass * info["unit_mass"].express(C.Msun)
 # Kinetic energy
 factor = (info["unit_mass"] * info["unit_velocity"]**2).express(C.J)
 kin_energy_J = part_mass * part_vel**2 * factor
· Not so good:
 info = ro.info
 # Density
 factor = (info["unit_mass"] / info["unit_length"]**3).express(C.H_cc)
 rho_H_cc = rho_ramses * factor
 # Mass
 factor = (info["unit_density"]*info["unit_length"]**3).express(C.Msun)
 part_mass_Msun = part_mass * factor
 # Kinetic energy
 factor = (info["unit_pressure"] * info["unit_length"] ** 3).express(C.J)
 kin_energy_J = part_mass * part_vel**2 * factor
```

1.8 Data filtering

In PyMSES, a Filter is a data source that:

- filter the data coming from an origin data source.
- provides a new data source out of this filtering process.

1.8.1 Region filter

For a lot of analysis, you are often interested in a particular region of your simulation domain, for example:

• spherical region centered on a dark matter halo in a cosmological simulation.

1.8. Data filtering

• cylindrical region containing a galactik disk or a cosmological filament.

• ...

```
# Region of interest
from pymses.utils.regions import Sphere
center = [0.5, 0.5, 0.5]
radius = 0.1
region = Sphere(center, radius)

To filter data source with a region, use the RegionFilter:
from pymses.filters import RegionFilter
from pymses import RamsesOutput
ro = RamsesOutput("/data/Aquarius/output/", 193)
parts = ro.particle_source(["mass"])
amr = ro.amr_source(["rho"])

# Particle filtering
filt_parts = RegionFilter(region, parts)

# AMR data filtering
filt_amr = RegionFilter(region, amr)
```

Note

The region filters can greatly improve the I/O performance of your analysis process since it doesn't require to read all the cpu files (of your entire simulation domain) but only those whose domain intersects your region of interest.

The filtering process occurs not only at the cpu level (as any other Filter) but also in the choice of required cpu files.

1.8.2 The CellsToPoints filter

see AMR grid to cell list conversion.

1.8.3 Function filters

You can also define your own function filter. Here an example where only the particles of mass equal to $3\times 10^3 M_{\odot}$ are gathered :

```
from pymses.filters import PointFunctionFilter
from pymses.utils import constants as C

part_source = ro.particle_source(["mass"])

# Stellar disc particles filter : only keep particles of mass = 3000.0 Msun
part_mass_Msun = 3.0E3 * C.Msun
part_mass_code = part_mass_Msun.express(ro.info["unit_mass"])
st_disc_func = lambda dset: (dset["mass"] == part_mass_code)

# Stellar disc particle data source
st_disc_parts = PointFunctionFilter(st_disc_func, part_source)
```

1.8.4 Randomly decimated data

You can use the PointRandomDecimatedFilter filter to pick up only a given fraction of points (randomly chosen) from your point-based data:

```
from pymses.filters import PointRandomDecimatedFilter
part_source = ro.particle_source(["mass"])

# Pick up 10 % of the particles
fraction = 0.1
dec_parts = PointRandomDecimatedFilter(fraction, part_source)
```

1.8.5 Combining filters

You can pile up as many filters as you want to get the particular data you're interested in:

```
# Region filter
reg_parts = RegionFilter(region, parts)

# Stellar disc filter
st_disc_parts = PointFunctionFilter(st_disc_func, reg_parts)

# 10 % randomly decimated filter
dec_parts = PointRandomDecimatedFilter(fraction, st_disc_parts)
```

In this example, the dec_parts data source will provide you 10% of the stellar particles contained within a given region

1.9 Analysis tools

1.9.1 Profile computing

In this section are presented 2 examples of profile computing. The first is based on AMR data and the second on particles data.

Cylindrical profile of an AMR scalar field

Use case

You want to compute the cylindrical profile (for example, the surface density of a galactic disk) of a scalar AMR field (here, the rho density field). We assume that we know beforehand the configuration of the disk (center, radius, thickness, normal vector).

We take the configuration of the galactic disk to be:

```
gal_center = [ 0.567811, 0.586055, 0.559156 ] # in box units
gal_radius = 0.00024132905460547268 # in box units
gal_thickn = 0.00010238202316595811 # in box units
gal_normal = [ -0.172935, 0.977948, -0.117099 ] # Norm = 1
```

1.9. Analysis tools

Reading AMR data from the RAMSES output

As already explained in *Get a RAMSES output into PyMSES* and *AMR data access*, we create the AMR data source from the RAMSES output we are intersted in, reading only the density field:

```
from pymses import RamsesOutput
output = RamsesOutput("/data/Aquarius/output", 193)
# Prepare to read the density field only
source = output.amr_source(["rho"])
```

Random sampling of the AMR data fields in a given region of interest

Now we build the Cylinder that will define the region of interest for the profile:

```
from pymses.utils.regions import Cylinder
cyl = Cylinder(gal_center, gal_normal, gal_radius, gal_thickn)
```

Generation of an array of 10^6 random points uniformly spread within the cylinder (random_points() function), and then sampling of the AMR fields at these coordinates (see *AMR field point-sampling*):

```
from pymses.analysis import sample_points
points = cyl.random_points(1.0e6) # 1M sampling points
point_dset = sample_points(source, points)
```

Computing the profile from the point-based samples


As we are interested in the density profile, we use the data field rho as the weight function. We also take 200 linearly spaced radial bins within the cylinder radius:

```
import numpy
rho_weight_func = lambda dset: dset["rho"]
r_bins = numpy.linspace(0.0, gal_radius, 200)
```

Now we compute the profile of the resulting PointDataset using the bin_cylindrical() function.

We set the *divide_by_counts* flag to True, because we're averaging the density field in each cylindrical shell:

Finally, we can plot the profile with Matplotlib:



Spherical profile of a set of particle data

Use case

You want to compute the spherical radial profile of a given particle data field.

Example: From a RAMSES cosmological simulation, you want to compute the radial density profile of a dark matter halo. You already know the position and the size of the halo.

We take the location and spatial extension of the dark matter halo to be:

```
halo_center = [ 0.567811, 0.586055, 0.559156 ] # in box units
halo_radius = 0.00075 # in box units
```

Reading particle data from a RAMSES output

As already explained in *Get a RAMSES output into PyMSES* and *Reading particles*, we create the particle data source from the RAMSES output we are intersted in, reading only the *mass* and *epoch* fields:

```
from pymses import RamsesOutput
ro = RamsesOutput("/data/Aquarius/output", 193)
# Prepare to read the mass/epoch fields only
source = ro.particle_source(["mass", "epoch"])
```

1.9. Analysis tools

Filtering all the initial particles within a given region of interest

See Data filtering for details.

Now we build the Sphere that will define the region of interest for the profile:

```
from pymses.utils.regions import Sphere
sph = Sphere(halo_center, halo_radius)
```

Then filter all the particles contained in the sphere by using a RegionFilter:

from pymses.filters import RegionFilter point_dset = RegionFilter(sph, source)

Filter all the particles which are initially present in the simulation using a PointFunctionFilter:

```
from pymses.filters import PointFunctionFilter
dm_filter = lambda dset: dset["epoch"] == 0.0
dm_parts = PointFunctionFilter(dm_filter, point_dset)
```

Computing the profile

As we are interested in the density profile, we use the data field mass as the weight function. We also take 200 linearly spaced radial bins within the sphere radius:

```
import numpy
m_weight_func = lambda dset: dset["mass"]
r_bins = numpy.linspace(0.0, halo_radius, 200)
```


Now we compute the profile bin_spherical() function.

We set the *divide_by_counts* flag to False (optional, this is the default value), because we're cumulating the masses of the particles in spherical shells:

```
from pymses.analysis import bin_spherical
# This triggers the actual reading of the particle data files from disk.
mass_profile = bin_spherical(dm_parts, halo_center, m_weight_func, r_bins, divide_by_counts=False)
```

To compute the density profile, we divide the mass profile by the volume of each spherical shell:

```
sph_vol = 4.0/3.0 * numpy.pi * r_bins**3
shell_vol = numpy.diff(sph_vol)
rho_profile = mass_profile / shell_vol
```



1.10 Visualization tools

1.10.1 Camera and Operator

Camera

To do some data visualization, the view parameters are handled by a Camera:

```
from pymses.analysis.visualization import Camera
cam = Camera(center=[0.5, 0.5, 0.5], line_of_sight_axis='z', region_size=[0.5, 0.5], distance=0.5,
    far_cut_depth=0.5, up_vector='y', map_max_size=512, log_sensitive=True)
```


This object is then used in every PyMSES visualization tool to render an image from the data.

The standard isometric (parallel rays) camera is:

- centered around center
- oriented according to a **line_of_sight_axis** pointing towards the observer and an **up_vector** pointing upwards (in the camera plane)
- delimited by a **region_size** in the directions perpendicular to the camera plane. region_size[0] defines the size along the u camera horizontal vector, and region_size[1] defines the size along the v camera vertical vector
- · delimited by front/background cut planes at position distance/far_cut_depth along the line-of-sight axis

1.10. Visualization tools


- built with a virtual CCD-detector matrix of max. size map_max_size
- PyMSES camera box filtering definition:




projection plane

There is now a possibilty to transfom the standard pymses isometric view into a perspective view using the perspectiveAngle option (which uses degree unit). The default value "0" correspond to the isometric view, while a non zero value for this angle will set a perspective view as presented on the following figures:

• PyMSES perspective camera:





Notice that with this perspective camera definition, the filtered space is the same as the one of the isometric camera but the visualized space is restricted.

Saving / loading a Camera

Camera can be saved into a CSV file:

```
from pymses.analysis.visualization import Camera
cam = Camera(center=[0.5, 0.5, 0.8], line_of_sight_axis='y', region_size=[0.5, 0.8], distance=0.2)
cam.save_csv("my_cam.csv")
```

It can also be loaded from a CSV file to retrieve a previous view:

```
from pymses.analysis.visualization import Camera
cam = Camera.from_csv("my_cam.csv")
```

Other utility functions

The camera definition can be used to know the maximum Ramses AMR level up needed to compute the image map:

```
level_max = cam.get_required_resolution()
```

To do further computation we can also get the pixel surface from the camera object:

```
pixel_surface = cam.get_pixel_surface()
```

We can get some camera oriented slice points directly from the camera (see *Slices*):

```
slice_points = cam.get_slice_points(z)
```

Operator

For every PyMSES visualization method you might use, you must define the physical scalar quantity you are interested in.

For example, you can describe the kinetic energy of particles with the ScalarOperator:

```
import numpy
from pymses.analysis.visualization import ScalarOperator
def kin_en_func(dset):
    m = dset["mass"]
    v2 = numpy.sqrt(numpy.sum(dset["vel"]**2, axis=1))
    return m*v2
Ek = ScalarOperator(kin_en_func)
```

You can also define FractionOperator. For example, if you need a mass-weighted temperature operator for your AMR grid (FFT-maps):

```
from pymses.analysis.visualization import FractionOperator
M_func = lambda dset: dset["rho"] * dset.get_sizes()**3
def num(dset):
    T = dset["P"]/dset["rho"]
    M = M_func(dset)
    return T * M
op = FractionOperator(num, M_func)
```

If you want to ray-trace the max. AMR level of refinement along the line-of-sight, use MaxLevelOperator.

1.10.2 Maps

Slices

Intro

A quick way to look at data is to compute 2D data slice map.

Here is how it works: It first gets some sample points from a camera object, using a basic 2D Cartesian grid. Then those points are evaluated using the pymses point_sampler module. A sampling operator can eventually be applied on the data.

Example

We first need to define a suitable camera:


```
from pymses.analysis.visualization import Camera
cam = Camera(center=[0.5, 0.5, 0.5], line_of_sight_axis='z', region_size=[1., 1.],\
    up_vector='y', map_max_size=512, log_sensitive=True)
```

Using the amr data previously defined in *AMR data access*, we can get the map corresponding to the defined slice view. A logarithmic scale is here applied as it is defined in the camera object.

```
from pymses.analysis.visualization import SliceMap, ScalarOperator
rho_op = ScalarOperator(lambda dset: dset["rho"])
map = SliceMap(amr, cam, rho_op, z=0.4) # create a density slice map at z=0.4 depth position
```

The result can be seen using the matplotlib library:

```
import pylab as P
P.imshow(map)
P.show()
```



FFT-convolved maps

Intro

A very simple, fast and accurate data projection (3D->2D) method: each particle/AMR cell is convolved by a 2D gaussian kernel (*Splatter*) which size depends on the local AMR grid level.

The convolution of the binned particles/AMR cells histogram with the gaussian kernels is performed with FFT techniques by a MapFFTProcessor. You can see two examples of this method below:

- · Particles map
- AMR data map

Important note on operators


You must keep in mind that any X Operator you use with this method must describe an **extensive** physical variable since this method compute a summation over particle/AMR quantities:

$$map[i, j] = \sum_{\text{particles/AMR cells}} X$$

Examples

Particles map


```
from numpy import array, log10
import pylab
from pymses.analysis.visualization import *
from pymses import RamsesOutput
from pymses.utils import constants as C
# Ramses data
ioutput = 193
ro = RamsesOutput("/data/Aquarius/output/", ioutput)
parts = ro.particle_source(["mass", "level"])
# Map operator : mass
scal_func = ScalarOperator(lambda dset: dset["mass"])
# Map region
center = [ 0.567811, 0.586055, 0.559156 ]
axes = {"los": array([-0.172935, 0.977948, -0.117099])}
# Map processing
mp = fft_projection.MapFFTProcessor(parts, ro.info)
for axname, axis in axes.items():
                  cam = Camera(center=center, line_of_sight_axis=axis, up_vector="z", region_size=[5.0E-1, 4.
                                                       distance=2.0E-1, far_cut_depth=2.0E-1, map_max_size=512)
                  map = mp.process(scal_func, cam, surf_qty=True)
                  factor = (ro.info["unit_mass"]/ro.info["unit_length"]**2).express(C.Msun/C.kpc**2)
                  scale = ro.info["unit_length"].express(C.Mpc)
                    pylab.imshow(map)
                    pylab.show()
                   # Save map into HDF5 file
                  mapname = "DM_Sigma_%s_%5.5i"%(axname, ioutput)
                  h5fname = save_map_HDF5(map, cam, map_name=mapname)
                   # Plot map into Matplotlib figure/PIL Image
                  fig = save\_HDF5\_to\_plot (h5fname, map\_unit=("$M_{\oodot}.kpc^{-2}$", factor), axis\_unit=("Mpc", facto
                    pil_img = save_HDF5_to_img(h5fname, cmap="Blues", fraction=0.1)
                   # Save map into PNG image file
#
                     axis_unit=("Mpc", scale), img_path="./", cmap="Blues", fraction=0.1)
                     save_HDF5_to_img(h5fname, img_path="./", cmap="Blues", fraction=0.1)
# pylab.show()
```



AMR data map

```
from numpy import array
import pylab
from pymses.analysis.visualization import *
from pymses import RamsesOutput
from pymses.utils import constants as C
# Ramses data
ioutput = 193
ro = RamsesOutput("/data/Aquarius/output/", ioutput)
amr = ro.amr_source(["rho", "P"])
# Map operator : mass-weighted density map
up_func = lambda dset: (dset["rho"] **2 * dset.get_sizes() **3)
down_func = lambda dset: (dset["rho"] * dset.get_sizes()**3)
scal_func = FractionOperator(up_func, down_func)
# Map region
center = [ 0.567811, 0.586055, 0.559156 ]
axes = {"los": array([-0.172935, 0.977948, -0.117099])}
# Map processing
mp = fft_projection.MapFFTProcessor(amr, ro.info)
for axname, axis in axes.items():
```

```
cam = Camera(center=center, line_of_sight_axis=axis, up_vector="z", region_size=[5.0E-1, 4.
                                                                                     distance=2.0E-1, far_cut_depth=2.0E-1, map_max_size=512)
                           map = mp.process(scal_func, cam)
                            factor = ro.info["unit_density"].express(C.H_cc)
                            scale = ro.info["unit_length"].express(C.Mpc)
                              pylab.imshow(map)
                             # Save map into HDF5 file
                           mapname = "gas_mw_$s_$5.5i" $(axname, ioutput)
                            h5fname = save_map_HDF5(map, cam, map_name=mapname)
                            # Plot map into Matplotlib figure/PIL Image
                            fig = save_HDF5_to_plot(h5fname, map_unit=("H/cc",factor), axis_unit=("Mpc", scale), cmap="jetalor",
                              pil_img = save_HDF5_to_img(h5fname, cmap="jet")
                             # Save into PNG image file
                                save\_HDF5\_to\_plot (h5fname, \ map\_unit=("H/cc", factor), \ axis\_unit=("Mpc", \ scale), \ img\_path="./linearing", factor), \ axis\_unit=("Mpc", \ scale), \ 
                                save_HDF5_to_img(h5fname, img_path="./", cmap="jet")
# pylab.show()
```



Ray-traced maps

Intro

Ray-traced maps are computed in PyMSES by integrating a physical quantity along *rays*, each one corresponding to a pixel of the map. Ray-tracing is handled by a RayTracer. You can see two examples of this method below:

- Density map
- Min. temperature map
- Max. AMR level of refinement map

Important note on operators

You must keep in mind that any X Operator you use with this method must describe an **intensive** physical variable since this method compute an integral of an AMR quantity over each pixel surface and along the line-of-sight:

$$map[i,j] = \int_{z_{\min}}^{z_{\max}} X \mathrm{d}S_{\mathsf{pix}} \mathrm{d}z$$

Examples


Density map

```
from numpy import array
import pylab
from pymses.analysis.visualization import *
from pymses import RamsesOutput
from pymses.utils import constants as C
# Ramses data
ioutput = 193
ro = RamsesOutput("/data/Aquarius/output/", ioutput)
# Map operator : mass-weighted density map
up_func = lambda dset: (dset["rho"] * *2)
down_func = lambda dset: (dset["rho"])
scal_op = FractionOperator(up_func, down_func)
# Map region
center = [ 0.567811, 0.586055, 0.559156 ]
axes = {"los": array([ -0.172935, 0.977948, -0.117099 ])}
# Map processing
rt = raytracing.RayTracer(ro, ["rho"])
for axname, axis in axes.items():
        cam = Camera(center=center, line_of_sight_axis=axis, up_vector="z", region_size=[3.0E-2, 3.0]
                        distance=2.0E-2, far_cut_depth=2.0E-2, map_max_size=512)
       map = rt.process(scal_op, cam)
        factor = ro.info["unit_density"].express(C.H_cc)
        scale = ro.info["unit_length"].express(C.Mpc)
        # Save map into HDF5 file
        mapname = "gas_rt_mw_%s_%5.5i"%(axname, ioutput)
        h5fname = save_map_HDF5(map, cam, map_name=mapname)
```

```
# Plot map into Matplotlib figure/PIL Image
fig = save_HDF5_to_plot(h5fname, map_unit=("H/cc", factor), axis_unit=("Mpc", scale), cmap="je
pil_img = save_HDF5_to_img(h5fname, cmap="jet")


# Save into PNG image file
save_HDF5_to_plot(h5fname, map_unit=("H/cc", factor), axis_unit=("Mpc", scale), img_path="./"
save_HDF5_to_img(h5fname, img_path="./", cmap="jet")
```





Min. temperature map

```
def invT_func(dset):
                        P = dset["P"]
                        rho = dset["rho"]
                        r = rho/P
                         print r[(rho <= 0.0) + (P <= 0.0)]
                         r[(rho <= 0.0) * (P <= 0.0)] = 0.0
                        return r
                d = {"invTemp": invT_func}
                Operator.__init__(self, d, is_max_alos=True)
        def operation(self, int_dict):
                        map = int_dict.values()[0]
                        mask = (map == 0.0)
                        mask2 = map != 0.0
                        map[mask2] = 1.0 / map[mask2]
                        map[mask] = 0.0
                        return map
scal_op = MyTempOperator()
# Map region
center = [ 0.567111, 0.586555, 0.559156 ]
axes = {"los": "z"}
# Map processing
rt = raytracing.RayTracer(ro, ["rho", "P"])
for axname, axis in axes.items():
        cam = Camera(center=center, line_of_sight_axis=axis, up_vector="y", region_size=[3.0E-3, 3.0E-3]
                        distance=1.5E-3, far_cut_depth=1.5E-3, map_max_size=512)
        map = rt.process(scal_op, cam)
        factor = ro.info["unit_temperature"].express(C.K)
        scale = ro.info["unit_length"].express(C.Mpc)
        # Save map into HDF5 file
        mapname = "gas_rt_Tmin_%s_%5.5i"%(axname, ioutput)
        h5fname = save_map_HDF5(map, cam, map_name=mapname)
        # Plot map into Matplotlib figure/PIL Image
        fig = save_HDF5_to_plot(h5fname, map_unit=("K", factor), axis_unit=("Mpc", scale), cmap="hot"
        pil_img = save_HDF5_to_img(h5fname, cmap="hot")
        # Save into PNG image file
         save_HDF5_to_plot(h5fname, map_unit=("K", factor), axis_unit=("Mpc", scale), img_path="./",
         save_HDF5_to_img(h5fname, img_path="./", cmap="hot")
#pylab.show()
```



Max. AMR level of refinement map

```
from numpy import array
import pylab
from pymses.analysis.visualization import *
from pymses import RamsesOutput
from pymses.utils import constants as C
# Ramses data
ioutput = 193
ro = RamsesOutput("/data/Aquarius/output/", ioutput)
# Map operator : max. AMR level of refinement along the line-of-sight
scal_op = MaxLevelOperator()
# Map region
center = [ 0.567811, 0.586055, 0.559156 ]
axes = {"los": array([-0.172935, 0.977948, -0.117099])}
# Map processing
rt = raytracing.RayTracer(ro, ["rho"])
for axname, axis in axes.items():
       cam = Camera(center=center, line_of_sight_axis=axis, up_vector="z", region_size=[4.0E-2, 4.0E-2]
                        distance=2.0E-2, far_cut_depth=2.0E-2, map_max_size=512, log_sensitive=False
       map = rt.process(scal_op, cam)
```


```
scale = ro.info["unit_length"].express(C.Mpc)

# Save map into HDF5 file
mapname = "gas_rt_lmax_%s_%5.5i"%(axname, ioutput)
h5fname = save_map_HDF5(map, cam, map_name=mapname)

# Plot map into Matplotlib figure/PIL Image
fig = save_HDF5_to_plot(h5fname, map_unit=("AMR level",1.0), axis_unit=("Mpc", scale), cmap=
pil_img = save_HDF5_to_img(h5fname, cmap="jet", discrete=True)

# Save into PNG image file
save_HDF5_to_plot(h5fname, map_unit=("AMR level",1.0), axis_unit=("Mpc", scale), img_path="
save_HDF5_to_img(h5fname, img_path="./", cmap="jet", discrete=True)
```

#pylab.show()



Multiprocessing

If you are using python 2.6 or higher, the RayTracer will try to use multiprocessing speed up. You can desactivate it to save RAM memory and processor use by setting the multiprocessing option to False:

```
map = rt.process(scal_op, cam, multiprocessing = False)
```

1.10.3 AMRViewer GUI

Starting the GUI


PyMSES has a Graphical User Interface (GUI) module which can be used to navigate into AMR data. Once installed as described in *Installing PyMSES*, the GUI can be started with the following python prompt commands:

```
from pymses.analysis.visualization import AMRViewer
AMRViewer.run()
```

Loading AMR data

To load some data, a Ramses outputs folder has to be selected via the toolbar button or the menu.


The required output number can be specified with the output number list on the left of the main window




Playing with the camera

The camera parameters can be adjusted with the line-of-sight axis expander. You can drag-and-drop the line-of-sight axis to modify it interactively. You can also press Ctrl while dragging the axes to perform a rotation around the line-of-sight axis.

A few convenient shortcuts have been added to this menu.




There is a possibility to save and load camera parameter via the Camera menu bar.




The Region Finder

The *update view* button is the trigger to actually read and process the data. Progress can then be seen in the command prompt, until the view has been totally computed.




Navigation

The AMRViewer Region finder is made to navigate through data. Left clicks set the zoom center/zoom box size while right clicks unset them. Mouse wheel let you adjust the zoom box size.




Other map types, other tabs


Some other map types can be processed and seen through other tabs as suggested in the display menu:




1.10. Visualization tools 35




Mass weighted gas density map (see FFT-convolved maps):



Max. AMR level of refinement along the line-of-sight map (see *Ray-traced maps*):




Magnifier



1.10. Visualization tools

Rule



SOURCE DOCUMENTATION

2.1 Data structures and containers

2.1.1 pymses.core.sources — PyMSES generic data source module

```
class Source
     Bases: object
     Base class for all data source objects
     flatten()
          Read each data file and concatenate resulting dsets. This method tries to use multiprocessing if possible.
          This method uses cache_dset if this class is an instance of pymses Filter with self.remember_data==True
               Returns fdset: flattened dataset
     iter dsets()
          Datasets iterator method. Yield datasets from the datasource
     set_read_lmax (max_read_level)
          Sets the maximum AMR grid level to read in the datasource
               Parameters max read level: int
                     max. AMR level to read
class Filter (source)
     Bases: pymses.core.sources.Source
     Data source filter generic class.
     filtered_dset (dset)
          Abstract filtered_dset() method
     get_domain_dset (idomain, fields_to_read=None)
          Get the filtered result of self.source.get_domain_dset(idomain)
               Parameters idomain: int
                     number of the domain from which the data is required
               Returns dset: Dataset
                     the filtered dataset corresponding to the given idomain
     get_source_type()
               Returns type: int
```

```
the result of the get\_source\_type() method of the source param. set\_read\_lmax(max\_read\_level)
```

Source inherited behavior + apply the set_read_lmax() method to the *source* param.

Parameters max_read_level:int

max. AMR level to read

class SubsetFilter (data_sublist, source)

Bases: pymses.core.sources.Filter

SubsetFilter class. Selects a subset of datasets to read from the datasource

Parameters data sublist: list of int

list of the selected dataset index to read from the datasource

2.1.2 pymses.core.datasets — PyMSES generic dataset module

```
class Dataset
    Bases: pymses.core.sources.Source
    Base class for all dataset objects
    add_scalars (name, data)
        Scalar field addition method
```

Parameters name: string

human-readable name of the scalar field to add

data: array

raw data array of the new scalar field

add_vectors (name, data)

Vector field addition method

Parameters name: string

human-readable name of the vector field to add

data: array

raw data array of the new vector field

fields

Dictionary of the fields in the dataset

classmethod from_hdf5 (h5file, where='/', close_at_end=False)

iter dsets()

Returns an iterator over itself

write_hdf5 (h5file, where='/', close_at_end=False)

class PointDataset (points)

Bases: pymses.core.datasets.Dataset

Point-based dataset base class

add random shift()

Add a random shift to point positions in order to avoid grid alignment effect on processed images. The field "size" (from CellsToPoints Filter and IsotropicExtPointDataset) is needed to know the shift amplitude. This method is processed only once, and turn the random_shift attribute to True.

```
classmethod concatenate(dsets, reorder indices=None)
          Datasets concatenation class method. Return a new dataset
              Parameters dsets: list of PointDataset
                    list of all datasets to concatenate
                  reorder indices: array of int (default to None)
                    particles reordering indices
              Returns dset: the new created concatenated PointDataset
     filtered_by_mask (mask_array)
          Datasets filter method. Return a new dataset
              Parameters mask_array: numpy.array of numpy.bool
                    filter mask
              Returns dset: the new created filtered PointDataset
     classmethod from_hdf5 (h5file, where='/')
     reorder_points (reorder_indices)
          Datasets reorder method. Return a new dataset
              Parameters reorder indices: array of int
                    points order indices
              Returns dset: the new created reordered PointDataset
     transform(xform)
          Transform the dataset according to the given xform Transformation
              Parameters xform: Transformation
     write_hdf5 (h5file, where='/')
class IsotropicExtPointDataset (points, sizes=None)
     Bases: pymses.core.datasets.PointDataset
     Extended point dataset class
     get sizes()
              Returns sizes: array
                    point sizes array
```

2.1.3 Dataset transformations

pymses.core.transformations Geometrical transformations module

class Transformation

Bases: object

Base class for all geometric transformations acting on Numpy arrays

inverse()

Returns the inverse transformation

transform_points(coords)

Abstract method. Returns transformed coordinates.

```
Parameters:
              coords – a Numpy array with data points along axis 0 and coordinates along axis 1+
     transform_vectors (vectors, coords)
          Abstract method. Returns transformed vector components for vectors attached to the provided coordinates.
          Parameters:
              vectors – a Numpy array of shape (ndata, ndim) containing the vector components
              coords - a Numpy array of shape (ndata, ndim) containing the point coordinates
class AffineTransformation (lin_xform, shift)
     Bases: pymses.core.transformations.Transformation
     An affine transformation (of the type x \rightarrow L(x) + shift)
     inverse()
          Inverse of an affine transformation
     transform_points(coords)
          Apply the affine transformation to coordinates
     transform vectors (vectors, coords)
          Apply the affine transformation to vectors
class LinearTransformation (matrix)
     Bases: pymses.core.transformations.Transformation
     A generic (matrix-based) linear transformation
     inverse()
          Inverse of the linear transformation
     transform_points(coords)
          Applies a linear transformation to coordinates
     transform vectors (vectors, coords)
          Applies a linear transformation to vectors
class ChainTransformation (xform_seq)
     Bases: pymses.core.transformations.Transformation
     Defines the composition of a list of transformations
     inverse()
          Inverse of a chained transformation
     transform points (coords)
          Applies a chained transformation to coordinates
     transform vectors (vectors, coords)
          Applies a chained transformation to vectors
identity(n)
          Returns the identity as a LinearTransformation object :
translation (vect)
          Returns an AffineTransformation object corresponding to a translation :
              of the specified vector:
rot3d_axvector_matrix (axis_vect, angle)
     Returns the rotation matrix of the rotation with the specified axis vector and angle
```

```
rot3d_axvector (axis_vect, angle, rot_center=None)
```

Returns the Transformation corresponding to the rotation specified by its axis vector, angle, and rotation center.

If rot_center is not specified, it is assumed to be [0, 0, 0].

```
rot3d_euler (axis_sequence, angles, rot_center=None)
```

Returns the Transformation corresponding to the rotation specified by its Euler angles and the corresponding axis sequence convention.

The rotation is performed by successively rotating the object around its current local axis axis_sequence[i] with an angle angle[i], for i = 0, 1, 2.

See http://en.wikipedia.org/wiki/Euler_angles for details.

rot3d_align_vectors (source_vect, dest_vect, dest_vect_angle=0.0, rot_center=None)

Gives a Transformation which brings a given source_vect in alignment with a given dest_vect.

Optionally, a second rotation around *dest_vect* can be specified by the parameter *dest_vect_angle*.

```
Parameters source_vect: array
```

source vector coordinates array

dest_vect : array

destination vector coordinates array

dest_vect_angle : float (default 0.0)

optional final rotation angle around the dest_vect vector

Returns rot: Transformation

rotation bringing *source_vect* in alignment with *dest_vect*. This is done by rotating around the normal to the (*source_vect*, *dest_vect*) plane.

Examples

```
>>> R = rot3d_align_vectors(array([0.,0.,1.]), array([0.5,0.5,0.5]))
```

 $\verb|scale| (n, scale_factor, scale_center=None)|$

2.2 Sources module

2.2.1 pymses.sources — Source file formats package

2.2.2 pymses.sources.ramses.output — RAMSES output package

2.2.3 pymses.sources.ramses.sources — RAMSES data sources module

Bases: pymses.core.sources.Source

RAMSES generic data source

```
get_domain_dset (icpu, fields_to_read=None)
```

Data source reading method

2.2. Sources module 45

```
Parameters icpu: int
                   CPU file number to read
                 fields_to_read : list of strings
                   list of AMR data fields that need to be read: Warning: usually this information is not
                   needed here as it is already stored in self.fields to read (or in self.part read fields):
                   this option is only used internally for the remember_data cell_to_point source option
                   Warning: It is the self.readers[...].ivars descrs by file information that is used to de-
                   termine which field is really read from the file system. This information is created when
                   the source is created (the scripts line like source = RamsesOutput.amrsource(["rho"]))
              Returns dset: Dataset
                   the dataset containing the data from the given cpu number file
class RamsesAmrSource (reader_list,
                                                                                    ndim=None,
                                         dom_decomp=None,
                                                                 cpu_list=None,
                         fields_to_read=None)
     Bases: pymses.sources.ramses.sources.RamsesGenericSource
     RAMSES AMR data source class
     get_source_type()
              Returns Source.AMR SOURCE = 10 (compared to Source.PARTICLE SOURCE = 11):
class RamsesParticleSource (reader_list,
                                             dom_decomp=None,
                                                                   cpu_list=None,
                                                                                    ndim=None,
                               fields_to_read=None)
     Bases: pymses.sources.ramses.sources.RamsesGenericSource
     RAMSES particle data source class
     get_source_type()
              Returns Source.PARTICLE SOURCE = 11 (compared to Source.AMR SOURCE = 10):
2.2.4 pymses.sources.hop — HOP data sources package
2.3 Filters module
2.3.1 pymses.filters — Data sources filters package
class RegionFilter (region, source)
     Bases: pymses.core.sources.SubsetFilter
     Region Filter class. Filters the data contained in a given region of interest.
          Parameters region: Region
                 region of interest
              source: Source
                 data source
class PointFunctionFilter (mask_func, source)
     Bases: pymses.core.sources.Filter
     PointFunctionFilter class
          Parameters mask func: function
```

function evaluated to compute the data mask to apply

source: Source

PointDataset data source

class PointIdFilter (ids_to_keep, source)

Bases: pymses.core.sources.Filter

PointIdFilter class

Parameters ids_to_keep: list of int

list of the particle ids to pick up

source: Source

PointDataset data source

class PointRandomDecimatedFilter (fraction, source)

Bases: pymses.core.sources.Filter

PointRandomDecimatedFilter class

Parameters fraction: float.

fraction of the data to keep

source: Source

PointDataset data source

Bases: pymses.core.sources.Filter

AMR grid to cell list conversion filter Filters an AMR dataset and converts it into a point-based dataset

source: AMR source

include_nonactive_cells (default False): If True, the created PointDataset keeps non active cells (i.e. ghost cells)

include_boundary_cells (default False): If True, boundary cells are included

- include_split_cells (default False): If True, the created PointDataset will include all points from intermediary AMR resolution level (i.e. cells that are refined). If False, only leaf cell values are converted (this save memory and computation time for cell_to_points splatting rendering)
- smallest_cell_level integer (default None): If not None, the cells that are too small (compared to this given level of resolution) are filtered.
- **remember_data** [boolean (default False)] Option which uses a "self.cache_dset" dictionarry attribute as a cache to avoid reloading dset from disk. This uses a lot of memory as it currently remembers a active_mask by levelmax filtering for each (dataset, levelmax) couple
- cache_dset [python dictionary (default {})] Cache dsets dictionary reference, used only if remember_data == True, to share the same cache between various MapFFTProcessor. It is a dictionary of Point-Datasets created with the CellsToPoints filter, referenced by [icpu, lmax] where icpu is the cpu number and lmax is the max AMR level used.

filtered_dset (dset)

Filters an AMR dataset and converts it into a point-based dataset

Returns PointDataset source:

2.3. Filters module 47

```
class SplitCells (source, info, particle_mass)
     Bases: pymses.core.sources.Filter
     Create point-based data from cell-based data by splitting the cell-mass into uniformly-distributed particles
     filtered dset(dset)
           Split cell filtering method
               Parameters dset: Dataset
               Returns fdset: Dataset
                      filtered dataset
class ExtendedPointFilter (source, remember_data=False, cache_dset={})
     Bases: pymses.core.sources.Filter
     ExtendedParticleFilter class
     filtered_dset (dset)
           Filter a PointDataset and converts it into an IsotropicExtPointDataset with a given size for each point
2.4 Analysis module
2.4.1 Visualization module
pymses.analysis.visualization — Visualization module
class Camera (center=None, line_of_sight_axis='z', up_vector=None, region_size=[1.0, 1.0], distance=0.5,
               far cut depth=0.5, map max size=1024, log sensitive=True, perspectiveAngle=0)
     Camera class for 2D projected maps computing. Take a look at documentation figures to get a clearer definition.
           Parameters center: region of interest center coordinates (default value is [0.5, 0.5, 0.5],
                   the simulation domain center).
               line_of_sight_axis: axis of the line of sight (z axis is the default_value)
                    [ux, uy, uz] array or simulation domain specific axis key "x", "y" or "z"
               up_vector: direction of the y axis of the camera (up). If None, the up vector is set
                   to the z axis (or y axis if the line-of-sight is set to the z axis). If given a not zero-normed
                   [ux, uy, uz] array is expected (or a simulation domain specific axis key "x", "y" or "z").
               region_size: projected size of the region of interest (default (1.0, 1.0))
               distance: distance of the camera from the center of interest (along the line-of-sight
                   axis, default 0.5).
               far_cut_depth : distance of the background (far) cut plane from the center of interest
                   (default 0.5). The region of interest is within the camera position and the far cut plane.
               map_max_size : maximal resolution of the camera (default 1024 pixels)
               log_sensitive: whether the camera pixels are log sensitive or not (default True).
               perspectiveAngle: (default 0 = isometric view) angle value in degree which can be used to
                   transfom the standard pymses isometric view into a perspective view. Take a look at
```

documentation figures to get a clearer definition.

```
>>> cam = Camera(center=[0.5, 0.5, 0.5], line_of_sight_axis='z', region_size=[1., 1.], \
... distance=0.5, far_cut_depth=0.5, up_vector='y', map_max_size=512, log_sensitive=True)
```

contains_camera(cam)

Parameters An other camera object :

Returns Boolean: True if data needed for this camera view include all data

needed for the camera view given in argument.

copy()

Returns a copy of this camera.

deproject_points (uvw_points, origins=None)

Return xyz_coords deprojected coordinates of a set of points from given [u,v,w] coordinates: - (u=0,v=0, w=0) is the center of the camera. - v is the coordinate along the vaxis - w is the depth coordinate of the points along the line-of-sight of the camera. if origins is True, perform a vectorial transformation of the vectors described by uvw_points anchored at positions 'origins'

classmethod from_HDF5 (h5f)

Returns a camera from a HDF5 file.

classmethod from_csv(csv_file)

Returns a camera from a csv (Comma Separated Values) file.

```
get_3D_right_eye_cam (z_fixed_point=0.0, ang_deg=1.0)
```

Get the 3D right eye camera for stereoscopic view, which is made from the original camera with just one rotation around the up vector (angle ang_deg)

Parameters ang deg: float

angle between self and the returned camera (in degrees, default 1.0)

z_fixed_point : float

position (along w axis) of the fixed point in the right eye rotation

Returns right_eye_cam: the right eye Camera object for 3D image processing

get bounding box()

Returns the bounding box of the region of interest in the simulation domain corresponding of the area covered by the camera

get_camera_axis()

Returns the camera u, v and z axis coordinates

get_map_box (reduce_u_v_to_PerspectiveRatio=False)

Returns the (0.,0.,0.) centered cubic bounding box of the area covered by the camera Parameters ————reduce_u_v_to_PerspectiveRatio: boolean (default False)

take into account the camera.perspectiveAngle if it is defined to make a perspective projection. This reduce the map u and v (i.e.horizontal and vertical) size with the perspective ratio.

get_map_mask (float32=True)

use "float32" numpy dtype array instead of float64 to save memory (when float type is not needed, int8 type will be used anyway)

```
get_map_size()
```

```
Returns (nx, ny): (int, int) tuple
```

the size (nx,ny) of the image taken by the camera (pixels)

get_pixel_surface()

Returns the surface of any pixel of the camera

get_pixels_coordinates_edges (take_into_account_perspective=False)

Returns the edges value of the camera pixels x/y coordinates The pixel coordinates of the center of the camera is (0,0)

get_rays()

Returns ray_vectors, ray_origins and ray_lengths arrays for ray tracing ray definition

get_region_size_level()

Returns the level of the AMR grid for which the cell size ~ the region size

get_required_resolution()

Returns lev: int

the level of refinement up to which one needs to read the data to compute the projection of the region of interest with the specified resolution.

$get_slice_points(z=0.0)$

Returns the (x, y, z) coordinates of the points contained in a slice plane perpendicular to the line-of-sight axis at a given position z.

z — slice plane position along line-of-sight (default $0.0 \Rightarrow$ center of the region)

printout()

Print camera parameters in the console

project_points (points, take_into_account_perspective=False)

Return a (coords_uv, depth) tuple where 'coord_uv' is the projected coordinates of a set of points on the camera plane. (u=0,v=0) is the center of the camera plane. 'depth' is the depth coordinate of the points along the line-of-sight of the camera. Parameters ———— points: numpy array of floats

array of points(x,y,z) coordinates to project

take_into_account_perspective [boolean (default False)] take into account the camera.perspectiveAngle if it is defined to make a perspective projection.

rotate_around_up_vector (ang_deg=1.0)

save HDF5 (h5f)

Saves the camera parameters into a HDF5 file.

save csv (csv file)

Saves the camera parameters into a csv (Comma Separated Values) file.

set_perspectiveAngle (perspectiveAngle=0)

Set the perspectiveAngle (default 0 = isometric view) angle value in degree which can be used to transfom the standard pymses isometric view into a perspective view.

similar(cam)

Draftly test if a camera is roughly equal to an other one, just to know in the amrviewer GUI if we need to reload data or not.

viewing_angle_rotation()

Returns the rotation corresponding to the viewing angle of the camera

```
viewing_angle_transformation()
          Returns the transformation corresponding to the viewing angle of the camera
save_map_HDF5 (map, camera, unit=None, scale_unit=None, hdf5_path='./', map_name='my_map',
                   float32=True, save map mask=True)
     Saves the map and the camera into a HDF5 file Parameters ———— map numpy array
          map to save
     camera Pymses camera camera associated with the map to save
     unit pymses unit (default None) map unit
     scale_unit float? (default None) scale unit
     hdf5_path string (default "./") path of the hdf5 file to create
     map_name string (default "my_map") name of the map
     float32 Boolean (default True) use "float32" numpy dtype array instead of float64 to save memory
     save_map_mask Boolean (default True) save camera map_mask or not (which is used to set transparency
          when there is no intersection with the simulation domain)
save HDF5 to plot (h5fname, img path=None, axis unit=None, map unit=None, cmap='jet',
                        cmap range=None, fraction=None, save into png=True, discrete=False, ver-
                        bose=True)
     Function that plots the map with axis + colorbar from an HDF5 file
          Parameters h5fname: the name of the HDF5 file containing the map
               img_path: the path in wich the plot img file is to be saved
               axis_unit: a (length_unit_label, axis_scale_factor) tuple containing:
                 • the label of the u/v axes unit
                 • the scaling factor of the u/v axes unit, or a Unit instance
               map_unit: a (map_unit_label, map_scale_factor) tuple containing:
                 • the label of the map unit
                 • the scaling factor of the map unit, or a Unit instance
               cmap: a Colormap object or any default python colormap string
               cmap_range : a [vmin, vmax] array for map values clipping (linear scale)
               fraction: fraction of the total map values below the min. map range (in percent)
               save_into_png: whether the plot is saved into an png file or not (default True):
               discrete: wheter the map values are discrete integer values (default False). for colormap
save_HDF5_to_img (h5fname, img_path=None, cmap='jet', cmap_range=None, fraction=None, dis-
                       crete=False, ramses_output=None, ran=None, adaptive_gaussian_blur=False, draw-
                       StarsParam=None, verbose=True, log sensitive=None, alpha map mask=True)
     Function that plots, from an HDF5 file, the map into a Image and saves it into a PNG file
          Parameters h5fname: string
                   the name of the HDF5 file containing the map
               img_path : string (default value)
```

the path in wich the img file is to be saved. the image is returned (and not saved) if left to None (default value)

cmap : string or Colormap object (default "jet")

colormap to use

cmap_range : [vmin, vmax] array (default None)

value range for map values clipping (linear scale)

fraction : float (default None)

fraction of the total map values below the min. map range (in percent)

discrete: boolean (default False)

whether the colormap must be integer values only or not.

ramses_output: Ramses_output

specify ramses output for additional csv star file (look for a "sink_%iout.csv" file with 3D coordinates in output directory) to add stars on the image

ran: boolean or (float, float) (default None)

specify map range value to fix colormap during a movie sequence (same as the "Colormap range" values printed in console when verbose=True)

adaptive_gaussian_blur: boolean (default False)

experimental: compute local image resolution and apply an adaptive gaussian blur to the image where it is needed (usefull to avoid AMR big pixels with ray tracing technique) For rotated view: give the levelmax map in this parameter to get the good local image resolution

drawStarsParam : DrawStarsParameters (default None)

if ramses_output is specified and if a star file is found, this may be used to specify some parameters

verbose: boolean (default True)

if True, print colormap range in console.

log_sensitive : boolean (default None)

apply logarithmic value, if not precise, this code use the hdf5 camera.log_sensitive value to decide

alpha map mask: boolean (default True)

use the camera map_mask for the alpha band : ray that doesn't intersect the simulation domain are see-through (alpha = 0)

Returns:

img: PIL Image

if *img_path* is left to None

ran = (vmin, vmax):

if *img_path* is specified: return the Colormap range that can be used as a ran parameter for future images

```
save_HDF5_seq_to_img(h5f_iter, *args, **kwargs)
     fraction: fraction (percent) of the total value of the map above the returned vmin value (default 1%)
get_map_range (map, log_sensitive=False, cmap_range=None, fraction=None)
     Map range computation function. Computes the linear/log (according to the map values scaling) scale map
     range values of a given map:
          •if a user-defined cmap range is given, then it is used to compute the map range values
          •if not, the map range values is computed from a fraction (percent) of the total value of the map parameter.
          the min. map range value is defined as the value below which there is a fraction of the map (default 1 %)
           Parameters map: 2D map from wich the map range values are computed
               log_sensitive: whether the map values are log-scaled or not (True or False)
               cmap_range : user-defined map range values (linear scale)
               fraction: fraction of the total map values below the min. map range (in percent)
           Returns map_range: [float, float]
                   the map range values [min, max]
apply_log_scale (map, verbose=True)
     Used to apply log-scale map if the camera captors are log-sensitive. Takes care of null and negative values
     warning
           Parameters map: original numpy array of map values
           Returns map: ~ numpy.log10(map) (takes care of null and negative values)
                                                                          255,
class DrawStarsParameters (adapt_intensity=True,
                                                           rgb = [255,
                                                                                   255],
                                                                                             PSF=True,
                                 RT_instensity_dimming=False)
     Utility class to store parameters for the draw_stars function
           Parameters adapt_intensity:boolean
                   Whether to adpat the intensity or not with the sink csv 4th colum
               rgb: [R, G, B] list of int
                   list of 3 integers between 0 and 255 corresponding to a RGB color
               PSF: boolean or Colormap object
                   colormap to use
               RT_instensity_dimming: boolean
                   experimental: this option add a ray tracing pass on data to compute star intensity dim-
                   ming
class Operator (scalar func dict, is max alos=False, use cell dx=False)
     Base Operator generic class
class ScalarOperator (scalar_func)
     ScalarOperator class
           Parameters scalar_func: function
```

single *dset* argument function returning the scalar data array from this *dset* Dataset.

Examples

$$I = \frac{\int\limits_{V} \rho \times \rho dV}{\int\limits_{V} \rho dV}$$

class MaxLevelOperator

Max. AMR level of refinement operator class

SliceMap (source, camera, op, z=0.0, interpolation=False, use_C_code=True, use_openCL=False, verbose=False)

Compute a map made of sampling points

Parameters source: Source

data source

camera: Camera

camera handling the view parameters

 ${\bf op}: {\tt Operator}$

data sampling operator

z:float

position of the slice plane along the line-of-sight axis of the camera

interpolation : boolean (default False)

Experimental: A proper bi/tri-linear interpolation could be great! THIS IS NOT IM-PLEMENTED YET: in this attempt we supposed corner cell data while ramses use centered cell data, letting alone the problem of different AMR level...

use_C_code : boolean (default True)

```
The pure C code is slightly faster than the (not well optimized) Cython code, and should
                 give the same result
             use openCL: boolean (default False)
                 Experimental: use "pyopencl" http://pypi.python.org/pypi/pyopencl
             verbose: boolean (default False)
                 some console printout...
             Returns:
             map: array
                 sliced map
pymses.analysis.visualization.fft projection — FFT-convolved map module
class MapffTProcessor (source, info, ker_conv=None, pre_flatten=False, remember_data=False,
                        cache_dset={}, use_camera_lvlmax=True)
     data source
     info [dict] RamsesOutput info dict.
     ker conv [:class: ~pymses.analysis.visualization.ConvolKernel' (default None leads to use a GaussSplatterK-
```

ker_conv [:class: ~pymses.analysis.visualization.ConvolKernel' (default None leads to use a GaussSplatterK-ernel)] Convolution kernel used for the map processing

pre_flatten [boolean (default False)] Option to flatten the data source (using multiprocessing if possible) before computing the map The filtered data are then saved into the "self.filtered_source" source attribute.

remember_data [boolean (default False)] Option which uses a "self.cache_dset" dictionarry attribute as a cache to avoid reloading dset from disk. This uses a lot of memory as it currently remembers a active_mask by levelmax filtering for each (dataset, levelmax) couple

cache_dset [: python dictionary (default {})] Cache dsets dictionnary reference, used only if remember_data == True, to share the same cache between various MapFFTProcessor. It is a dictionary of Point-Datasets created with the CellsToPoints filter, referenced by [icpu, lmax] where icpu is the cpu number and lmax is the max AMR level used.

use_camera_lvlmax [boolean (default True)] Limit the transformation of the AMR grid to particles to AMR cells under the camera octree levelmax (so that visible cells are only the ones that have bigger size than the camera pixel size). Set this to False when using directly particle data from ".part" particles files (dark matter and stars particles), so as to get the cache_dset working without the levelmax specification

```
prepare_data(camera, field_list=None)
```

camera containing all the view params, the filtering is done according to those param

field_list list of strings list of AMR data fields needed to be read

```
Parameters op: Operator
                     physical scalar quantity data operator
                   camera: Camera
                     camera containing all the view params
                   surf qty: boolean (default False)
                     whether the processed map is a surface physical quantity. If True, the map is divided by
                     the surface of a camera pixel.
                   multiprocessing: boolean (default True)
                     try to use multiprocessing to compute both of the FractionOperator's "top" and "down"
                     FFT maps in parallel
                   FFTkernelSizeFactor: int or float (default 1)
                     allow to change the convolution kernel size by a multiply factor to adjust points size
                   data_already_prepared: boolean (default False)
                     set this option to true if you have already called the prepare_data() method: this method
                     will then simply used it's "self.filtered_source" source attribute without computing it
                     again
                   random_shift : boolean (default False)
                     add a random shift to point positions to avoid seeing the grid on resulting image
                   stars_age_instensity_dimming : boolean (default False)
                     Requires the "epoch" field. Make use of this formula: if star_age < 10 Million
                       years (Myr): intensity_weights = operator_weights (young stars are normally bright)
                       else: intensity_weights = operator_weights * [star_age/10**6 Myr]**-0.7 (intensity
                       dimming with years old)
               Returns map: array
                     FFT-convolved processed map
class ConvolKernel (ker_func, size_func=None, max_size=None)
     Convolution kernel class
     convol_fft (map_dict, cam_dict)
           FFT convolution method designed to convolute a dict. of maps into a single map
           map_dict: map dict. where the dict. keys are the size of the convolution kernel. cam_dict: Extended-
           Camera dict. corrsponding to the different maps of the map dict.
     get size(dset)
class GaussSplatterKernel (size_func=None, max_size=None)
     2D Gaussian splatter convolution kernel
class Gauss1DSplatterKernel (axis, size_func=None, max_size=None)
     2D Gaussian splatter convolution kernel
class PyramidSplatterKernel (size_func=None, max_size=None)
     2D pyramidal splatter convolution kernel
class Cos2SplatterKernel (size_func=None, max_size=None)
     2D Squared cosine splatter convolution kernel
```

pymses.analysis.visualization.raytracing — Ray-tracing module class RayTracer (ramses_output, field_list) RayTracer class Parameters ramses_output: RamsesOutput ramses output from which data will be read to compute the map field_list: list of string list of all the required AMR fields to read (see amr_source()) camera, surf_qty=False, verbose=True, multiprocessing=True, source=None, use_hilbert_domain_decomp=True, use_C_code=True, use_bottom_up=False) Map processing method: ray-tracing through data cube Parameters op: Operator physical scalar quantity data operator camera: Camera camera containing all the view params surf qty: boolean (default False) whether the processed map is a surface physical quantity. If True, the map is divided by the surface of a camera pixel. verbose: boolean (default False) show more console printouts multiprocessing : boolean (default True) try to use multiprocessing (process cpu data file in parallel) to speed up the code (need more RAM memory, python 2.6 or higher needed) **source** : class:~*pymses.sources...* (default None) Optional: The source to process may be specified here if you want to reuse a CameraOctreeDatasource already loaded in memory for example (see pymses/bin/pymses_tf_ray_tracing.py) use hilbert domain decomp: boolean (default True) If False, iterate on the whole octree for each cpu file(instead of iterating on the cpu minimal domain decomposition, which is faster) use_C_code : boolean (default True) Our pure C code is faster than the (not well optimized) Cython code, and should give the same result use_bottom_up : boolean (default False) Force the use of the bottom-up algorithm instead of the classic top-down on the octree. Use the "neighbors" array. DOESN'T WORK YET class OctreeRayTracer (*args) RayTracerDir class Parameters ramses output: RamsesOutput ramses output from which data will be read to compute the map

field list: list of string

```
list of all the required AMR fields to read (see amr_source())
     process (op,
                       camera,
                                 surf_qty = False,
                                                   return\_image=True, rgb=True,
                                                                                      use C code=True,
                 use openCL=False, dataset already loaded=False, reload scalar field=False)
           Map processing method: directional ray-tracing through AMR tree
           Parameters op: Operator
               physical scalar quantity data operator
           camera [Camera] camera containing all the view params
           surf_qty [boolean (default False)] whether the processed map is a surface physical quantity. If True,
               the map is divided by the surface of a camera pixel.
           return_image [boolean (default True)] if True, return a PIL image (when rgb option is also True), else
               it returns a numpy array map
           rgb [boolean (default True)] if True, this code use the camera.color_tf to compute a rgb image if False,
               this code doesn't use the camera.color_tf, and works like the standard RayTracer. Then it returns two
               maps: the requested map, and the AMR levelmax map
           use_C_code [boolean (default True)] Our pure C code is faster than the (not well optimized) Cython
               code, and should give the same result
           use openCL [boolean
                                        (default
                                                    False)]
                                                               Experimental
                                                                                           use
                                                                                                   "pyopencl"
               http://pypi.python.org/pypi/pyopencl
           dataset_already_loaded [boolean (default False)] Flag used with use_openCL=True to avoid reload-
               ing a dataset on the device
           reload scalar field [boolean
                                            (default
                                                      False)]
                                                               Flag
                                                                       used
                                                                              with
                                                                                      use openCL=True
               dataset_already_loaded=True to avoid reloading the dataset structure on the device while using
               a different scalar field
class RayTracerMPI (ramses_output, field_list, remember_data=False)
     RayTracer class
           Parameters ramses_output: RamsesOutput
                   ramses output from which data will be read to compute the map
               field_list: list of string
                   list of all the required AMR fields to read (see amr source())
               remember data: boolean (default False)
                   option to remember dataset loaded. Avoid reading the data again for each frame of a
                   rotation movie. WARNING: The saved cache data don't update yet it's levelmax and
                   cpu list, so use carefully this
                     if zooming / moving too much inside the simulation box.
     process (op, camera, surf_qty=False, use_balanced_cpu_list=False, testing_ray_number_max=100,
                 verbose=False, use C code=True)
           Map processing method using MPI: ray-tracing through data cube
               Parameters op: Operator
                     physical scalar quantity data operator
                   camera: Camera
                     camera containing all the view params
```

```
surf_qty : boolean (default False)
```

whether the processed map is a surface physical quantity. If True, the map is divided by the surface of a camera pixel.

use_balanced_cpu_list : boolean (default False)

option to optimize the load balancing between MPI process, add an intial dsets testing before processing every rays

testing_ray_number_max: boolean (default 100)

number of testing ray for the balanced cpu list option

verbose: boolean (default False)

more printout (may flood the console out for big simulation with many cpu)

use_C_code : boolean (default True)

Our pure C code is faster than the (not well optimized) Cython code, and should give the same result

2.4.2 pymses.analysis — Analysis and post-processing package

Parameters amr source: RamsesAmrSource

data description

points : (npoints, ndim) array

sampling points coordinates

add_level : boolean (default False)

whether we need to add a *level* field in the returned dataset containing the value of the AMR level the sampling points fall into

add_cell_center : boolean (default False)

whether we need to add a *cell_center* field in the returned dataset containing the coordinates of the AMR cell center the sampling points fall into

interpolation : boolean (default False)

Experimental: A proper bi/tri-linear interpolation could be great! THIS IS NOT IM-PLEMENTED YET: in this attempt we supposed corner cell data while ramses use centered cell data, letting alone the problem of different AMR level...

use_C_code : boolean (default True)

The pure C code is slightly faster than the (not well optimized) Cython code, and should give the same result

use_openCL : boolean (default False)

Experimental: use "pyopencl" http://pypi.python.org/pypi/pyopencl

verbose: boolean (default False)

some console printout...

Returns dset: PointDataset

```
Contains all these sampled values.
bin_cylindrical (source, center, axis_vect, profile_func, bin_bounds, divide_by_counts=False)
      Cylindrical binning function for profile computing
           Parameters center: array
                   center point for the profile
               axis_vect: array
                   the cylinder axis coordinates array.
               profile_func: function
                   a function taking a PointDataset object as an input and producing a numpy array
                   of weights.
               bin_bounds: array
                   a numpy array delimiting the profile bins (see numpy.histogram documentation)
               divide_by_counts : boolean (default False)
                   if True, the returned profile is the array containing the sum of weights in each bin. if
                   False, the mean weight per bin array is returned.
           Returns profile: array
                   computed cylindrical profile
bin_spherical (source, center, profile_func, bin_bounds, divide_by_counts=False)
      Spherical binning function for profile computing
           Parameters center: array
                   center point for the profile
               profile_func: function
                   a function taking a PointDataset object as an input and producing a numpy array
                   of weights.
               bin bounds: array
                   a numpy array delimiting the profile bins (see numpy.histogram documentation)
               divide_by_counts: boolean (default False)
                   if True, the returned profile is the array containing the sum of weights in each bin. if
                   False, the mean weight per bin array is returned.
           Returns profile: array
                   computed spherical profile
average_point (source, weight_func=None, returned=False)
      Return the average point coordinates of a PointDataSource assuming an optional weight function
           Parameters source : PointDataSource
                   the PointDataSource from which the average point is computed
               weight_func: function, optional
                   function used to give a weight for each point of the PointDataSource. Takes a Dataset
                   for single argument and returns the weight value for each point
```

```
returned: boolean, optional (default False)
                   if True, the sum of the weights is also returned
           Returns av_pos: array
                   coordinates of the barycenter
               sow: float
                   returned only if returned was True. Sum of the weights
amr2cube (source, var, xmin, xmax, cubelevel, out=None)
     amr2cube tool.
```

2.5 Utilities package

2.5.1 Dimensional physical constants

```
pymses.utils.constants — physical units and constants module
```

```
class Unit (dims, val)
     Bases: object
```

Dimensional physical unit class

```
Parameters dims: 6-tuple of int
```

dimension of the unit object expressed in the international system units (m, kg, s, K, h, T)

val: float

value of the unit object (in ISU)

Examples

```
>>> V_{km_s} = Unit((1,0,-1,0,0), 1000.0)
>>> print "1.0 km/s = %.1e m/h"%(V_km_s.express(m/hour))
1.0 \text{ km/s} = 3.6e + 0.6 \text{ m/h}
```

express(unit)

Unit conversion method. Gives the conversion factor of this Unit object expressed into another (dimension-compatible) given unit.

Checks that:

•the *unit* param. is also a Unit instance

•the *unit* param. is dimension-compatible

Parameters unit: Unit object

unit in which the conversion is made

Returns fact: float

conversion factor of itself expressed in unit

```
Conversion of a kpc expressed in light-years:
          >>> factor = kpc.express(ly)
          >>> print "1 kpc = %f ly"%factor
          1 \text{ kpc} = 3261.563163 \text{ ly}
          Conversion of 1M_{\odot} into kilometers :
          >>> print Msun.express(km)
          ValueError: Incompatible dimensions between (1.9889e+30 kg) and (1000.0 m)
list all()
     Print all available constants list:
     none, m, cm, km, pc, au, kpc, Mpc, Gpc, kg, g, mH, Msun, s, hour, day, year, Myr, Gyr, N, dyne, K,
     J, W, erg, eV, G, kB, c, ly, H, rhoc, H_cc, h, sigmaSB, a_R, T, Gauss, uGauss
2.5.2 Geometrical region module
pymses.utils.regions — Regions module
class Region
     Generic region class
     contains (points)
              Parameters points: float array of 3D points coordinates
              Returns points: boolean array
                    True when points coordinates are inside the region
     random_points (npoints, ensure_exact_count=True)
          Generates a set of randomly distrubuted points in the region
              Parameters npoints: int
                    number of points to generate
                  ensure_exact_count : boolean (default True)
                    whether the exact required number of random points are generated or not
              Returns points: array
                    ramdom points array
class Sphere (center, radius)
     Bases: pymses.utils.regions.Region
     Spherical region class
          Parameters center: 3-tuple of float
                 sphere center coordinates
              radius: float
                  radius of the sphere
```

```
>>> sph = Sphere((0.5, 0.5, 0.5), 1.0)
     contains (points)
          TODO
     get_bounding_box()
          TODO
     get_volume()
              Returns V: float
                    volume of the sphere (radius r) given by V = \frac{4}{3}\pi r^3
class SphericalShell (center, radius_in, radius_out)
     Bases: pymses.utils.regions.Region
     Spherical shell class
          Parameters center: 3-tuple of float
                  spherical shell center coordinates
              radius in: float
                  radius of the innerr sphere
              radius_out: float
                  radius of the outer sphere
     Examples
     >>> sph_shell = SphericalShell((0.5, 0.5, 0.5), 0.5, 0.6)
     contains (points)
          TODO
     get_bounding_box()
          TODO
     get_volume()
              Returns V: float
                    volume of the spherical shell (r_{in} < r < r_{out}) given by V = \frac{4}{3}\pi(r_{out}^3 - r_{in}^3)
class Box (bounds)
     Bases: pymses.utils.regions.Region
     Box region class
          Parameters bounds: 2-tuple of list
                  box region boundary min and max positions as a (min, max) tuple of coordinate
                  arrays
```

```
>>> min_coords = [0.1, 0.2, 0.25]
     \rightarrow >  max_coords = [0.9, 0.8, 0.75]
     >>> b = Box((min_coords, max_coords))
     get_bounding_box()
              Returns (min_coords, max_coords): 2-tuple of list
                    bounding box limit
     get_volume()
              Returns V: float
                    volume of the box given by V = \prod (\operatorname{cmax}_i - \operatorname{cmin}_i)
     printout()
          Print bounding box limit in console
class Cube (center, width)
     Bases: pymses.utils.regions.Box
     Cubic region class
          Parameters center: tuple
                  cube center coordinates
              width: float
                  size of the cube
     Examples
     >>> cu = Cube((0.5, 0.5, 0.5), 1.0)
     get_volume()
              Returns V: float
                    volume of the cube (size L) given by V = L^{\text{ndim}}
class Cylinder (center, axis vector, radius, height)
     Bases: pymses.utils.regions.Region
     Cylinder region class
          Parameters center: 3-tuple of float
                  cylinder center coordinates
              axis_vector : 3-tuple of float
                  cylinder axis vector coordinates
              radius: float
                  cylinder radius
              height: float
                  cylinder height
```

```
>>> center = (0.5, 0.5, 0.5)
>>> axis = (0.1, 0.9, -0.1)
>>> radius = 0.3
>>> h = 0.05
>>> cyl = Cylinder(center, axis, radius, h)

contains(points)
    TODO

get_bounding_box()
    TODO

get_volume()

    Returns V: float
    volume of the cylinder (radius r, height h) given by V = πr²h
```

PYTHON MODULE INDEX

р

```
pymses.analysis, 59
pymses.analysis.amrtocube, 61
pymses.analysis.avg_point, 60
pymses.analysis.point_sampler, 59
pymses.analysis.profile_binners, 60
pymses.analysis.visualization, 48
pymses.analysis.visualization.fft_projection,
pymses.analysis.visualization.raytracing,
pymses.core.datasets, 42
pymses.core.sources,41
pymses.core.transformations, 43
pymses.filters,46
pymses.sources, 45
pymses.sources.hop, 46
pymses.sources.ramses.output, 45
pymses.sources.ramses.sources,45
pymses.utils.constants,61
pymses.utils.regions, 62
```

68 Python Module Index

INDEX

A	D
add_random_shift() (PointDataset method), 42	Dataset (class in pymses.core.datasets), 42
add_scalars() (Dataset method), 42	deproject_points() (Camera method), 49
add_vectors() (Dataset method), 42	DrawStarsParameters (class in pym-
AffineTransformation (class in pym-	ses.analysis.visualization), 53
ses.core.transformations), 44	_
amr2cube() (in module pymses.analysis.amrtocube), 61	E
apply_log_scale() (in module pym-	express() (Unit method), 61
ses.analysis.visualization), 53	ExtendedPointFilter (class in pymses.filters), 48
average_point() (in module pymses.analysis.avg_point),	F
60	F
В	fields (Dataset attribute), 42
	Filter (class in pymses.core.sources), 41
bin_cylindrical() (in module pym-	filtered_by_mask() (PointDataset method), 43
ses.analysis.profile_binners), 60	filtered_dset() (CellsToPoints method), 47
bin_spherical() (in module pym- ses.analysis.profile_binners), 60	filtered_dset() (ExtendedPointFilter method), 48
Box (class in pymses.utils.regions), 63	filtered_dset() (Filter method), 41
Dox (class in pythises.utils.regions), 03	filtered_dset() (SplitCells method), 48
C	flatten() (Source method), 41
Camera (class in pymses.analysis.visualization), 48	FractionOperator (class in pymses.analysis.visualization), 54
CellsToPoints (class in pymses.filters), 47	from_csv() (pymses.analysis.visualization.Camera class
ChainTransformation (class in pym-	method), 49
ses.core.transformations), 44	from_HDF5() (pymses.analysis.visualization.Camera
concatenate() (pymses.core.datasets.PointDataset class	class method), 49
method), 43	from_hdf5() (pymses.core.datasets.Dataset class
contains() (Cylinder method), 65	method), 42
contains() (Region method), 62	from_hdf5() (pymses.core.datasets.PointDataset class
contains() (Sphere method), 63	method), 43
contains() (SphericalShell method), 63	0
contains_camera() (Camera method), 49	G
convol_fft() (ConvolKernel method), 56	Gauss1DSplatterKernel (class in pym-
ConvolKernel (class in pym-	ses.analysis.visualization.fft_projection),
ses.analysis.visualization.fft_projection),	56
56	GaussSplatterKernel (class in pym-
copy() (Camera method), 49 Cos2SplatterKernel (class in pym-	ses.analysis.visualization.fft_projection),
Cos2SplatterKernel (class in pymses.analysis.visualization.fft_projection),	56
56	get_3D_right_eye_cam() (Camera method), 49
Cube (class in pymses.utils.regions), 64	get_bounding_box() (Box method), 64
Cylinder (class in pymses.utils.regions), 64	get_bounding_box() (Camera method), 49 get_bounding_box() (Cylinder method), 65
	get_bounding_box() (Cylinder method), 03

get_bounding_box() (Sphere method), 63	Operator (class in pymses.analysis.visualization), 53
get_bounding_box() (SphericalShell method), 63	P
get_camera_axis() (Camera method), 49	
get_domain_dset() (Filter method), 41	PointDataset (class in pymses.core.datasets), 42
get_domain_dset() (RamsesGenericSource method), 45	PointFunctionFilter (class in pymses.filters), 46
get_map_box() (Camera method), 49	PointIdFilter (class in pymses.filters), 47
get_map_mask() (Camera method), 49	PointRandomDecimatedFilter (class in pymses.filters), 47
get_map_range() (in module pym-	prepare_data() (MapFFTProcessor method), 55
ses.analysis.visualization), 53	printout() (Box method), 64
get_map_size() (Camera method), 49	printout() (Camera method), 50
get_pixel_surface() (Camera method), 50	process() (MapFFTProcessor method), 55
get_pixels_coordinates_edges() (Camera method), 50	process() (OctreeRayTracer method), 58
get_rays() (Camera method), 50	process() (RayTracer method), 57
get_region_size_level() (Camera method), 50	process() (RayTracerMPI method), 58
get_required_resolution() (Camera method), 50	project_points() (Camera method), 50
get_size() (ConvolKernel method), 56	pymses.analysis (module), 59
get_sizes() (IsotropicExtPointDataset method), 43 get_slice_points() (Camera method), 50	pymses.analysis.amrtocube (module), 61
get_source_type() (Filter method), 41	pymses.analysis.avg_point (module), 60
get_source_type() (RamsesAmrSource method), 46	pymses.analysis.point_sampler (module), 59
get_source_type() (RamsesAnnisource method), 46 get_source_type() (RamsesParticleSource method), 46	pymses.analysis.profile_binners (module), 60
get_source_type() (Ramsesi arteresource method), 40 get_volume() (Box method), 64	pymses.analysis.visualization (module), 48
get_volume() (Cube method), 64	pymses.analysis.visualization.fft_projection (module), 55
get_volume() (Cylinder method), 65	pymses.analysis.visualization.raytracing (module), 56
get_volume() (Sphere method), 63	pymses.core.datasets (module), 42
get_volume() (SphericalShell method), 63	pymses.core.sources (module), 41 pymses.core.transformations (module), 43
Set_verame() (Sphericalismen memos), es	pymses.filters (module), 46
	pymses.sources (module), 45
identity() (in module pymses.core.transformations), 44	pymses.sources.hop (module), 46
inverse() (AffineTransformation method), 44	pymses.sources.ramses.output (module), 45
inverse() (ChainTransformation method), 44	pymses.sources.ramses.sources (module), 45
inverse() (LinearTransformation method), 44	pymses.utils.constants (module), 61
inverse() (Transformation method), 43	pymses.utils.regions (module), 62
IsotropicExtPointDataset (class in pymses.core.datasets),	PyramidSplatterKernel (class in pym-
43	ses.analysis.visualization.fft_projection),
iter_dsets() (Dataset method), 42	56
iter_dsets() (Source method), 41	
	R
L	RamsesAmrSource (class in pym-
LinearTransformation (class in pym-	ses.sources.ramses.sources), 46
ses.core.transformations), 44	RamsesGenericSource (class in pym-
list_all() (in module pymses.utils.constants), 62	ses.sources.ramses.sources), 45
iss_un() (in module pj msesiumstensums), ez	RamsesParticleSource (class in pym-
M	ses.sources.ramses.sources), 46
MapFFTProcessor (class in pym-	random_points() (Region method), 62
ses.analysis.visualization.fft_projection),	RayTracer (class in pym-
55	ses.analysis.visualization.raytracing), 57
MaxLevelOperator (class in pym-	RayTracerMPI (class in pym-
ses.analysis.visualization), 54	ses.analysis.visualization.raytracing), 58
Sectionary 5151. 115 dailed to 117, 5-1	Region (class in pymses.utils.regions), 62
0	RegionFilter (class in pymses.filters), 46
OctreeRayTracer (class in pym-	reorder_points() (PointDataset method), 43
OctreeRayTracer (class in pym- ses.analysis.visualization.raytracing), 57	rot3d_align_vectors() (in module pym-
ses.anarysis.visuanzation.raytracing), 3/	ses.core.transformations), 45

70 Index

```
rot3d axvector()
                                                         viewing angle transformation() (Camera method), 50
                        (in
                                   module
         ses.core.transformations), 44
rot3d axvector matrix()
                             (in
                                     module
                                                  pym-
         ses.core.transformations), 44
                                                         write hdf5() (Dataset method), 42
rot3d_euler() (in module pymses.core.transformations),
                                                         write hdf5() (PointDataset method), 43
rotate around up vector() (Camera method), 50
S
sample_points()
                                  module
                       (in
                                                  pym-
         ses.analysis.point sampler), 59
save csv() (Camera method), 50
save_HDF5() (Camera method), 50
save_HDF5_seq_to_img()
                              (in
                                     module
                                                  pym-
         ses.analysis.visualization), 52
save_HDF5_to_img()
                           (in
                                    module
                                                  pym-
         ses.analysis.visualization), 51
save_HDF5_to_plot()
                                    module
                           (in
                                                  pym-
         ses.analysis.visualization), 51
save_map_HDF5()
                         (in
                                   module
                                                  pym-
         ses.analysis.visualization), 51
ScalarOperator (class in pymses.analysis.visualization),
scale() (in module pymses.core.transformations), 45
set perspectiveAngle() (Camera method), 50
set_read_lmax() (Filter method), 42
set_read_lmax() (Source method), 41
similar() (Camera method), 50
SliceMap() (in module pymses.analysis.visualization), 54
Source (class in pymses.core.sources), 41
Sphere (class in pymses.utils.regions), 62
SphericalShell (class in pymses.utils.regions), 63
SplitCells (class in pymses.filters), 47
SubsetFilter (class in pymses.core.sources), 42
Т
transform() (PointDataset method), 43
transform_points() (AffineTransformation method), 44
transform points() (ChainTransformation method), 44
transform points() (LinearTransformation method), 44
transform points() (Transformation method), 43
transform_vectors() (AffineTransformation method), 44
transform vectors() (ChainTransformation method), 44
transform vectors() (LinearTransformation method), 44
transform vectors() (Transformation method), 44
Transformation (class in pymses.core.transformations),
translation() (in module pymses.core.transformations), 44
U
Unit (class in pymses.utils.constants), 61
V
```

Index 71

viewing angle rotation() (Camera method), 50