

REHEARSAL WALK

Shaper Assistant · the live site, www.shaperassistant.com · sheet of Saturday 3 October 2026. It replaces the 30 September sheet: the site has changed since (the ghost, Undo and Redo, the thin sideways bar, the blank corrections, Phase 14's curves and Thinning Starts).

DONE ON 3 OCT

1 Google sign-in open to everyone ✓ · 2 Room for a crowd ✓ · 3 A new email sign-up on a phone ✓ · 7 A friend's Google sign-up ✓

STILL TO DO

4 iPhone walk · 5 Android walk · 6 Laptop walk · 8 Demo account · 9 The freeze, Wednesday 7 October evening

HOW TO MARK

Tick a box for a pass. For a fail, put a cross and write what happened in your own words; that sentence becomes the fix. About 25 minutes a device. Use Google to sign in on one device and email on another.

NEVER WRITE DOWN

Anything you typed into a sign-in form: no email address, password or code, and no screenshot showing one. Only whether it worked.

KNOWN BEFORE YOU WALK (FOUND BY MACHINE ON 3 OCT)

On a phone held upright, the tail's Automatic button on **ROCKER** (step 6) sits under the Redo button and can't be tapped. Undo takes a tail start back; turning the phone sideways reaches the button. A fix is waiting on your word.

THE WALK · STEPS 1 TO 9

#	DO THIS	LOOK FOR	IPHONE	ANDROID	LAPTOP
1	Text yourself www.shaperassistant.com and tap the link (laptop: type the address)	The preview card with the board picture and "Shaper Assistant — Surfboard Shaping and Design"; the home screen opens	☐	☐	☐
2	Read the four preset cards	Shortboard 6'2" · 18 3/4" · 2 1/4" · 29.6 L Fish 5'8" · 20 1/4" · 2 1/2" · 35.3 L Mid-length 7'2" · 21 1/4" · 2 3/4" · 50.4 L Longboard 9'0" · 22 1/2" · 3" · 75.3 L	☐	☐	☐
3	Sign in with your own account (phones: in the menu, top right; laptop: Sign in, in the top bar)	The keyboard never hides the field you're typing in; any code arrives within a minute; you land back signed in	☐	☐	☐
4	Start Shaping on a preset → TEMPLATE : drag an outline point, then Undo and Redo	The point follows your finger or mouse and the numbers update; the Undo and Redo pair appears at the bottom right and puts it back exactly; a faint line shows the shape before the change, and the ghost button in the drawing's corner hides it	☐	☐	☐
5	ROCKER : press Change Blank and pick another blank, slide Placement, drag Deck Skin	The list opens, shortest first, with greyed blanks saying where they don't fit; the picked blank, the drawing, the foam-off numbers and the planer passes follow you	☐	☐	☐
6	NEW ROCKER , at the end of the controls: drag Nose Thinning Starts and Tail Thinning Starts, then press Automatic on each	The label follows the drag (12" to 13"), the hint reads "Automatic would be 12"" and the dashed mark on the drawing moves; Automatic puts it back and the hint reads "Picked automatically"; the DATASHEET tab shows THINNING STARTS . <i>Phone held upright: the tail's Automatic is under the Redo button — see the box above</i>	☐	☐	☐
7	RAILS : View Full Sized, then each tab including INSTRUCTIONS , where you flip Flat / Domed	Nothing cut off; View Full Sized opens and Close shuts it	☐	☐	☐
8	VOLUME : note the litres; change width or thickness on TEMPLATE ; come back	The litres change and read sensibly	☐	☐	☐
9	FINS : change the fin setup; tick and untick Import Template Values	The fin numbers and the drawing follow	☐	☐	☐

THE WALK · STEPS 10 TO 17

#	DO THIS	LOOK FOR	IPHONE	ANDROID	LAPTOP
10	SUMMARY: read the order form, then Print Order Form — print for real or save as a PDF	Both pages complete and legible. Page 2's Planing box ends "Thinning starts from the tip: nose ..., tail" inside its box. On the iPhone, page 2's rail markings and fin numbers each sit inside their own box	☐	☐	☐
11	SUMMARY: Export Template → Overview Sheet → Download PDF	A PDF of the board opens or downloads	☐	☐	☐
12	Save (top bar) with a name → tap the wordmark for home → open the board from Your Boards → rename it, duplicate it, delete the copy	The same board comes back, with its blank and any Thinning Start you set by hand; Cancel is easy to hit on the delete question	☐	☐	☐
13	Menu (gear on the laptop) → Metric; look at ROCKER and SUMMARY; switch back to Imperial	Centimetres for sizes, millimetres for marks; Thinning Starts read in centimetres (30.5 cm for 12"); back in Imperial every number is exactly what it was	☐	☐	☐
14	Menu → Contact, then Privacy. Send one Contact message from one device only	Both pages open; the message reaches support@ in Zoho	☐	☐	☐
15	Type a wrong address, e.g. www.shaperassistant.com/xyz	"We couldn't find that page", with a way home	☐	☐	☐
16	Phones: turn sideways on a design screen, then upright again	Sideways the top bar stays one thin line (wordmark, Save, menu) with the six screens in the menu, and the controls sit beside the board; no sideways scrolling; upright stacks them again	☐	☐	N/A
17	Sign out, then sign back in	Your boards are all still there	☐	☐	☐

Laptop extras: use the browser you'll present from. If a projector or TV will be used, walk at least steps 2 to 10 on it and pick the theme that reads best from the back of the room. Print one order form on a real printer.

PHASE 14'S FIVE LOOKS · SAME SITTING

	ON	DO THIS	WHAT GOOD IS	OK
A	A phone, then the laptop	In Metric on ROCKER, drag each Thinning Starts slider to both ends. On the laptop, click a slider that is on Automatic and press the arrow keys	On the Shortboard the ends read 16.0 cm and 93.0 cm and nothing jumps. A start set at 6" in Imperial reads 15.2 cm in Metric with the thumb at the left end. From 30.5 cm the right arrow steps to 31.0 and 32.0 and the left arrow back, with no jump on the first press	☐
B	Paper	Print page 2 of the order form with a blank picked: on Letter, on A4 if you have it, and from a phone	The Planing box ends "Thinning starts from the tip: nose 12", tail 12". (in Metric, "nose 30.5, tail 30.5 cm."), on two lines at most, inside its box	☐
C	Both phones	With Change Blank's list open, drag a Thinning Starts slider, slide Placement end to end and change a tip setting	The list and the fit flag keep up; no stutter or freeze	☐
D	The laptop	In each of the four themes, look at ROCKER's drawing with a blank picked and both starts at 12"	The faint dashed mark can be picked out where it meets the 12" line. At go-live 2 you found it hard to pick out on a computer and asked for no change; confirm that still stands	☐
E	The laptop	In a private window open www.shaperassistant.com/design/volume , then ROCKER: the first board a visitor sees. Then the thin-board corner you saw at go-live 2	VOLUME reads 30.51 L and the curves read the way a board flows. The thin-board corner (a 1" to 1 1/4" center on the Arctic Foam 7'9" SBF, its tail reading below the center) is still what you want to leave for the showing	☐

WHAT FAILED, IN YOUR OWN WORDS (DEVICE AND STEP NUMBER FIRST)

CHECK 8 · THE DEMO ACCOUNT

A separate demo account, so nothing typed during the demo touches your real boards (your call). For example one signed up on support@shaperassistant.com, whose codes land in Zoho.

BOARD (NAME IT THE WAY A SHAPER WOULD)	BLANK PICKED ON ROCKER	FINS SET ON FINS	OPENS ON THE LAPTOP	ORDER FORM PRINTED
1.	☐	☐	☐	☐
2.	☐	☐	☐	☐
3.	☐	☐	☐	☐
4.	☐	☐	☐	☐

One board per family is a good spread. A blank picked on ROCKER is what puts numbers in the order form’s Planing table. A few printed order forms also make handouts for the room.

CHECK 9 · THE FREEZE, WEDNESDAY 7 OCTOBER EVENING

- ☐ The walk has passed on all three devices, or passed after fixes.
- ☐ Claude tags the live build and writes down the Vercel deployment it runs on; the tag goes to GitHub on your go.
- ☐ From then on nothing is pushed, and nothing is changed in Clerk, Google, Neon or Vercel, except a fix for something this walk found, on your go. At most one fix should follow the freeze.

THE DEMO-DAY CARD

The address

www.shaperassistant.com

For shapers’ questions

support@shaperassistant.com

Demo account (its name, never its password)

Live build (tag) and Vercel deployment

Backup connection

Your phone’s hotspot

IF THE SITE MISBEHAVES ON THE DAY

Vercel → the shaper project → the Production Deployment → Instant Rollback → Continue → Confirm Rollback.

On the free plan that goes back one deployment only. A rollback also stops new pushes going live until Undo Rollback is pressed, so tell Claude when you’ve used it.

IF SIGN-UPS STALL IN THE ROOM

One Wi-Fi is one internet address, and Clerk lets one address start 5 sign-ups every 10 seconds. A “too many requests” message clears after ten seconds.

Continue with Google is the quickest. Or ask people to use their phone’s own data, or sign up a few at a time. Looking round the app signed out is never limited.