Client-Server Configuration Guide BSIT 2A - SUARING, CRAIG FRENAN S.

- 1) Set Up the Server (Windows Server)
- 1. Boot from Windows Server installation media.
- 2. Choose Desktop Experience → select Custom (Advanced) → format/partition drives → install.
- 3. Set the Administrator password on first boot.
- 4. Open Services → set Function Discovery Resource Publication to Automatic.
- 5. In Server Manager → Local Server:

Disable Windows Firewall, Defender, and Automatic Updates (if lab requires).

**Enable Remote Desktop.** 

6. Configure Network Adapter → IPv4 Properties:

Disable IPv6.

Set static IP (example):

IP: 192.168.10.10

Subnet: 255.255.255.0 Gateway: 192.168.10.1

DNS: 127.0.0.1 (or server IP if serving DNS).

- 2) Set Up the Client (Windows 10 Pro)
- 1. Boot from Windows 10 installation media → choose Windows 10 Pro → Custom install.
- 2. Configure Network Adapter → IPv4 Properties:

Disable IPv6.

Set to Obtain IP automatically (DHCP).

- 3. Set Function Discovery Resource Publication to Automatic in Services.
- 4. Enable Network Discovery and File & Printer Sharing in Network & Sharing Center.
- 3) Install Server Roles (AD DS, DNS, DHCP, RDS)
- 1. Open Server Manager → Add Roles and Features.
- 2. Install:

**Active Directory Domain Services (AD DS)** 

**DNS Server** 

**DHCP Server** 

Remote Desktop Services (if required)

3. After AD DS installation, Promote server to domain controller:

Create a new forest (example domain: casy.lab)

Set DSRM password → reboot.

4) Configure DNS & DHCP

**DNS**:

Open DNS Manager → create Reverse Lookup Zone for your subnet.

Add PTR records for server/clients (optional).

**DHCP:** 

Authorize DHCP server in the domain.

Create IPv4 scope (example): 192.168.10.100-192.168.10.200, subnet 255.255.255.0.

**Configure scope options:** 

Gateway: 192.168.10.1

DNS: 192.168.10.10 (or 127.0.0.1)

Activate scope.

## 5) Join Client to Domain

1. On client, run in elevated Command Prompt:

ipconfig /release

ipconfig /renew

- 2. Go to System → Change Settings → Computer Name → Change → Domain, enter domain name.
- 3. Enter domain admin credentials → restart.
- 4. Login with domain account via Other User.
- 6) Create User Accounts (AD Users & Computers)
- 1. On server, open Active Directory Users and Computers.
- 2. Expand domain → right-click Users (or custom OU) → New → User.
- 3. Enter user details and set initial password.

Optional: uncheck User must change password at next logon for fixed lab accounts.

Optional: check User cannot change password / Password never expires if required.

4. Finish to create account.