The TDMR Package: Tuned Data Mining in R

Wolfgang Konen, Patrick Koch, Cologne University of Applied Sciences

Initial version: February, 2012 Last update: May, 2016

Contents

1	Usi	ng TDMR	3
	1.1	Overview	3
	1.2	Installing TDMR	3
2	TD	MR Workflow	4
	2.1	Level 1: DM without Tuning	4
	2.2	Level 2: Tuned Data Mining in R	5
	2.3	Level 3: "The Big Loop"	5
3	TD	MR Experiment Concept	6
4	TD	MR Data Reading and Data Split in Train / Validation / Test Data	7
	4.1	Data Reading	7
	4.2	Training, Validation, and Test Set	9
		4.2.1 Principles	9
		4.2.2 Test Set Splitting	9
		4.2.3 main_TASK and its training/validation/test logic	11
	4.3	Examples	12
5	TD	MR Important Variables	14
	5.1	Variable opts	14
	5.2	TDMR RGain Concept	14
		5.2.1 Classification	14
		5.2.2 Regression	16

CI	TOP Report 02/2012 The TDMR Package: Tuned Data Mining in R	2
	5.3 Classes tdmClass and tdmRegre	17 17
6	TDMR parallel computing concept	19
	6.1 How to use parallel computing	19
	6.2 Environment envT for parallel mode	19
7	Variable-length vectors in TDMR classification	19
	7.1 sampsize	20
	7.2 cutoff	21
	7.3 classwt	22
8	Example Usage	23
9	Frequently Asked Questions (FAQ)	23
10	TDMR for Developers	24
	10.1 TDMR Tuner Concept	24
	10.1.1 How to use different tuners	24
	10.1.2 How to integrate new tuners	24
	10.2 How to integrate new machine learning algorithms	26
	10.3 Details on TDMR parallel computing concept	26
	10.4 TDMR Design Mappping Concept	27
	10.4.1 How to add a new tuning variable	27
	10.5 TDMR seed Concept	28
	10.6 TDMR Graphic Device Concept	30
11	Summary	32
A	Appendix A: tdmMapDesign.csv	33
В	Appendix B: List opts	34
\mathbf{C}	Appendix C: List tdm	38
D	Appendix D: Data frames envT\$res and envT\$bst	40

1 Using TDMR

1.1 Overview

The TDMR framework is written in R with the aim to facilitate the training, tuning and evaluation of data mining (DM) models. It puts special emphasis on tuning these data mining models as well as simultaneously tuning certain preprocessing options. TDMR is especially designed to work with SPOT [Bartz-Beielstein, 2010] as the preferred tuner, but it offers also the possibility to use other tuners, e.g., CMA-ES [Hansen, 2006], LHD [McKay et al., 1979] or direct-search optimizers [BFGS, Powell] for comparison.

This document (TDMR-docu.pdf, Konen and Koch [2012a])

- gives a short overview over the TDMR framework,
- explains some of the underlying concepts and
- gives more details for the developer.

This document should be read in conjunction with the companion document TDMR-tutorial.pdf [Konen and Koch, 2012b], which shows example usages of TDMR in the form of lessons.

Both documents are available online as CIOP Reports (PDF, Konen and Koch [2012a,b]) from http://www.gm.fh-koeln.de/ciopwebpub.

Both documents concentrate more on the software usage aspects of the TDMR package. For a more scientific discussion of the underlying ideas and the results obtained, the reader is referred to Konen et al. [2010, 2011], Konen [2011], Koch et al. [2012], Koch and Konen [2012], Stork et al. [2013], Koch and Konen [2013], Koch et al. [2014].

1.2 Installing TDMR

Once you have R (http://www.r-project.org/), > 2.14, up and running, simply install TDMR with

```
install.packages("TDMR");
```

Then, library TDMR is loaded with

```
library(TDMR);

## Loading required package: SPOT

## Warning: package 'SPOT' was built under R version 3.2.5

## Loading required package: twiddler

## Loading required package: tcltk
```

 $^{^1{\}rm The}$ precise links are http://www.gm.fh-koeln.de/ciopwebpub/Kone12a.d/Kone12a.pdf and http://www.gm.fh-koeln.de/ciopwebpub/Kone12b.d/Kone12b.pdf. The same files are available as well via the index page of the TDMR package (User guides and package vignettes).

Table 1: Elements of result

result				
	In case of classification, object of class TDMclassifier, containing:			
	opts # with some settings perhaps adjusted in tdmClassify			
	lastRes	# last run, last fold: object of class tdmClass, see Tab. 5		
	$C_{-}train$	# classification error on training set (vector of length NRUN)		
	$G_{-}train$	# gain on training set (vector of length NRUN)		
	$R_{\text{-}}$ train	# relative gain (% of max. gain) on training set (vector of length		
		NRUN)		
	*_test # — similar, with validation set instead of training set			
	*_test2 # — similar, with test2 set instead of training set			
	У	# what to be minized by SPOT, usually mean(-R_test)		
	sd.y # standard deviation of y over the opts\$NRUN runs			
	In case of regression, object of class TDMregressor, containing:			
	opts # with some settings perhaps adjusted in tdmRegress			
	lastRes	# last run, last fold: object of class tdmRegr, see Table 5		
	$R_{\text{-train}}$	# RMAE on training set (vector of length NRUN)		
	S_train # RMSE on training set (vector of length NRUN)			
	T_train # Theil's U for RMAE on training set (vector of length N			
	*_test # — similar, with validation set instead of training set			
	У	# the quantity to be minized by the tuner, usually mean(R_test)		
	sd.y	# standard deviation of y over the opts\$NRUN runs		

2 TDMR Workflow

2.1 Level 1: DM without Tuning

Two kinds of DM tasks, classification or regression, can be handled. For each DM task TASK, create one task-specific function main_TASK(opts=NULL), as short as possible. If called without any parameter, main_TASK() should set default parameters for opts via tdmOptsDefaultsSet(). main_TASK() reads in the task data, does the preprocessing if necessary and then calls with the preprocessed data dset the task-independent functions tdmClassifyLoop or tdmRegressLoop, which in turn call the task-independent functions tdmClassify or tdmRegress.

A template may be copied from inst/demo02sonar/main_sonar.r². The template is invoked with

```
result <- main_sonar();</pre>
```

See **Lesson 1** in TDMR-tutorial.pdf [Konen and Koch, 2012b] for a complete example. See Table 1 for an overview of elements in list result.

²Here and in the following inst/ refers to the directory where the package TDMR is installed. Use find.package("TDMR") to locate this directory.

Table 2: Configuration files for a tuning run

.apd	problem design: all opts-settings
.roi	SPOT ROI file, specifies which parameters to tune in which ROI (region of interest)
.conf	SPOT configuration file, usually with alg.func = "tdmStartSpot". Furthermore, io.apdFileName and io.roiFileName should specify the two files above.

2.2 Level 2: Tuned Data Mining in R

A TDMR task consists of a DM task (Level 1) plus a tuner configuration (decision which parameters to tune within which ROI, which meta parameters to set for the tuner,)

It is recommended to create for each DM task TASK a separate subdirectory. In this subdirectory the files shown in Table 2 have to be created for each tuner configuration (each TDMR task).

Templates for these three files may be copied from inst/demo02sonar/sonar_01.*. The whole SPOT tuning can be started with demo/demo02sonar.r:

```
demo(demo02sonar,ask=F);
```

This script will define a main_TASK in tdm\$mainFunc, reads the .apd file and calls SPOT. SPOT reads the .conf file, calls the generic function tdm\$tartSpot(spotConfig), which finally executes tdm\$mainFunc. The only requirement on tdm\$mainFunc is that it returns in

```
result$y
```

a suitable quantity to be minimized by SPOT. If spot.fileMode==T, SPOT will generate .des and .aroi files (needed by SPOT internally) and the output files .bst and .res. If spot.fileMode==F, tdmStartSpot will read the design from spotConfig\$alg.currentDesign and it writes the .res data frame onto spotConfig\$alg.currentResult.

See Lesson 2 in TDMR-tutorial.pdf [Konen and Koch, 2012b] for the complete example.

2.3 Level 3: "The Big Loop"

"The Big Loop" (several TDM runs with unbiased evaluations) is a script to start several Level-2-TDMR tasks (usually on the same DM task), optionally with

- several tuners (see Table 7 for a list of tuners) and
- several modes of unbiased evaluations and

• several seeds.

The modes of unbiased evaluations allow to compare the best solutions obtained by the tuners. Different modes are available, e.g. to use unseen test data (tdm\$umode = "TST") or to start a new, independent CV (tdm\$umode = "CV") or to start a new, independent re-sampling (tdm\$umode = "RSUB").

To start the Big Loop, only one script file has to be created in the user directory. A template may be copied from demo/demoO3sonar.r. It is invoked with

```
demo(demo03sonar,ask=F);
```

This will specify in runList the list of TDMR tasks and a list of tuners. For each TDMR task and each tuner

- (a) the tuning process is started (if spotStep=="auto") or a previous tuning result is read in from file (if spotStep=="rep") and
- (b) one or more unbiased evaluations are started. This is to see whether the result quality is reproducible on independently trained models and / or on independent test data.

The result is a data frame the Finals with one row for each TDMR task and each tuner. Several columns measure the success of the best tuning solution in different unbiased evaluations, see Table 3. The data frame the Finals is written to tdm final File.

More detailed results are returned in the environment envT. See Sec. 5.4 and Table 6 for more details on envT.

See Lesson 3 in TDMR-tutorial.pdf [Konen and Koch, 2012b] for the complete example.

3 TDMR Experiment Concept

TDMR Level 3 ("The Big Loop") allows

- (a) to conduct experiments, where different .conf files, different tuners, and different unbiased evaluations are tried on the same task;
- (b) to repeat certain experiments of kind (a) multiple times with different seeds (tdm\$nExperim > 1).

Each TDMR experiment consist of three parts:

Model building: • During model building (training) and tuning the user starts with a data set, which is partitioned into training and validation set.

- The relative gain achieved on the validation set acts as performance measure for the tuning process.
- In the case of opts\$TST.kind=="cv" or in the case opts\$NRUN > 1 multiple models are build, each with its own training and validation set. In this case multiple relative gains are averaged to get the performance measure for the tuning process.

Tuning:

- The above model building process is started several times with different model parameters and preprocessing parameters (design points). The tuning process uses the performance measure returned to guide the search for better parameters.
- As a result of the tuning process, a best parameter set is established. It has a certain performance measure attached to it, but this measure might be too optimistic (e.g. due to validation data being used as training data in a prior tuning step or due to extensive search for good solutions in a noisy environment)
- Unbiased Evaluation (Test): Once a best parameter set is established, an unbiased performance evaluation is recommended. This evaluation is done by calling unbiasedRun() with the object dataObj containing a split into test and training-validation data. See Sec. 4.2 on "Training, Validation, and Test Set".
 - If tdm\$nrun > 1, multiple calls to unbiasedRun() are executed. The performance measure returned is the average over all runs.

More details:

- Each experiment of kind (a) initially deletes file tdm\$finalFile, if it exists, and then writes for each combination (.conf file, tuner) it encounters a line to tdm\$finalFile (usually a file with suffix .fin). This line is a one-row data frame finals which is built in unbiasedBestRun.r (classification) and contains the columns listed in Table 3.
- In the case of regression experiments, each "RGain" has to be replaced by "RMAE" in the table above, see here for further explanation.
- If tdm\$experFile is not NULL, then the same one-row data frame finals is also appended to the file tdm\$experFile. Usually, tdm\$experFile is a file with .exp as suffix. This file is never deleted by the TDMR system, only the user may delete it. tdm\$experFile serves the purpose to accumulate experiments carried out multiple times (with different random seeds). This multiple-experiment execution may be done either directly, within one "big-loop" experiment, if tdmm\$nExperim > 1, or it may be done subsequently by the user when starting demo03sonar.r again at a later point in time with the same tdm\$experFile defined.
- An .exp file can be analyzed with scripts like exp_summ.r in TDM.SPOT.d/appAcid/.

4 TDMR Data Reading and Data Split in Train / Validation / Test Data

4.1 Data Reading

TDMR reads the task data according to function opts\$READ.TrnFn, usually from opts\$filename (but this depends on opts\$READ.TrnFn). Optionally, if opts\$READ.TstFn!=NULL, test data are also read according to this function. Both function have the signature function(opts) and they have to return a data frame. Data are read prior to tuning when the object dataObj is constructed

Table 3: Elements of data frame finals

finals\$	Description	Condition			
- columns obtained from the tuning process -					
CONF	the base name of the .conf file				
TUNER	the value of tdm\$tuneMethod				
-PARAMS-	all tuned parameters appearing in .roi file	if tdm\$withParams==T			
NEVAL	tuning budget, i.e. # of model evaluations during				
	tuning (rows in data frame res)				
RGain.bst	best solution (RGain) obtained from tuning				
RGain.avg	average RGain during tuning (mean of res\$Y)				
Time.TRN	time needed for tuning (see tdm\$timeMode in Ap-				
	pendix C)				
- columns obto	ained from the unbiased runs –				
NRUN	# of runs with different test $&$ train samples in				
	unbiasedRun or # of unbiased CV-runs. Usu-				
	ally NRUN = tdm\$nrun, see fct map.opts in td-				
	mMapDesign.r.				
RGain.TRN	mean training RGain (averaged over all unbi-				
	ased runs). This is OOB training RGain in case				
	opts\$MOD.method==*.RF and the normal train-				
ID EDM	ing RGain for all other model training methods				
sdR.TRN	std. dev. of RGain.TRN	·C··· A · · · · · · · · · · · · · · · ·			
RGain.RSUB	mean test RGain (test set = random subsample)	if tdm\$umode=="RSUB"			
sdR.RSUB	std. dev. of RGain.RSUB	if tdm\$umode=="RSUB"			
RGain.TST	mean test RGain (test set = separate data, user-provided)	if tdm\$umode=="TST"			
sdR.TST	std. dev. of RGain.TST	if tdm\$umode=="TST"			
$RGain.SP_{-}T$	mean test RGain (test set = split-test prior to tuning)	if tdm\$umode=="SP_T"			
$sdR.SP_T$	std. dev. of RGain.RSUB	if tdm\$umode=="SP_T"			
RGain.CV	mean test RGain (test set $=$ CV, cross validation	if tdm\$umode=="CV"			
	with tdm\$nfold CV-folds				
sdR.CV	std. dev. of RGain.CV	if tdm\$umode=="CV"			
Time.TST	time needed for unbiased runs (see tdm\$timeMode				
	in Appendix C)				
Note that from	n the "RGain" columns with "if tdm\$umode" only c	one will be selected, since			
tdm\$umode has exactly one value. The same for the "sdR" columns.					

For more information on "RGain" see Sec. 5.2. Mean and standard deviation of RGain are obtained by averaging over all unbiased runs.

```
opts <- tdmEnvTGetOpts(envT);
dataObj <- tdmSplitTestData (opts,tdm,nExp);</pre>
```

where tdmSplitTestData lets the function tdmReadData2 do the read work (using the options opts\$READ.TrnFn, opts\$READ.TstFn, opts\$READ.TXT, and opts\$READ.NROW).

This object dataObj is passed into tdmBigLoop or tdmTuneIt³. Inside tdmBigLoop or tdmTuneIt, dataObj is passed on to tdmDispatchTuner and unbiasedRun, where the training-validation data and the test data are extracted with

```
dset <- dsetTrnVa(dataObj);
tset <- dsetTest(dataObj);</pre>
```

and passed on to main_TASK(..., dset=dset,tset=tset).

4.2 Training, Validation, and Test Set

4.2.1 Principles

In data mining we know three kind of data or data sets:

- 1. Training set: the data for learning or model training.
- 2. Validation set: the data used to obtain a performance measure of the trained model. The performance on the validation data is used to guide the tuning process.
- 3. **Test set**: When training and tuning is finished, we build a final model. To estimate the quality of the model for new data, we test its performance on test data. Usually, the test data were not seen by the model or the tuner. The user should NOT use the performance on the test data in any way to tune the model further.

Usually, the split into test set on the one side and training/validation set on the other side is done *once* prior to the tuning process. During tuning, many tuning steps are possible, each containing at least one model training and each step may have a new separation of the training/validation set into a training part and a validation part.

4.2.2 Test Set Splitting

How can we split the data into test set on one side and training/validation set (which we will abbreviate with TrnVaSet in the following) on the other side?

TDMR offers within the call

³ This is at least recommended behaviour. For downward compatibility, there exist the possibility to enter tdmBigLoop or tdmTuneIt with dataObj=NULL (not recommended). Then two further branches come into effect: a) if opts\$READ.INI=TRUE: read the data at the beginning of bigLoopStep in tdmBigLoop.r; b) if opts\$READ.INI=FALSE: set dset=NULL,tset=NULL and the data reading is done in main_TASK, for each tuning step anew.

```
dataObj <- tdmSplitTestData (opts,tdm,nExp);</pre>
```

four options [the value in brackets denotes the choice for tdm\$umode]:

1. TDMR sets a random fraction of the data aside for testing ["SP_T"].

This is done once before the tuning starts. The test set (the data which are set aside for testing) is used only in unbiased evaluation. The whole procedure can be repeated (if tdmnExperim > 1) and another random test set is set aside.

This is the recommended option, it has a completely independent test set and allows to assess the variability due to varying test set selection.

To use this option, set tdm\$umode="SP_T" and tdm\$TST.testFrac to the desired random fraction to be set aside (default is 10%). The splitting is coded in the column dset\$tdmSplit with 0 for all records belonging to TrnVaSet and 1 for test data. Set tdm\$SPLIT.SEED=<number> if you want reproducible splits (but varying for each experiment which has a different <number>).

- 2. TDMR makes CV with different test set folds ["SP_CV"]. TODO.
- 3. User-defined test set splitting ["TST"]. The user provides two reading functions opts\$READ.TrnFn and opts\$READ.TstFn. ⁴ TDMR reads both, adds then a new column opts\$TST.COL to the data frames with 0 for the train/validataion data and 1 for the test data. Finally, both data frames are bound together into one data frame dset. ⁵
- 4. Test set is part of TrnVaSet ["RSUB" or "CV"]. (NOTE: This option is strongly discouraged, since the test set is already visible during training and tuning, which inevitably leads to overfitting and / or oversearching. But sometimes you may have only very few data and cannot afford to set test data aside.)

The whole data is used for training/validation and later also as the reservoir from which the test set sample is drawn.

To use this option, set tdm\$umode="RSUB" or tdm\$umode="CV". In case "RSUB" set tdm\$TST.testFrac to the desired random fraction to be drawn from the whole data (default is 20%). In case "CV" set tdm\$nfold to the desired number of CV folds (default is 5).

With each of these choices for tdm\$umode, the following happens during unbiased evaluation: A "fresh" model is build using (all or a fraction of) the data in TrnVaSet for training. Then this model is evaluated on the test data and the performance (relative gain or RMAE) on these test data is an unbiased estimator of the model's performance on new data.

⁴ Often these functions will make use of the data file names opts\$filename and opts\$filetest, resp.

⁵ There might be the special case that the user does not have training and test data in two different files, but instead she has a data frame or file containing both training and test records in different rows, distinguished by the value in a special column TST.COL. If this is the case, provide suitable functions opts\$READ.TrnFn and opts\$READ.TstFn which extract the appropriate subsets from the data frame. You might wish to subtract column TST.COL from the data frames returned.

4.2.3 main_TASK and its training/validation/test logic

The signature of function main_TASK is

```
main_TASK(opts=NULL, dset=NULL, tset=NULL)
```

It is usually called in three cases

- 1. by the user (solo ML task or user-defined tuning procedure)
- 2. from TDMR during tuning
- 3. from TDMR during unbiased evaluation

In case 2 the syntax is main_TASK(opts,dset), where dset = dsetTrnVa(dataObj) and tset = NULL.

In case 3 the syntax is main_TASK(opts,dset,tset), where dset = dsetTrnVa(dataObj) and in addition tset = dsetTest(dataObj).

How does main_TASK split into training and validation data (during tuning) or into training and test data (during unbiased evaluation)?




Figure 1: Modes of data splitting in main_TASK. Blue boxes: modes of splitting into training and validation set. Maroon boxes: splitting into training and test set.

If tset==NULL, then tdmClassifyLoop takes care of splitting dset into training and validation data: Three options are supported here, which are distinguished by the value of opts\$TST.kind:

1. "rand" = Random Subsampling: Sample a fraction opts\$TST.valiFrac from dset (the train-validation-data) and set it aside for validation. Use the rest for training,

if opts\$TST.trnFrac is NULL. If opts\$TST.trnFrac is defined (and if it is ≤ 1 - opts\$TST.valiFrac, otherwise error), then use only a random fraction opts\$TST.trnFrac of the non-validation data from dset for training.

- 2. "cv" = Cross Validation: Split dset into opts\$TST.nfold folds and use them for cross validation.
- 3. "col" = User-Defined Column: All records with a 0 in column opts\$TST.COL are used for training, the rest for validation.

The split into training and validation data is done in tdmClassifyLoop, i.e. for each call of main_TASK. This allows to construct different splits train/vali for each tuning step or each repeated run.

Note that the fractions opts\$TST.valiFrac and opts\$TST.trnFrac are relative to the number of rows in dset. dset may be the TrnVaSet defined above or the complete dataset.

opts\$TST.kind =="col" in combination with tdm\$umode="TST" above is normally NOT recommended (the same data are specified for test set and validation set). But it is o.k. in the special case of opts\$MOD.method =="RF" or =="MC.RF" (Random Forest): Then the validation data are in fact never used, since RF uses its own validation measure with the OOB-error on the training data.

If tset != NULL, only opts\$TST.kind=="rand" is allowed. Training data are taken from dset, by choosing a random subsample (fraction opts\$TST.trnFrac).⁶

4.3 Examples

```
opts$READ.TrnFn=readDmc2010Trn
opts$READ.TstFn=readDmc2010Tst
opts$filename="dmc2010_train.txt"
opts$filetest="dmc2010_test.txt"
opts$TST.kind="col"
opts$TST.COL="TST"
opts$MOD.method="RF"
tdm$umode="TST"
```

Read the data prior to tuning, with train-set from dmc2010_train.txt, test set from dmc2010_test.txt. This is coded with 0 and 1 in column TST of the data frame dset. With opts\$TST.kind="col" we specify that all TST==0 data are used for training. The model RF (Random Forest) needs no validation data, since the performance measure is "OOB on the training set".

```
opts$filename="sonar.txt"
opts$TST.testFrac=0.15
```

 $^{^6}$ If opts\$TST.trnFrac==NULL, set it to 1 - opts\$TST.valiFrac. Set opts\$TST.trnFrac=1 (and opts\$TST.valiFrac=0), if you want to use all data from dset for training.

Table 4: Overview of important variables in TDMR

```
opts
        list with DM settings (used by main_TASK and its subfunctions). Parameter
        groups:
        opts$READ.*
                       # reading the data
                       # training / validation / test set and resampling
        opts$TST.*
        opts$PRE.*
                       # preprocessing
        opts$SRF.*
                       # sorted random forest (or similar other variable rankings)
        opts$MOD.*
                       # genera model issues
        opts$CLS.*
                       # classification issues
        opts$RF.*
                       # Random Forest
        opts$SVM.*
                       # Support Vector Machine
        opts$GD.*
                       # graphic device issues
        See Appendix B or ?tdmOptsDefaultsSet for a complete list of all elements in
        opts.
        preprocessed data set (used by main_TASK and its subfunctions)
dset
result
        list with results from Level 1, see Table 1
finals see Table 3
lastRes list with results from tdmClassify/tdmRegress, see Table 5
        environment, see Table 6
envT
tdm
        list with all options for controlling TDMR, see Appendix C or
        ?tdmDefaultsFill for a complete list of all elements in tdm
```

```
opts$TST.kind="cv"
opts$TST.nfold=5
tdm$umode="SP_T"
```

Read the data prior to tuning from sonar.txt, split them by random subsampling: 15% into test set and 85% into train+validation set. This is coded with 0 and 1 in column "tdmSplit" of data frame dset. During tuning, the train+validation set is further split by cross validation with 5 folds (new split in each tuning step). The unbiased run uses all 85% train+validation data for training and reports the performance on the 15% test set data.

Details: opts\$TST.kind="rand" triggers random resampling for the division of dset into training and test set. In the case of classification this resampling is done by stratified sampling: each level of the response variable appears in the training set in proportion to its relative frequency in dset, but at least with one record. This last condition is important to ensure proper functioning also in the case of "rare" levels (most DM models will crash if a certain level does never appear in the training set). In the case of regression the sample is drawn randomly (without stratification).

5 TDMR Important Variables

5.1 Variable opts

opts is a long list with many parameters which control the behaviour of main_TASK, i.e. the behaviour of Level 1. To give this long list a better structure, the parameters are grouped with key words after "opts\$" and before "." (see Table 4 above).

There are some other parameters in opts which do not fall in any of the above groups, e.g.

- opts\$NRUN
- opts\$VERBOSE

and others.

You should create opts with tdmOptsDefaultsSet() and specify in your application (i.e. main_TASK or *.apd) only those elements of opts which differ from these defaults. Or you enter main_TASK with a partially filled opts and leave the rest to function tdmFillOptsDefaults (in tdmOptsDefaults.r), which is called from main_TASK after the user's opts-settings (because some settings might depend on these settings of the user).

The accessor function Opts(envT\$result) returns the element envT\$result\$lastRes\$opts.

• For "type safety", every object opts should be created as

```
opts = tdmOptsDefaultsSet()
```

and not with opts = list().

- If the list opts is extended by element X in the future, you need only to add a default specification of opts\$X in function tdmOptsDefaultsSet, and all functions called from main_TASK will inherit this default behaviour.
- tdmOptsDefaultsSet calls finally the internal function tdmOptsDefaultsFill(opts), and this fills in further defaults derived from actual settings of opts (e.g. opts\$LOGFILE is an element which is derived from opts\$filename as <opts\$filename>.log).

5.2 TDMR RGain Concept

5.2.1 Classification

The **total gain** is defined as the sum of the pointwise product **gainmat*confmat**. Here **confmat** is the confusion matrix (actual vs. predicted cases) and **gainmat** is the gain associated with each possible outcome.⁷

The R_-elements (i.e. result\$R_train and result\$R_test, referred to as "RGain" in different places of this document) can contain different performance measures, depending on the value of opts\$rgain.type:

⁷If there are for example different costs for different types of misclassification, the gain matrix can be defined with zeros on the diagonal and a negative gain "-cost" for each non-diagonal element (negative cost matrix).

Table 5: Elements of lastRes. The items last* are specific for the *last* model (the one built for the last response variable in the last run and the last fold)

lastRes lis	Res list with results from tdmClassify/tdmRegress:		
Ir	In the case of classification, an object of class tdmClass with:		
	pts	# with some settings perhaps adjusted	
d	d_train # training set + predicted class column(s)		
d.	_test	# test set + predicted class column(s)	
d	_dis	# disregard set + predicted class column(s)	
al	llEVAL	# data frame with evaluation measures, one row for each response	
		# variable, the columns are explained in Sec. 5.3	
la	astCm*	# confusion matrix for $*$ = train or test	
la	astModel	# the trained model (for last response variable)	
la	astPred	# name of prediction column	
la	astProbs	# a list with three probability matrices (row: records, col: classes)	
		$\#$ v_train, v_test, v_dis if the model provides probabilities.	
Ir	n the case of r	egression, an object of class tdmRegre with:	
O]	opts # with some settings perhaps adjusted		
d.	d_train # training set + predicted regression column(s)		
d.	d_test # test set + predicted regression column(s)		
al	llRMAE	# data frame with rows = response.variables and columns accord-	
		ing to Sec. $5.2.2$ (RMAE = relative mean absolute error):	
	# \$rmae.train: RMAE on training set		
		# \$theil.train: Theil's U [RMAE] on training set	
		# \$rmae.test: RMAE on test set	
		# \$theil.test: Theil's U [RMAE] on test set	
al	llRMSE	# data frame with rows = response.variables and columns accord-	
		ing to Sec. $5.2.2$ (RMSE = root mean square error):	
		# \$rmse.train: RMSE on training set	
		# \$theil.train: Theil's U [RMSE] on training set	
		# \$rmse.test: RMSE on test set	
	# \$theil.test: Theil's U [RMSE] on test set		
la	astModel	# the trained model (for last response variable)	

- "rgain" or NULL [def.]: the relative gain in percent, i.e. the total gain actually achieved divided by the maximal achievable gain on the given data set,
- "meanCA": mean class accuracy: For each class the accuracy (1 error rate) on the data set is calculated and the mean over all classes is returned,
- "minCA": same as "meanCA", but with min instead of mean. For a two-class problem this is equivalent to maximizing the min(Specificity,Sensitivity).

For binary classification there are additional options for opts\$rgain.type, based on package ROCR [Sing et al., 2005]:

- "arROC": area under ROC curve (a number in [0,1]),
- "arLIFT": area between lift curve and horizontal line 1.0,
- "arPRE": area under precision-recall curve (a number in [0,1]).

In each classification case, TDMR seeks to minimize -result\$R_train, i.e. to maximize result\$R_train.

5.2.2 Regression

For regression: The R_-elements (i.e. result\$R_train and result\$R_test, referred to as "RGain" in different places of this document) can contain different things, depending on the value of opts\$rgain.type (with y_i = true response and p_i = predicted response):

• "rmae" or NULL [def.]: the relative mean absolute error RMAE, i.e.

$$RMAE = \frac{\frac{1}{N} \sum_{i=1}^{N} |y_i - p_i|}{\frac{1}{N} \sum_{i=1}^{N} |y_i|}$$

• "rmse", root mean square error:

$$RMSE = \sqrt{\frac{1}{N} \sum_{i=1}^{N} (y_i - p_i)^2}$$

• "made", mean absolute deviation:

$$MADE = \frac{1}{N} \sum_{i=1}^{N} |y_i - p_i|$$

In each regression case, TDMR seeks to minimize result\$R_train.

In addition, the measure Theil's U is returned in lastRes\$allRMSE\$theil.*, which is in the case of RMSE:

Theil's U =
$$\frac{RMSE}{\sqrt{\frac{1}{N}\sum_{i=1}^{N}(y_i - p_i^{(naive)})^2}},$$

where $p_i^{(naive)}$ is the prediction of a naive prediction model. This naive model is by default the mean of the response variable on the training data set (but other naive models could be used as well). The meaning of Theil's U is: If it is greater than 1, then the model is of no use, because it is beaten by the naive model. If it is smaller than 1, the model has some predictive power.

In the case of RMAE, Theil's U is defined similarly:

Theil's U =
$$\frac{RMAE}{\frac{1}{N}\sum_{i=1}^{N}|y_i - p_i^{(naive)}|},$$

5.3 Classes tdmClass and tdmRegre

Function tdmClassify returns as result an object of class tdmClass and function tdmRegress returns an object of class tdmRegre. Both objects are lists. Within list result (Tab. 1), the element lastRes is an object of either tdmClass or tdmRegre (Tab. 5).

Objects of class tdmClass (Tab. 5) contain a data frame allEVAL. The 9 evaluation measures in allEVAL are

cerr.* misclassification error,

gain.* total gain and

rgain.* relative gain, i.e. total gain divided by max. achievable gain in *

where * = [trn | tst | tst2] stands for [training set | test set | test set with special treatment] and the special treatment is either opts\$test2.string = "no postproc" or "default cutoff".

5.4 Environment envT

The environment envT is used for several purposes in TDMR

- to report results from a call to tdmBigLoop (Level 3) back to the user,
- to communicate information between different parts of TDMR,
- to pass necessary information to and back from the parallel slaves, see Sec. 6.2 Environment envT for parallel mode.

Environment envT is constructed in tdmEnvTMakeNew, with some elements filled in later by other functions. Table 6 shows the elements of envT.

Table 6: Elements of environment envT. The 3rd column shows which function adds the specified element to envT.

variable	remark	function
bst	data frame (see Appendix D)	tdmStartOther or spotTuner, lhdTuner
bstGrid	list with all bst data frames, bstGrid[[k]] retrieves the kth data frame	tdmBigLoop or populateEnvT
$_{\left(\mathrm{conf},\mathrm{tuner},n\right) }^{\mathrm{getBst}}$	function returning from bstGrid the bst data frame for configuration file conf, tuning method tuner and experiment n	tdmBigLoop
res	data frame (see Appendix D)	tdmStart* or tdm- BigLoop
resGrid	list with all res data frames, resGrid[[k]] retrieves the kth data frame	tdmBigLoop or populateEnvT
getRes (conf,tuner,n)	function returning from resGrid the res data frame for configuration file conf, tuning method tuner and experiment n	tdmBigLoop
result	list with results of tdm\$mainFunc as called in the last unbiased evaluation, see Table 1	unbiasedRun
$\operatorname{runList}$	a list with .conf files	tdmBigLoop
spotConfig	see package SPOT	tdmBigLoop
tdm	see Appendix C	tdmBigLoop
theFinals	data frame with one row for each res file, see Table 3	tdmBigLoop or populateEnvT
tunerVal	the value of $tdmDispatchTuner$ (which can be a long list in case of SPOT)	tdmDispatchTuner

envT is used to pass information back and forth between different functions of TDMR,
where envT\$sCList[[k]]\$opts and envT\$tdm pass info into tdmStart*, while envT\$res and
envT\$bst are used to pass info back from tdmStart* to the main level. Note that the variable opts with various settings for the DM process is returned in several variables of envT:

envT\$result\$opts,
envT\$result\$lastRes\$opts,
envT\$tunerVal\$opts,
envT\$spotConfig\$opts,
envT\$sCList[[k]]\$opts.

6 TDMR parallel computing concept

6.1 How to use parallel computing

TDMR supports parallel computing through the packages snow and package parallel. Parallelization of TDMR's level-3-tasks is very easy, you simply have to set tdm\$parallelCPUs to a suitable value > 1. This will invoke the parSapply-mechanism of parallel.

Note that a certain parSapply will try to spawn always tdm\$parallelCPUs processes, but if the last process(es) are less than this number, parSapply will wait for the slowest to complete before the next parSapply takes over. So it is a good idea to bundle as many processes as possible into one parSapply, if you want an even load distribution over time. But on the other hand, it has also advantages to send several tdmBigLoop's because every such call will have its own envT, which is saved on its own .RData file at the end of function tdmBigLoop and so the intermediate results are preserved, even if the parallel cluster should crash.

6.2 Environment envT for parallel mode

The environment envT is used to pass necessary information to and back from the parallel slaves. It replaces in nearly all cases the need for file reading or file writing. (File writing is however still possible for the sequential case or for parallel slaves supporting file access. File writing might be beneficial to trace the progress of parallel or sequential tuning processes while they are running and to log the resulting informations.)

See Sec. 5.4 and Table 6 for more information on envT.

7 Variable-length vectors in TDMR classification

When running TDMR for classification, some possible tuning parameters need special treatment. These are (in the case of RF or similar learning algorithms):

- sampsize
- cutoff
- classwt

We explain the details in the following.

7.1 sampsize

The parameter sampsize in a call to randomForest can be either

- a) a scalar, then it is the total sample size
- b) a vector of length n.class = "number of levels in response.variable", then it is the size of each strata (number of samples with that class level), so the sum of this vector is the overall sample size.

TDMR allows to tune the sampsize variables in either case a) or b), in case b) up to a limit of n.class=5. A ROI file can contain lines with SAMPSIZE1, SAMPSIZE2, SAMPSIZE3, SAMPSIZE5, SAMPSIZE5 which are mapped to opts\$RF.samp[i], i=1,...,5.

If only SAMPSIZE1 is present in ROI file, then opts\$RF.samp is a scalar, which is case a) above. Otherwise, we have case b).

In more detail:

For classification:

- SAMPSIZEi in ROI will be mapped to opts\$RF.samp[i]. If the user wants to tune just a scalar sampize, she defines only SAMPSIZE1 in ROI file.
- After mapping, opts\$RF.samp has to be a scalar or a vector of length n.class. That is, the APD file is responsible for setting all opts\$RF.samp[i] that do not appear in ROI file (because they shall not be tuned).
- Prior to training the model on data to.model, a call tdmModAdjustSampsizeC will check all this and will throw errors, if not fulfilled. In addition,

```
tdmModAdjustSampsizeC(opts$RF.samp,...)
```

will compare opts\$RF.samp[i] with the number of records for each class level in the training set to model and clip it, if necessary. The result is a vector opts\$RF.sampsize, which is guaranteed to work in train.rf for a call randomForest(...,sampsize,...).

• If importance check is enabled (SRF), then a similar call

```
tdmModAdjustSampsizeC(opts$SRF.samp,...)
```

will be done before importance check. Currently, opts\$SRF.samp will be only a scalar (if not set otherwise in APD file). It is not (yet) in the set of tunable parameters.

For regression:

- very much the same, only tdmModAdjustSampsizeC is replaced by tdmModAdjustSampsizeR;
- this takes care of the fact, that for regression, sampsize can only be a scalar (or NULL).

7.2 cutoff

The parameter cutoff in a call to randomForest (for classification only) can be either

- a) not present, then cutoff[i] = 1/n.class is the default, where n.class = "number of levels in response.variable"
- b) a vector of length n.class, whose sum has to be exactly 1.

TDMR allows to tune the cutoff variables in b) up to a limit of n=n.class=5. A ROI file can contain lines with CUTOFF1, CUTOFF2, CUTOFF3, CUTOFF4, CUTOFF5 which are mapped to opts\$CLS.cutoff[i], i=1,...,5.

It is a bit tricky to ensure for $c_i = \text{CUTOFF}$ the constraint $\sum_{i=1}^n c_i = 1$.

This is because a tuning of any CUTOFFi tells the tuner to select a random value from [lower,upper] as specified in ROI file, independent of the other CUTOFFk. Therefore a design point will almost always violate the sum constraint. Even if we map the violating design points to legal ones, the problem remains that many different design points are mapped to the same configuration.

How to cure? - The short story is: It is not wise to tune all c_i , i = 1,..,n. Instead: Set one $c_i = -1$ in APD file, specify positive values for the $\mathtt{n.class}-1$ other c_i either in ROI or in APD file. This reduces the tuning complexity because at most $\mathtt{n.class}-1$ cutoffs need to be tuned. Example:

```
optsCLS.cutoff = c(0.1, -1, 0.5)
```

Then TDMR (with function tdmModAdjustCutoff) will take care to set the negative cutoff to $1 - \sum$ (other cutoffs), i.e. $c_2 = 1 - 0.6 = 0.4$ in the example above.

In more detail:

- opts\$CLS.cutoff is the cutoff for model training. opts\$SRF.cutoff is the cutoff for the randomForest used during importance check.
- The APD file may or may not specify values for opts\$CLS.cutoff and opts\$SRF.cutoff. E.g.

```
opts$CLS.cutoff=c(0.1, 0.1, -1)
```

signaling that opts\$CLS.cutoff[3] gets the remainder to 1. If it does not specify anything, the default

```
opts$CLS.cutoff=NULL opts$SRF.cutoff=opts$CLS.cutoff
```

is taken (function tdmOptsDefaultsSet). If any cutoff is NULL, there will be no cutoff argument in the call to randomForest.

• Now the design point according to the ROI file is mapped, e.g. with

```
CUTOFF1 = 0.243
CUTOFF2 = 0.115
```

we get opts\$CLS.cutoff=c(0.243, 0.115, -1).

Note: Any settings in the ROI file will overwrite prior settings of the APD file. This means that the setting opts\$CLS.opt[1]=0.1 in APD file is overwritten by the appearance of CUTOFF1 in the ROI file

- The setting opts\$CLS.cutoff=c(0.243, 0.115, -1) is passed on to TDMR and TDMR (with function tdmModAdjustCutoff) takes care to map the cutoff vector to valid cutoff vector (all $c_i > 0$ and $\sum c_i = 1$). It takes care of some special cases:
 - If the cutoff vector has length n.class-1, it adds a -1 at the end.
 - If exactly one cutoff is negative, it is set to $1 \sum$ (other cutoffs). If more than one cutoff is negative, it throws an error.
 - If ∑ (other cutoffs) ≥ 1, it scales all those elements to sum 0.9. Why 0.9? Because then the left-over cutoff can get a positive value 0.1. A warning "sum ≥ 1"is issued. There is no problem if this warning occurs only for some design points, it can happen sometimes for certain ROI regions. But if it happens very often, the user may change the ROI, so that the left-over cutoff is not always 0.1.
 - It is a good idea to tune the smaller cutoffs and have the largest cutoff as left-over, in this case warnings will occur less often or never.

7.3 classwt

The parameter classwt in a call to randomForest (for classification only) can be either

- a) not present, then all class levels get the same weight,
- b) a vector of length n.class, where n.class = "number of levels in response variable".

TDMR allows to tune the classwt variables in case b) up to a limit of n=n.class=5. A ROI file can contain lines with CLASSWT1, CLASSWT2, CLASSWT3, CLASSWT5, CLASSWT5 which are mapped to opts\$CLS.CLASSWT[i], i=1,...,5.

Similar to cutoff, CLASSWTi tells the tuner to select a random value from [lower,upper] as specified in ROI file, independent of the other CLASSWTk. Similar to cutoff, only the relative weight to the other CLASSWTi is important. Therefore, it is not wise to tune all CLASSWTi, i = 1,.,n. Instead: Set one CLASSWTi in APD file, specify positive values for the n.class-1 other CLASSWTi either in ROI or in APD file. This reduces the tuning complexity because at most n.class-1 variables in classwt need to be tuned.

8 Example Usage

The usage of the TDMR workflow is fairly easy. We show several example lessons in the accompanying document TDMR-tutorial.pdf [Konen and Koch, 2012b].

9 Frequently Asked Questions (FAQ)

See the FAQ section in the accompanying document TDMR-tutorial.pdf [Konen and Koch, 2012b].

10 TDMR for Developers

This section contains more details about some aspects of TDMR. It can be skipped on first reading.

10.1 TDMR Tuner Concept

10.1.1 How to use different tuners

If you want to tune a TDMR-task with two tuners SPOT and CMA-ES: Simply specify

```
tdm$tuneMethod = c("spot","cmaes")
```

in demo03sonar.r and set the variable spotStep to "auto". The tuning results are in envT\$bst and envT\$res and in envT\$bstGrid and envT\$resGrid (see Appendix D and Table 6).

10.1.2 How to integrate new tuners

Originally TDMR was only written for SPOT as tuning method.

In November'2010, we started to add other tuners to aid the comparision with SPOT on the same footing. As the first other tuner, we introduced CMA-ES [Hansen, 2006]. Since comparison with SPOT is the main issue, CMA-ES was wrapped in such a way in tdmDispatchTuner.r that the behaviour and output is very similar to SPOT.

This has the following implications which should also be obeyed when adding other tuners to TDMR:

- Each tuning method has a unique name (e.g. "spot", "cma_j"): this name is an allowed entry for tdm\$tuneMethod and finals\$TUNER and it is the name of a subdir in TDM.SPOT.d/TASK/.
- Each tuner writes result files (.bst, .res) in a fashion similar to SPOT. These result files are copied to the above mentioned subdir at the end of tuning. This facilitates later comparision of results from different tuners.
- Each tuner supports at least two values for spotStep: "auto" and "rep" (="report"). In the latter case it is assumed that .bst and .res already exist (in their subdir) and they are usually analysed with spot(confFile, "rep",...).
- Each tuner reads in the .conf file and infers from spotConfig the tuner settings (e.g. budget for function calls, max repeats, ...) and tries to make its tuning behaviour as similar to these settings as possible.

For the current CMA-ES tuner the relevant source code for integration in TDMR is in functions tdmDispatchTuner and cmaesTuner (both in tdmDispatchTuner.r) and in tdmStartCMA.r. These functions may be used as templates for the integration of other tuners in the future.

Table 7: Tuners availabe in TDMR

tdm\$tuneMethod	Description
spot	Sequential Parameter Optimization Toolbox,
_	Bartz-Beielstein [2010]
lhd	Latin Hypercube Design, McKay et al. [1979]
	(truncated SPOT, all budget for the initial step)
cmaes	Covariance Matrix Adaption ES, Hansen [2006]
	(R-version, package cmaes)
cma_j	Covariance Matrix Adaption ES, Hansen [2006]
	(Java-version, interfaced to R via package rCMA)
powell	Powell's method, Powell [1970]
	(direct & local search)
bfgs	Broyden, Fletcher, Goldfarb and Shannon method,
	Shanno [1985] (direct & local search)

Table 8: Parallel operating modes

tdm\$		
parallelCPUs	fileMode	description
= 1	FALSE	sequential, everything is returned via environment envT, no files are written
= 1	TRUE	sequential, everything is returned via environment envT, and logged on several files
> 1	FALSE	parallel, everything is returned via environment envT, no files are written or read
> 1	TRUE	parallel, everything is returned via environment envT, and logged on several files

10.2 How to integrate new machine learning algorithms

Assume you want to add a new algorithm named ALGO, similar to the existing algorithms RF or SVM.

- Add a new function train.ALGO in tdmClassify.r and/or tdmRegress.r.
- Add a new function apply.ALGO in tdmClassify.r and/or tdmRegress.r.
- Add a new choice "ALGO" to opts\$MOD.method.
- Add the tunable parameters of ALGO as opts\$ALGO.* to the list opts, see tdmOptsDefaults.r.
- Add for each parameter opts\$ALGO.* a suitable mapping in tdmMapDesign.csv.

10.3 Details on TDMR parallel computing concept

We parallelize the tdmDispatchTuner-calls which are currently inside the 3-fold loop tdm\$nExperim, runList, tdm\$tuneMethod). Therefore, these loops are written as sapply commands, which can be transformed to parSapply.

Four operating modes are shown in Table 8:

- {= 1,FALSE} is the current and recommended sequential mode.
- {= 1,TRUE} is the older (May'2011) and deprecated sequential mode.
- {> 1,FALSE} is the parallel mode needed for LIDO (TU DO). It requires more software redesign, since the code should make no file access (no sourcing, no data set reading!) below the call to tdmDispatchTuner.
- {> 1,TRUE} is the parallel mode viable on maanys-clusters at GM (they have access to a file system), if the user is sure that the file writings cannot interfere. For safety it is nevertheless recommended to use {> 1,FALSE}.

More Details

- We have in tdmBigLoop only one parallelization mode (parallel over experiments, tuners and .conf files). We decided that it is sufficient to have one strategy for parallelization, for all values of tdm\$parallelCPUs. We decided that it is dangerous to have nested parSapply-calls.
- When does parSapply return? The manual says that parSapply first hands out nCPU jobs to the CPUs, then waits for all (!) jobs to return and then hands out another nCPU jobs until all jobs are finished. parSapply returns when the last job is finished. Therefore it is not clear what happens with nested parSapply-calls and we make our design in such a way that no such nested calls appear.
- We added column NEXP (=envT\$nExp) to tdm\$finalFile and tdm\$experFile. So it might be that older .fin and .exp files can no longer be merged with the new ones.

- File writing is no longer necessary for the process, because all data needed are logged in environment envT. But it may be beneficial for tracing the progress of a long-running process. If tdm\$fileMode==TRUE, each parallelizable branch makes its writing in a separate directory (e.g. spot/, cmaes/, ... for different tuner branches and/or 01/, 02/, 03, ... for different experiments with seeds 1,2,3,...). A master file might collect the information from the different files in the end.
- In case tdm\$nExperim>1 we write now on different .fin files, e.g. sonar-e01.fin, sonar-e02.fin, ... This is to avoid that parallel executing tasks will remove or write on the same .fin file concurrently.
- How and when is the res data frame passed back from SPOT? (we get an error with spot.fileMode=F). The bst data frame is in spotConfig\$alg.currentBest. Answer: With the new SPOT package version (>0.1.1372) and with spot.fileMode==F, the res data frame is passed back in spotConfig\$alg.currentResult. The user function spotConfig\$alg.func is responsible for writing this data frame. We do this for both values of spot.fileMode: we start in functions spotTuner and lhdTuner a new data frame spotConfig\$alg.currentResult (initially NULL) and fill it consecutively in tdmStartSpot.

10.4 TDMR Design Mappping Concept

Each variable appearing in.roi file (and thus in .des file) has to be mapped on its corresponding value in list opts. This is done in the file tdmMapDesign.csv (see Appendix A):

roiValue	optsValue	isInt
MTRY	opts\$RF.mtry	1
•••		

If a variable is defined with isInt=1, it is rounded in opts\$... to the next integer, even if it is non-integer in the design file. The base file tdmMapDesign.csv is read from <packageDir> = .find.package("TDMR").8 If in the <dir_of_main_task> = dirname(tdm\$mainFile) an additional file userMapDesign.csv exists, it is additionally read and added to the relevant data frame. The file userMapDesign.csv makes the mapping modifiable and extendable by the user without the necessity to modify the corresponding source file tdmMapDesign.r.

These files are read in when starting tdmCompleteEval via function tdmMapDesLoad and the corresponding data frames are added to envT\$map and envT\$mapUser, resp. This is for later use by function tdmMapDesApply; this function can called from the parallel slaves, which might have no access to a file system.

10.4.1 How to add a new tuning variable

There are several options:

⁸resp. from tdm\$tdmPath/inst/ for the developer version.

- (user) add a new line to userMapDesign.csv or
- (developer) add a new line to tdmMapDesign.csv or
- (optional, for developer) add a line to tdmOptsDefaultsSet(), if it is a new variable opts\\$... and if all existing and further tasks should have a default setting for this variable

Details We have in tdmMapDesign.r beneath tdmMapDesLoad, tdmMapDesApply a second pair of functions tdmMapDesSpot\$load, tdmMapDesSpot\$apply with exactly the same functionality. Why? – The second pair of functions is for use in tdmStartSpot(spotConfig) where we have no access to envT due to the calling syntax of spot(). Instead the object tdmMapDesSpot store the maps in local, permanent storage of this object's environment. - The first pair of functions tdmMapDesLoad, tdmMapDesApply is for use in tdmStartOther, especially when called by a separate R process when using the tuner cma_j. In this case, the local, permanent storage mechanism does not work across different R sessions. Here we need the envT-based solution of the first pair, since the environment envT can be restored across R sessions easily via save & load.

10.5 TDMR seed Concept

In a TDMR task there are usually several places where non-deterministic decisions are made and therefore certain questions of reproducability / random variability arise:

- 1. Design point selection of the tuner,
- 2. Test/training-set division and
- 3. Model training (depending on the model, RF and neural nets are usually non-deterministic, but SVM is deterministic).

Part 1) is in the case of SPOT tuning controlled by the variable spot.seed in the .conf file. You may set spot.seed=any fixed number for selecting exactly the same design points in each run. (The design point selection is however dependent on the DM process: If this process is non-deterministic (i.e. returns different y-values on the same initial design points, you will usually get different design points from sequential step 2 on.) Or you set spot.seed=tdmRandomSeed() and get in each tuning run different design points (even if you repeat the same tuning experiment and even for a deterministic DM process). In the case of CMA-ES or other tuning algorithms, we use set.seed(spotConfig\$spot.seed) right before we randomly select the initial design point and ensure in this way reproducibility. Part 2) and 3) belong to the DM process and the TDMR software supports here three different cases of reproducability:

a) Sometimes you want two TDMR runs to behave exactly the same (e.g. to see if a certain software change leaves the outcome unchanged). Then you may set opts\$TST.SEED=any fixed number and opts\$MOD.SEED=any fixed number.

- b) Sometimes you want the test set selection (RSUB or CV) to be deterministic, but the model training process non-deterministic. This is the case if you want to formulate problem tasks of exactly the same difficulty and to see how different models or the same model in different runs perform on these tasks. Then you may set opts\$TST.SEED=any fixed number, opts\$MOD.SEED=NULL.
- c) Sometimes you want both parts, test set selection and model training, to be non-deterministic. This is if you want to see the full variability of a certain solution approach, i.e. if you want to measure the degree of reproducability in a whole experiment. Then you may set opts\$TST.SEED= NULL; opts\$MOD.SEED=NULL.

(The case TST.SEED= NULL; MOD.SEED=any value is a fourth possibility, but it has -as far as I can see - no practical application).

What happens if opts\$*.SEED is NULL? — In this case, TDMR will call opts\$*.SEED=tdmRandomSeed() in tdmClassify before each usage of opts\$*.SEED. (* = MOD, TST). Here, tdmRandomSeed is a function which returns a different integer seed each time it is called. This is even true, if it is called multiple times within the same second (where a function like Sys.time() would return the same number). This can easily happen in parallel execution mode, where processes on different slaves usually will be started in the same second. A second aspect of random variability: We usually want each run through main_TASK (loop over i in 1:opts\$NRUN in tdmClassifyLoop) and each repeat during tuning (loop over r in 1:des\$REPEATS[k] in tdmStart*) to explore different random regions, even in the case where all seed settings (spot.seed, opts\$TST.SEED and opts\$MOD.SEED) are fixed. We achieve this by storing the loop variables i and r in opts\$i and opts\$rep, resp., and use in tdmClassify.r the specific seeds

```
newseed=opts$MOD.SEED + (opts$i-1) + opts$NRUN*(opts$rep-1);
and
newseed=opts$TST.SEED + (opts$i-1) + opts$NRUN*(opts$rep-1);
```

In this way, each run through main_TASK gets a different seed. If opts\$*.SEED is any fixed number, the whole process is however exactly reproducible.

Why is opts\$MOD.SEED=tdmRandomSeed() and opts\$MOD.SEED=NULL different? — The first statement selects a random seed at the time of definition time of opts\$MOD.SEED, but uses it then throughout the whole tuning process, i.e. each design point evaluation within this tuning has the same opts\$MOD.SEED. The second statement, opts\$MOD.SEED=NULL, is different: Each time we pass through tdmClassify (start of response.variable-loop) we execute the statement

```
set.seed(tdmRandomSeed())
```

which selects a new random seed for each design point and each run.

New Jan'2012: When opts*.SEED (* = MOD, TST) is the string "algSeed", then TDMR will set the relevant seed to opts\ALG.SEED, which is the seed spotConfig\alg.seed+r from

SPOT, where spotConfig\$alg.seed is set by the user (reproducibility) and r is the repeatnumber for the design point in question (ensure that each repeat gets another seed to explore the random variability).

Details (RNG = random number generator)

- If TST.SEED=NULL, the RNG seed will be set to (a different) number via tdmRandomSeed() in each pass through the nrun-loop of tdmClassifyLoop / tdmRegressLoop (at start of loop).
- If MOD.SEED= NULL, the RNG seed will be set to (a different) number via tdmRandomSeed() in each pass through the response.variable-loop of tdmClassify / tdmRegress (at start of step 4.3 "model training").
- Before Nov'2010 the TDMR software would not modify RNG seed in any way if TST.SEED=NULL. But we noticed that with a call from SPOT two runs would exactly produce the same results in this case. The reason is that SPOT fixes the RNG seed for each configuration in the same way and so we got the same model training and test set results. To change this, we moved to the new behaviour, where each *.SEED=NULL leads to a "random" RNG-seed at appropriate places.

10.6 TDMR Graphic Device Concept

Utility Functions tdmGraphic* These functions are defined in tdmGraphicUtils.r and should provide a consistent interface to different graphics device choices.

The different choices for opts\$GRAPHDEV are

- "pdf": plot everything in one multipage pdf file opts\$GRAPHFILE
- "png": each plot goes into a new png file in opts\$GD.PNGDIR
- "win": each plot goes into a new window (X11())
- "rstudio": each plot goes to the RStudio plot window
- "non": all plots are suppressed (former opts\$DO.GRAPHICS=F)

tdmGraphicCloseWin does not close any X11()-window (because we want to look at it), but it closes the last open .png file with dev.off(), so that you can look at this .png file with an image viewer.

GD.RESTART, Case 1: main_TASK solo

If GD.RESTART==F: No window is closed, no graphic device restarted.

If GD.RESTART==T we want the following behaviour:

• close initially any windows from previous runs

	opts\$GRAPHDEV				
utility function	pdf	png	win	rstudio	non
tdmGraphicInit	open mul-	(create	_	-	-
	tipage pdf	and) clear			
		PNGDIR			
tdmGraphicNewWin	-	open new	open new	-	-
		png file in	window		
		PNGDIR			
tdmGraphicCloseWin	-	close png	-	-	-
		file			
${\tt tdmGraphicCloseDev}$	close all	close all	close all	clear all	-
	open pdf	open png	devices	plots	
	devices	devices	(graph-		
			ics.off())		

Table 9: Graphic Utility Functions

- not too many windows open (e.g. if NRUN=5, nfold=10, the repeated generation of windows can easily lead to s.th. like 250 open windows)
- the important windows should be open long enough to view them (at least shortly)
- in the end, the last round of windows should remain open.

We achieve this behaviour with the following actions in the code for the case GD.RESTART==T:

- close all open windows when starting main_TASK
- close all open windows before starting the last loop (i==NRUN, k=the.nfold) of tdmClassify
- close all open windows when starting the graphics part (Part 4.7) of tdmClassify UN-LESS we are in the last loop (i==NRUN, k=the.nfold); this assures that the windows remain open before the graphics part, that is during the time consuming training part.
- if GD.CLOSE==T and GD.GRAPHDEV="win": close in the end any open .png or .pdf

GD.RESTART, Case 2: During SPOT-Run "auto"

This will normally have GD.RESTART=F: No window is closed, no graphic device restarted; but also GD.GRAPHDEV="non", so that no graphic is issued from main_TASK, only the graphics from SPOT.

GD.RESTART, Case 3: During unbiased runs

This will normally have also GD.RESTART=F and GD.GRAPHDEV="non": No graphics. But you might as well set GD.RESTART=T and choose any of the active GD.GRAPHDEV's before calling unbiaseBestRun_*, if you want the plots from the last round of unbiasedBestRun_*.

11 Summary

This report has shown how to use TDMR, the Tuned Data Mining framework in R. The examples shown should make the reader familiar with the concepts and the workflow phases of TDMR. More examples are shown in the companion document TDMR-tutorial.pdf [Konen and Koch, 2012b]. They are deliberately made with fairly small datasets in order to facilitate quick reproducability. For results on larger datasets the reader is referred to Konen et al. [2010, 2011].

A Appendix A: tdmMapDesign.csv

```
# For each variable which appears in .roi (and thus in .des file):
# set its counterpart in list opts.
# For each variable not appearing:
# leave its optsValue at its default from .apd file.
 roiValue; optsValue;
                        isInt
 PCA.npc; opts$PRE.PCA.npc;
                                1
           opts$PRE.SFA.npc;
 SFA.npc;
                               1
 SFA.PPRANGE; opts$PRE.SFA.PPRANGE; 1
 SFA.ODIM; opts$PRE.SFA.ODIM; 1
 NCOPIES; opts$ncopies;
 TRNFRAC; opts$TST.trnFrac;
 XPERC;
          opts$SRF.XPerc;
                                0
 NDROP;
           opts$SRF.ndrop;
                                1
          opts$RF.mtry;
 MTRY;
                                1
 NODESIZE; opts$RF.nodesize;
                                1
 NTREE;
           opts$RF.ntree;
 SVMkernel; opts$SVM.kernel;
                                1
 SVMdegree; opts$SVM.degree;
                                1
 ADAcoeflrn; opts$ADA.coeflearn; 1
 ADAmfinal; opts$ADA.mfinal;
 EPSILON; opts$SVM.epsilon;
           opts$SVM.gamma;
 GAMMA;
 TOLERANCE; opts$SVM.tolerance; 0
 SIGMA; opts$SVM.sigma;
 COST;
           opts$SVM.cost;
                                0
 COEFO;
            opts$SVM.coef0;
                                0
 SAMPSIZE1; opts$RF.samp[1];
                                1
 SAMPSIZE2; opts$RF.samp[2];
 SAMPSIZE3; opts$RF.samp[3];
                                1
 SAMPSIZE4; opts$RF.samp[4];
                                1
 SAMPSIZE5; opts$RF.samp[5];
 CLASSWT1; opts$CLS.CLASSWT[1];0
 CLASSWT2; opts$CLS.CLASSWT[2];0
 CLASSWT3;
           opts$CLS.CLASSWT[3];0
 CLASSWT4; opts$CLS.CLASSWT[4];0
 CLASSWT5; opts$CLS.CLASSWT[5];0
 CUTOFF1;
            opts$CLS.cutoff[1]; 0
 CUTOFF2;
            opts$CLS.cutoff[2]; 0
             opts$CLS.cutoff[3]; 0
 CUTOFF3;
 CUTOFF4;
             opts$CLS.cutoff[4]; 0
 CUTOFF5;
            opts$CLS.cutoff[5]; 0
```

B Appendix B: List opts

List opts contains all options relevant for controlling a DM task.

This table – with proper hyperlinks – is as well obtained by typing ?tdmOptsDefaultsSet within an R session.

[<path>= dir(tdm\$mainFile), if tdm\$mainFile is defined, else the current dir.]

Element	Description
dir.txt	[<path>/data] where to find .txt/.csv files</path>
dir.data	[<path>/data] where to find other data files, including .Rdata</path>
dir.Rdata	<pre>[<path>/Rdata] - deprecated, use opts\$dir.data -</path></pre>
dir.output	[<path>/Output] where to put output files</path>
filename	["default.txt"] the task data
filetest	[NULL] the test data, only relevant for READ.TstFn!=NULL
fileMode	[TRUE] if =T, write opts\$EVALFILE=*_train_eval.csv,
	_train.csv.SRF..RData file and *_train.log file
data.title	["Default Data"] title for plots
READ.TXT	[T] =T: read data from .csv and save as .Rdata, =F: read from
	.Rdata
READ.NROW	[-1] read this amount of rows or -1 for 'read all rows'
READ.TrnFn	function to be passed into tdmReadData2. Signature:
	function(opts) returning a data frame. It reads the train-
	validation data.
READ.TstFn	[NULL] function to be passed into tdmReadData2. Signature:
	function(opts) returning a data frame. It reads a separate test
	data file. If NULL, this reading step is skipped.
READ.INI	[TRUE] read the task data initially, i.e. prior to tuning, using
	tdmReadData2. If =FALSE, the data are read anew in each pass
	through main_TASK, i.e. in each tuning step (deprecated).
TST.kind	["rand"] How to split the data into train and validation set. One
	of the choices from ["cv" "rand" "col"] for [cross vali-
	adation random sample column with train/test flag], see
	Sec. 4.2 and tdmModCreateCVindex for details
TST.COL	["TST.COL"] name of column with train/test/disregard-flag
TST.NFOLD	[3] number of CV-folds (only for TST.kind=="cv")
TST.valiFrac	[0.1] set this fraction of data aside for validation (only for
mom	TST.kind=="rand")
TST.testFrac	[0.1] set prior to tuning this fraction of data aside for testing (if
	tdm\$umode=="SP_T" and opts\$READ.INI==TRUE) or set this frac-
	tion of data aside for testing after tuning (if tdm\$umode=="RSUB"
mam appp	or =="CV")
TST.SEED	[NULL] a seed for the random test set selection (tdmRandom-
	Seed) and random validation set selection. (tdmClassifyLoop). If
	NULL, use tdmRandomSeed.

]

NRUN	[2] how many runs with different train & test samples – or – how many CV-runs, if opts\$TST.kind="cv"
PRE.PCA	["none"] PCA preprocessing: ["(default)"none" "linear" for [don't normal pca (prcomp)]
PRE.PCA.REPLACE	[T] =T: replace with the PCA columns the original numerical columns, =F: add the PCA columns
PRE.PCA.npc	[0] if > 0: add monomials of degree 2 for the first PRE.PCA.npc columns (PCs)
PRE.SFA	["none"] SFA preprocessing (see package rSFA: ["none" "2nd"] for [don't normal SFA with 2nd degree expansion]
PRE.SFA.REPLACE	[F] =T: replace the original numerical columns with the SFA columns; =F: add the SFA columns
PRE.SFA.npc	[0] if > 0 : add monomials of degree 2 for the first PRE.SFA.npc columns
PRE.SFA.PPRANGE	[11] number of inputs after SFA preprocessing, only those inputs enter into SFA expansion
PRE.SFA.ODIM	[5] number of SFA output dimensions (slowest signals) to return
PRE.SFA.doPB	[T] =T/F: do / don't do parametric bootstrap for SFA in case of
	marginal training data
PRE.SFA.fctPB	[sfaPBootstrap] the function to call in case of parametric boot-
1 1021811111001 2	strap, see sfaPBootstrap in package rSFA for its interface descrip-
	tion
PRE.Xpgroup	[0.99] bind the fraction 1— PRE.Xpgroup in column OTHER (see
	tdmPreGroupLevels)
PRE.MaxLevel	[32] if there are N cases, bind the $N-32+1$ least frequent cases in column OTHER (see tdmPreGroupLevels)
SRF.kind	["xperc" (default) "ndrop" "nkeep" "none"] the method used for feature selection, see tdmModSortedRFimport
SRF.ndrop	[0] how many variables to drop (if SRF.kind=="ndrop")
SRF.XPerc	$[0.95]$ if ≥ 0 , keep that importance percentage, starting with the
	most important variables (if SRF.kind=="xperc")
SRF.calc	[T] =T: calculate importance & save on SRF.file, =F: load from SRF.file (SRF.file = Output/ <filename>.SRF.<response.variable>.Rdata)</response.variable></filename>
SRF.ntree	[50] number of RF trees
SRF.samp	sampsize for RF in importance estimation. See RF.samp for fur-
Sitt samp	
CDE 1	ther info on sampsize.
SRF.verbose	
SRF.maxS	[40] how many variables to show in plot
SRF.minlsi	[1] a lower bound for the length of SRF\$input.variables
SRF.method	["RFimp"]
SRF.scale	[TRUE] option 'scale' for call importance() in tdmModSortedR-
MOD CEED	Fimport [NIII I] a good for the random model initialization (if model is
MOD.SEED	[NULL] a seed for the random model initialization (if model is non-deterministic). If NULL, use tdmRandomSeed.

 $\label{eq:model} MOD.method $$ ["RF" (default) | "MC.RF" | "SVM" | "NB"] use [RF |]$

MetaCost-RF | SVM | Naive Bayes] in tdmClassify

["RF" (default) | "SVM" | "LM"] use [RF | SVM | linear

model] in tdmRegress

RF.ntree [500]

RF.samp [1000] sampsize for RF in model training. If RF.samp is a scalar,

then it specifies the total size of the sample. For classification, it can also be a vector of length n.class (= number of levels in response variable), then it specifies the size of each strata. The

sum of the vector is the total sample size.

RF.mtry [NULL] RF.nodesize [1]

RF.OOB [TRUE] if =T, return OOB-training set error as tuning measure;

if =F, return validation set error

RF.p.all [FALSE] SVM.cost [1.0]

SVM.C [1] needed only for regression SVM.epsilon [0.005] needed only for regression

 $\begin{array}{ll} {\rm SVM.gamma} & [0.005] \\ {\rm SVM.tolerance} & [0.008] \end{array}$

ADA.coeflearn [1] =1: "Breiman", =2: "Freund", =3: "Zhu" as value for boost-

ing(...,coeflearn,...) (AdaBoost)

ADA.mfinal [10] number of trees in AdaBoost = mfinal boosting(...,mfinal,...)

ADA.rpart.minsplit [20] minimum number of observations in a node in order for a split

to be attempted

CLS.cutoff [NULL] vote fractions for the classes (vector of length n.class =

number of levels in response variable). The class i with maximum ratio (% votes)/CLS.cutoff[i] wins. If NULL, then each class gets the cutoff 1/n.class (i.e. majority vote wins). The smaller

CLS.cutoff[i], the more likely class i will win.

CLS.CLASSWT [NULL] class weights for the n.class classes, e.g. c(A=10,B=20)

for a 2-class problem with classes A and B (the higher, the more costly is a misclassification of that real class). It should be a named vector with the same length and names as the levels of the response variable. If no names are given, the levels of the response variables in lexicographical order will be attached in tdmClassify.

CLS.CLASSWT=NULL for no weights.

CLS.gainmat [NULL] (n.class x n.class) gain matrix. If NULL, CLS.gainmat

will be set to unit matrix in tdmClassify.

rgain.type ["rgain" (default) | "meanCA" | "minCA"] in case classifica-

tion: The measure Rgain returned from tdmClassifyLoop in $resultR_*$ is [relative gain (i.e. gain/gainmax) | mean class accuracy | minimum class accuracy] (see Sec. 5.2.1). The goal

is to maximize Rgain.

For binary classification there are the additional measures ["arROC" | "arLIFT" | "arPRE"], see tdmModConfmat.

	For regression, the goal is to <i>minimize</i> result\$R_* returned from tdmRegress. In this case, possible values are rgain.type = ["rmae" (default) "rmse" "made"] which stands for [relative mean absolute error root mean squared error mean absolute deviation] (see Sec. 5.2.2).
ncopies	[0] if > 0, activate tdmParaBootstrap in tdmClassify
fct.postproc	[NULL] name of a function with signature (pred, dframe, opts)
	where pred is the prediction of the model on the data frame dframe
	and opts is this list. This function may do some postprocessing on
	pred and it returns a (potentially modified) pred. This function
	will be called in tdmClassify if it is not NULL.
GD.DEVICE	["win"]
	="win": all graphics to (several) windows (X11)
	="rstudio": all graphics to RStudio plot window
	="pdf": all graphics to one multi-page PDF
	="png": all graphics in separate PNG files in opts\$GD.PNGDIR
	="non": no graphics at all
GD.RESTART	This affects TDMR graphics, not SPOT (or other tuner) graphics
GD.RESTARI	[T] =T: restart the graphics device (i.e. close all 'old' windows or
	re-open multi-page pdf) in each call to tdmClassify or tdmRegress,
	resp. =F: leave all windows open (suitable for calls from SPOT) or write more pages in same pdf.
GD.CLOSE	[T] =T: close graphics device "png", "pdf" at the end of main_*.r
GB.GBGSE	(suitable for main_*.r solo) or =F: do not close (suitable for call
	from tdmStartSpot, where all windows should remain open)
APPLY_TIME	[FALSE]
VERBOSE	[2] =2: print much output, =1: less, =0: none

Additional settings from tdmOptsDefaultsFill(opts), which depend on the already def'd elements of opts: [* is the stripped part of opts\$filename (w/o suffix).]

Element	Description				
PDFFILE	["*_pic.pdf"] file for multipage graphics in case				
	opts\$GD.DEVICE="pdf"				
GD.PNGDIR	["PNG*"] directory for .png files in case opts\$GD.DEVICE="png"				
LOGFILE	["*.log"] where to log the output				
EVALFILE	["*_eval.csv"] file with evaluation results allEVAL				
SRF.samp	sample size for SRF, derived from opts\$RF.samp				
SRF.cutoff	[opts\$CLS.cutoff] cutoff used during SRF modeling				
rgain.string	one out of c("RGain", "MeanCA", "MinCA", "RMAE", "RMSE"), de-				
	pending on opts\$rgain.type				

C Appendix C: List tdm

List ${\tt tdm}$ contains all options relevant for controlling TDMR.

This table – with proper hyperlinks – is as well obtained by typing ?tdmDefaultsFill within an R session.

Element	Description				
mainFile	[NULL] if not NULL, source this file from the current dir. It should contain the definition of tdm\$mainFunc.				
mainFunc	sub(".r","",basename(tdm\$mainFile),fixed=TRUE), if tdm\$mainFile is set and tdm\$mainFunc is NULL, else "mainFunc". This is the name of the function called by tdmStartSpot and unbiasedRun				
CMA.propertyFile	[NULL] (only for CMA-ES Java tuner) see cma_jTuner.				
CMA.populationSize	[NULL] (only for CMA-ES Java tuner) see cma_jTuner.				
experFile	[NULL] filename where to append envT\$theFinals, only relevant for tdm\$fileMode==TRUE				
fileMode	[FALSE] see "Note" section in ?tdmBigLoop				
finalFile	[NULL] filename where to save envT\$theFinals, only relevant for tdm\$fileMode==TRUE				
filenameEnvT	[NULL] filename where tdmBigLoop will save a small version of environment envT. If NULL, save envT to sub(".conf",".RData",tdm\$runList[1]). This RData file is written irrespective of fileMode's value, but only in case spotStep=="auto".				
nExperim	[1]				
nfold	[10] number of CV-folds for unbiased runs (only for umode="CV")				
nrun	[5] number of unbiased runs				
optsVerbosity	[0] the verbosity for the unbiased runs				
parallelCPUs	$\begin{bmatrix} 1 \end{bmatrix} = 1$: sequential, > 1 : parallel execution with this many CPUs (package parallel)				
parallelFuncs	[NULL] in case tdm\$parallelCPUs> 1: a string vector with functions which are clusterExport'ed in addition to tdm\$mainFunc.				
path	[NULL] where to search .conf and .apd file. If NULL, path is set to the actual working directory at the time when tdmEnvTMakeNew is executed				
runList	a list of .conf files				
stratified	$[\mathrm{NULL}]$ see tdmSplitTestData				
tdmPath	[NULL] from where to source the R sources. If NULL load library TDMR instead.				
test2.string	["default cutoff"]				
the Spot Path	[NA] use SPOT's package version				
timeMode	[1] 1: proc time, 2: system time, 3: elapsed time (columns				
tstCol	Time.TST and Time.TRN in envT\$theFinals, see Table 3) ["TST"] opts\$TST.COL for unbiased runs (only for umode="TST")				

tuneMethod	["spot"] other choices: "cmaes", "bfgs",, see					
	tdmDispatchTuner					
U.saveModel	[FALSE] if TRUE, save the last model, which is trained in					
	unbiasedRun, onto filenameEnvT					
umode	["RSUB"], one out of ["RSUB" "CV" "TST" "SP_T"], see unbiased Run					
unbiasedFunc	["unbiasedRun"] name of function to call for unbiased evaluation					
withParams	[TRUE] include the columns with tuned parameters in final results					
TST.trnFrac	[NULL] train set fraction (of all train-vali data), overwrites					
	opts\$TST.trnFrac if not NULL.					
TST.valiFrac	[NULL] validation set fraction (of all train-vali data), overwrites					
	opts\$TST.valiFrac if not NULL.					
TST.testFrac	[0.2] test set fraction (of *all* data) for unbiased runs (only for					
	<pre>umode="RSUB" or ="SP_T")</pre>					

Note

The settings tdm\$TST.trnFrac and tdm\$TST.valiFrac allow to set programmatically certain values for opts\$TST.trnFrac and opts\$TST.valiFrac *after* opts has been read from APD file. So use tdm\$TST.trnFrac and tdm\$TST.valiFrac with CAUTION!

For tdm\$timeMode, the 'user time' is the CPU time charged for the execution of user instructions of the calling process. The 'system time' is the CPU time charged for execution by the system on behalf of the calling process. The 'elapsed time' is the 'real' (wall-clock) time since the process was started.

D Appendix D: Data frames envT\$res and envT\$bst

Data frame envT\$res contains results from each run of tuner SPOT or other tuners producing equivalent output. Data frame res has the following columns:

- Y: the performance (-Rgain for classification, RMAE for regression) on the validation data with a specific configuration of the tuning variables (a design point), a value to be minimized.
- columns between Y and SEED: the values of the configuration (i.e. the design point in parameter space)
- SEED: seed for random number generator
- STEP: SPOT performs its tuning in several steps. The first step is the initial design (step 0 in the example), where 10 design points are drawn via LHS (latin hypercube design).
- CONFIG: the configuration number (design point number)
- REP: how many repeats were done for a CONFIG.

> envT\$res

```
Y
               CUTOFF1 CLASSWT2
                                      XPERC SEED STEP CONFIG REP
  -80.66667 0.6160287 8.143644 0.9500583 1236
                                                            1
  -77.33333 0.3870275 9.631080 0.9114447 1236
                                                    0
                                                                1
  -71.33333 0.2636683 13.205968 0.9399057 1236
                                                            3
                                                    0
                                                                1
  -76.66667 0.5369056 14.286117 0.9857516 1236
                                                    0
                                                                1
  -69.33333 0.7396785 10.203108 0.9723459 1236
                                                    0
                                                            5
                                                                1
                                                            6
6
  -70.66667 0.3264214 7.332868 0.9660157 1236
                                                    0
                                                                1
                       5.100756 0.9212448 1236
                                                            7
7
  -69.33333 0.1994577
                                                    0
                                                                1
  -54.00000 0.1001375 6.198328 0.9995300 1236
                                                    0
                                                            8
                                                                1
  -80.00000 0.5198881 12.832352 0.9488441 1236
                                                    0
                                                           9
                                                                1
10 -79.33333 0.6618317 11.971008 0.9080284 1236
                                                    0
                                                           10
                                                                1
11 -76.00000 0.6160287 8.143644 0.9500583 1237
                                                           1
                                                    1
                                                                1
12 -78.66667 0.5378022 12.584936 0.9530634 1236
                                                           11
                                                                1
13 -78.66667 0.5378022 12.584936 0.9530634 1237
                                                           11
                                                                2
                                                    1
14 -80.66667 0.4854926 12.055882 0.9491663 1236
                                                           12
                                                                1
                                                    1
15 -79.33333 0.4854926 12.055882 0.9491663 1237
                                                           12
                                                                2
                                                    1
16 -73.33333 0.6527187 12.708480 0.9063501 1236
                                                           13
                                                                1
                                                    1
17 -76.66667 0.6527187 12.708480 0.9063501 1237
                                                                2
                                                           13
                                                    1
18 -82.66667 0.5198881 12.832352 0.9488441 1237
                                                           9
                                                                1
19 -79.33333 0.4602900 11.756751 0.9545721 1236
                                                           14
                                                                1
20 -78.00000 0.4602900 11.756751 0.9545721 1237
                                                    2
                                                           14
                                                                2
21 -80.66667 0.6530202 12.215844 0.9574122 1236
                                                    2
                                                           15
                                                                1
22 -80.00000 0.6530202 12.215844 0.9574122 1237
                                                           15
                                                                2
23 -78.00000 0.5514645 12.624498 0.9086569 1236
                                                    2
                                                           16
                                                                1
24 -80.00000 0.5514645 12.624498 0.9086569 1237
                                                    2
                                                           16
                                                                2
25 -77.33333 0.4912961 11.326311 0.9611196 1236
                                                           17
                                                                1
```

```
26 -84.66667 0.4912961 11.326311 0.9611196 1237
                                                           17
27 -82.00000 0.5236395 11.964197 0.9307988 1236
                                                     3
                                                           18
                                                                1
28 -81.33333 0.5236395 11.964197 0.9307988 1237
                                                     3
                                                           18
                                                                2
29 -81.33333 0.4928852 13.998331 0.9564483 1236
                                                     3
                                                           19
                                                                1
30 -82.00000 0.4928852 13.998331 0.9564483 1237
                                                     3
                                                           19
                                                                2
```

Let's explain the res example above (which is truncated after STEP=3): In the first step (STEP=0) 10 configurations (design points) are generated by LHS and tested on the data mining task with SEED=1236. It turns out that CONFIG=4 has the lowest Y=-86.00.

In the next step (STEP=1), three new configurations 11,12,13 are generated (using a metamodel built upon the previous step) and all of them are evaluated with two repeats (SEED=1236,1237). To make a fair comparison, CONFIG=4 is evaluated a second time (SEED=1237). In all cases, the configurations are judged by the **average** Y of the two repeats, which are in this case

CONFIG	<y></y>
4	-84.00
11	-81.00
12	-79.00
13	-81.33

This means that CONFIG=4 survives STEP=1 as the best configuration. Now the next step (STEP=2) starts, where three new configurations $14{,}15{,}16$ are evaluated for two repeats. In this case CONFIG=14 gets an even better average Y = 84.66.

The information which configuration is the best one in each step of the tuning algorithm is contained as a summary in data frame envT\$bst. Most columns have exactly the same meaning as in data frame envT\$res, with the addition of the new column COUNT which gives the number of repeats being executed for CONFIG at the beginning of STEP.

> envT\$bst

	Y	CUTOFF1	CLASSWT2	XPERC	COUNT	CONFIG	STEP
4	-86.00000	0.5369056	14.28612	0.9857516	1	4	1
41	-84.00000	0.5369056	14.28612	0.9857516	2	4	2
14	-84.66667	0.5364093	14.43284	0.9608062	2	14	3
141	-84.66667	0.5364093	14.43284	0.9608062	2	14	4
142	-84.66667	0.5364093	14.43284	0.9608062	2	14	5
143	-84.66667	0.5364093	14.43284	0.9608062	2	14	6
144	-84.66667	0.5364093	14.43284	0.9608062	2	14	7
145	-84.66667	0.5364093	14.43284	0.9608062	2	14	8

We see that CONFIG=4 is with Y=-86.00 the best configuration at the beginning of STEP=1. At the beginning of STEP=2 this is reduced to Y=-84.00 due to the 2nd repeat, but CONFIG=4 is still the best. At the beginning of STEP=3 however, CONFIG=14 takes over with Y=-84.66 (average of 2 repeats) and it remains the best configuration until the end.

Note: Although the aim of the tuner is to minimize Y, we might sometimes see an increase in Y in the sequence of rows in envT\$bst. This can be the case if we go from a lower COUNT to

a higher COUNT. The reason is that at COUNT=1 we may have a 'lucky' validation set which produces a small Rgain for a certain CONFIG. If we repeat the run with another seed (another validation set), the same CONFIG may result in a higher Rgain, so that the 'lucky' Y for that CONFIG cannot be confirmed at COUNT=2. The higher COUNT has the statistically more sound value for Y.

References

- Thomas Bartz-Beielstein. SPOT: An R package for automatic and interactive tuning of optimization algorithms by sequential parameter optimization. arXiv.org e-Print archive, http://arxiv.org/abs/1006.4645, June 2010.
- N. Hansen. The CMA evolution strategy: a comparing review. In J.A. Lozano, P. Larranaga, I. Inza, and E. Bengoetxea, editors, Towards a new evolutionary computation. Advances on estimation of distribution algorithms, pages 75–102. Springer, 2006.
- Patrick Koch and Wolfgang Konen. Efficient sampling and handling of variance in tuning data mining models. In Carlos Coello Coello, Vincenzo Cutello, et al., editors, *PPSN'2012: 12th International Conference on Parallel Problem Solving From Nature, Taormina*, pages 195–205, Heidelberg, September 2012. Springer. URL http://www.gm.fh-koeln.de/ciopwebpub/Koch12a.d/Koch12a.pdf.
- Patrick Koch and Wolfgang Konen. Subsampling strategies in sym ensembles. In Frank Hoffmann and Eyke Hüllermeier, editors, *Proceedings 23. Workshop Computational Intelligence*, pages 119–134. Universitätsverlag Karlsruhe, 2013. URL http://www.gm.fh-koeln.de/~konen/Publikationen/kochGMA2013.pdf.
- Patrick Koch, Bernd Bischl, Oliver Flasch, Thomas Bartz-Beielstein, Claus Weihs, and Wolfgang Konen. Tuning and evolution of support vector kernels. *Evolutionary Intelligence*, 5:153-170, 2012. URL http://www.gm.fh-koeln.de/~konen/Publikationen/Koch11a-EvolIntel.pdf.
- Patrick Koch, Tobias Wagner, Michael T. M. Emmerich, Thomas Bäck, and Wolfgang Konen. Efficient multi-criteria optimization on noisy machine learning problems. *Applied Soft Computing*, (accepted for publication):1, 2014.
- W. Konen and P. Koch. The TDMR Package: Tuned Data Mining in R. Technical Report 02/2012, Research Center CIOP (Computational Intelligence, Optimization and Data Mining), Cologne University of Applied Science, Faculty of Computer Science and Engineering Science, 2012a. URL http://www.gm.fh-koeln.de/ciopwebpub/Kone12a.d/Kone12a.pdf. Last update: March, 2015.
- W. Konen and P. Koch. The TDMR Tutorial: Examples for Tuned Data Mining in R. Technical Report 03/2012, Research Center CIOP (Computational Intelligence, Optimization and Data Mining), Cologne University of Applied Science, Faculty of Computer Science and Engineering Science, 2012b. URL http://www.gm.fh-koeln.de/ciopwebpub/Kone12b.d/Kone12b.pdf. Last update: March, 2015.

- W. Konen, P. Koch, O. Flasch, and T. Bartz-Beielstein. Parameter-Tuned Data Mining: A General Framework. In *Proc. 20th Workshop Computational Intelligence*, pages 136–150. KIT Scientific Publishing, http://digbib.ubka.uni-karlsruhe.de/volltexte/1000020316, 2010. URL http://www.gm.fh-koeln.de/~konen/Publikationen/GMACI10_tunedDM.pdf.
- W. Konen, P. Koch, O. Flasch, T. Bartz-Beielstein, M. Friese, and B. Naujoks. Tuned data mining: A benchmark study on different tuners. In Natalio Krasnogor, editor, GECCO '11: Proceedings of the 13th Annual Conference on Genetic and Evolutionary Computation, volume 11, pages 1995–2002, 2011.
- Wolfgang Konen. Self-configuration from a machine-learning perspective. CIOP Technical Report 05/11; arXiv: 1105.1951, Research Center CIOP (Computational Intelligence, Optimization and Data Mining), Cologne University of Applied Science, Faculty of Computer Science and Engineering Science, May 2011. URL http://www.gm.fh-koeln.de/ciopwebpub/Kone11c.d/Kone11c.pdf.e-print published at http://arxiv.org/abs/1105.1951 and Dagstuhl Preprint Archive, Workshop 11181 "Organic Computing Design of Self-Organizing Systems".
- M. D. McKay, R. J. Beckman, and W. J. Conover. A comparison of three methods for selecting values of input variables in the analysis of output from a computer code. *Technometrics*, 21 (2):239–245, 1979.
- M.J.D. Powell. A new algorithm for unconstrained optimization. United Kingdom Atomic Energy Authority, 1970.
- D.F. Shanno. On Broyden-Fletcher-Goldfarb-Shanno method. Journal of Optimization Theory and Applications, 46(1):87–94, 1985.
- T. Sing, O. Sander, N. Beerenwinkel, and T. Lengauer. ROCR: visualizing classifier performance in R. *Bioinformatics*, 21(20):3940–3941, 2005. URL http://rocr.bioinf.mpi-sb.mpg.de/.
- Jörg Stork, Ricardo Ramos, Patrick Koch, and Wolfgang Konen. SVM ensembles are better when different kernel types are combined. In Berthold Lausen, editor, European Conference on Data Analysis (ECDA13). GfKl, 2013. URL http://www.gm.fh-koeln.de/~konen/Publikationen/storkECDA-2013.pdf.