# CS 107e Sound / Floating Point Numbers

Monday, Mar 9, 2025


Computer Systems from the Ground Up Winter 2025
Stanford University
Computer Science Department


$$V = (-1)^s \times M \times 2^E$$

Single precision (float)

31 30 23 22 0

s exp frac







## Today's Topics

- Logistics
  - Next week: Final projects!
  - Project presentations: Friday, March 21st, 9am-12pm
- Today: (Fake) Sound / Floating Point Numbers
  - Demos: I2S Microphone / MIDI
  - Real Numbers
  - Fixed Point
  - IEEE 754 Floating Point
    - Normalized values
    - Denormalized values
    - Exceptional values
    - Arithmetic





### 12S Microphone Demo

- Last week, Julie demonstrated I2S output (playing a .wav file converted into a C array). You can do this in two different ways:
  - Blocking: the sound plays, but your program is only playing sound. This is useful for short sounds that may indicate completion of a task, or an alert.
  - Non-blocking: Using DMA, the sounds plays while your program continues. This is useful for background sound (e.g., for a game).
- In addition to output I2S devices, you can also get input I2S microphones. These are inexpensive, and allow you to record sound.




### The output device:






Teyleten Robot PCM5102 PCM5102A AUX Stereo Digital Audio DAC Decoder Board Module Voice Module Player Module Digital-to-Analog Converter IIS I2S

\$6 on amazon.com (or by two for \$9)



### The microphone:





Adafruit I2S MEMS Microphone Breakout - SPH0645LM4H (\$12 on amazon.com)



INMP441 Omnidirectional Microphone Module MEMS I2S Interface (five for \$13 on amazon.com)

#### MIDI

#### MIDI: Musical Instrument Digital Interface

- Simple interface to control musical instruments
- Emerged from electronic music and instruments in 1970s
- First version described in Keyboard magazine in 1982




#### MIDI

### MIDI: Musical Instrument Digital Interface


- 31.25 kbps 8-N-1 serial protocol
- Commands are 1 byte, with variable parameters
- (c=channel, k=key, v=velocity, l=low bits, m=high bits)

Command	Code	Param	Param
Note on	1001ccc	0kkkkkk	0vvvvvv
Note off	1000ccc	0kkkkkk	0vvvvvv
Pitch bender	1110ccc	0111111	Ommmmmm



#### MIDI Circuit

0 is high, I is low!




Optocoupler completely isolates circuits electrically: no noise in instrument




#### MIDI Hack


If we don't have an optocoupler, we can do okay with an additional  $220\Omega$  resistor:













(can we go forever?)



(can we go forever?)

Nope! (not in C, at least)



(what about negative numbers?)



### Integer Representations

The C language has two different ways to represent numbers, unsigned and signed:


unsigned: can only represent non-negative numbers

signed: can represent negative, zero, and positive numbers



In C, we have the following integer types, with their bit size for the Mango Pi (C does not explicitly define anything but char, which is always 1 byte):

type	bits	bytes	min	max
char	8	1	-128	127
unsigned char	8	1	0	255
short	16	2	-32768	32767
unsigned short	16	2	0	65535
int	32	4	-2147483648	2147483647
unsigned int	32	4	0	4294967295
long	64	8	-9223372036854775808	9223372036854775807
unsigned long	64	8	0	18446744073709551615
long long	64	8	-9223372036854775808	9223372036854775807
unsigned long long	64	8	0	18446744073709551615



# Unsigned Integers

For positive (unsigned) integers, there is a 1-to-1 relationship between the decimal representation of a number and its binary representation. If you have a 4-bit number, there are 16 possible combinations, and the unsigned numbers go from 0 to 15:

0b0000 = 0	0b0001	= 1	0b0010 =	2	0b0011	=	3
0b0100 = 4	0b0101	= 5	0b0110 =	6	0b0111	=	7
0b1000 = 8	3 0b1001	= 9	0b1010 =	10	0b1011	=	11
0b1100 = 1	0b1101	= 13	0b1110 =	14	0b1111	=	15

The range of an unsigned number is  $0 \rightarrow 2^w - 1$ , where w is the number of bits in our integer. For example, a 32-bit int can represent numbers from 0 to  $2^{32} - 1$ , or 0 to 4,294,967,295.

What if we want to represent negative numbers? We have choices!

One way we could encode a negative number is simply to designate some bit as a "sign" bit, and then interpret the rest of the number as a regular binary number and then apply the sign. For instance, for a four-bit number:

```
0\ 001 = 1 1\ 001 = -1

0\ 010 = 2 1\ 010 = -2

0\ 011 = 3 1\ 011 = -3

0\ 100 = 4 1\ 100 = -4

0\ 101 = 5 1\ 101 = -5

0\ 110 = 6 1\ 110 = -6

0\ 111 = 7 1\ 111 = -7
```

This might be okay...but we've only represented 14 of our 16 available numbers...

0.001 = 1

1001 = -1

0.010 = 2

1010 = -2

0.011 = 3

1011 = -3

0.100 = 4

 $1\ 100 = -4$ 

0.101 = 5

 $1\ 101 = -5$ 

0.110 = 6

1110 = -6

0.111 = 7

 $1 \ 1111 = -7$ 

What about 0 000 and 1 000? What should they represent?

Well...this is a bit tricky!



0.001 = 1	1001 = -1	What about 0 000 and 1 0	00? What	should
0.010 = 2	1010 = -2	they represent?		
0.011 = 3	1011 = -3			
0.100 = 4	$1\ 100 = -4$	Wellthis is a bit tricky!		
0.101 = 5	$1\ 101 = -5$			
0.110 = 6	$1 \ 110 = -6$	Let's look at the bit patterns:	$\cap \cap \cap$	1 000
0.111 = 7	$1 \ 111 = -7$	Let 3 look at the bit patterns.	0 000	1 000

Should we make the 0 000 just represent decimal 0? What about 1 000? We could make it 0 as well, or maybe -8, or maybe even 8, but none of the choices are nice.



0.001 = 1	1001 = -1	What about 0 000 and 1 0	00? What	should
0.010 = 2	1010 = -2	they represent?		
0.011 = 3	1011 = -3			
0.100 = 4	$1\ 100 = -4$	Wellthis is a bit tricky!		
0.101 = 5	$1\ 101 = -5$			
0.110 = 6	$1 \ 110 = -6$	Let's look at the bit patterns:	$\cap \cap \cap$	1 000
0.111 = 7	1 111 = -7	Let 5 100k at the bit patterns.	0 000	1 000


Should we make the 0 000 just represent decimal 0? What about 1 000? We could make it 0 as well, or maybe -8, or maybe even 8, but none of the choices are nice.

Fine. Let's just make 0 000 to be equal to decimal 0. How does arithmetic work? Well...to add two numbers, you need to know the sign, then you might have to subtract (borrow and carry, etc.), and the sign might change...this is going to get ugly!





Behold: the "two's complement" circle:




In the early days of computing\*, two's complement was determined to be an excellent way to store binary numbers.

In two's complement notation, positive numbers are represented as themselves (phew), and negative numbers are represented as the two's complement of themselves (definition to follow).

This leads to some amazing arithmetic properties!

\*John von Neumann suggested it in 1945, for the EDVAC computer.




A two's-complement number system encodes positive and negative numbers in a binary number representation. The weight of each bit is a power of two, except for the most significant bit, whose weight is the negative of the corresponding power of two.


Definition: For vector  $ec{x} = [x_{w-1}, x_{w-2}, \dots, x_0]$  of an w-bit integer  $x_{w-1}x_{w-2}\dots x_0$  is given by the following formula:

$$B2T_w(ec{x}) = -x_{w-1}2^{w-1} + \sum_{i=0}^{w-2} x_i 2^i.$$

 $B2T_w$  means "Binary to Two's complement function"

In practice, a negative number in two's complement is obtained by inverting all the bits of its positive counterpart\*, and then adding 1.






In practice, a negative number in two's complement is obtained by inverting all the bits of its positive counterpart\*, and then adding 1, or: x = -x + 1

Example: The number 2 is represented as normal in binary: 0010

-2 is represented by inverting the bits, and adding 1:



\*Inverting all the bits of a number is its "one's complement"



Trick: to convert a positive number to its negative in two's complement, start from the right of the number, and write down all the digits until you get to a 1. Then invert the rest of the digits:

Example: The number 2 is represented as normal in binary: 0010


Going from the right, write down numbers until you get to a 1:

10

Then invert the rest of the digits: 1110



\*Inverting all the bits of a number is its "one's complement"




To convert a negative number to a positive number, perform the same steps!

Example: The number -5 is represented in two's complements as: 1011


5 is represented by inverting the bits, and adding 1:

Shortcut: start from the right, and write down numbers until you get to a 1:

Now invert all the rest of the digits: 0101



## Two's Complement: Neat Properties



There are a number of useful properties associated with two's complement numbers:


- 1. There is only one zero (yay!)
- 2. The highest order bit (left-most) is 1 for negative, 0 for positive (so it is easy to tell if a number is negative)
- 3. Adding two numbers is just...adding! Example:

$$2 + -5 = -3$$

1101 -3 decimal (wow!)



## Two's Complement: Neat Properties




More useful properties:

4. Subtracting two numbers is simply performing the two's complement on one of them and then adding. Example:

$$4 - 5 = -1$$

Find the two's complement of 5: 1011 add:




## Two's Complement: Neat Properties

#### -8

More useful properties:

5. Multiplication of two's complement works just by multiplying (throw away overflow digits).

Example: 
$$-2 * -3 = 6$$










$$\frac{1}{3} = 0.33333...$$



$$\frac{1}{3} = 0.33333...$$

When I was in 6th grade, this was a mind blowing concept.




#### Fractions



#### Real Numbers

$$\pi = 3.14159...$$

And don't get me started on this




#### Real Numbers

Once we leave the realm of integers, real numbers become ... tricky.

- Some rational numbers, e.g.,  $\frac{1}{5}$ , can be represented exactly, by a fixed number of decimal digits (0.2 in this case)
- Some rational numbers, e.g., ½, can not be represented exactly, and we have this idea of "repeating indefinitely," which we represent with "..." (0.33333...)
- Irrational numbers can never be represented by a fixed number of decimal digits, and the meaning of "..." means "indefinitely" but loses the "repeating" part.
   Irrational numbers can never be represented exactly using a digit notation.

The big question: how do we represent real numbers in a computer?



### Real Numbers in a Computer

#### The big question: how do we represent real numbers in a computer?

As always, we have choices. Here are some constraints:

- 1. We want to represent real numbers in a fixed number of bits. This means that we aren't going to be able to represent all real numbers exactly, nor even all rational numbers exactly. Furthermore, we can't even represent all rational numbers in a range exactly (there are infinitely many rational numbers in any fixed range).
- 2. We want to represent a large range of numbers.
- 3. We want to be able to perform calculations on the numbers.



### Real Numbers in a Computer

#### One idea: Fixed Point

When we represented integers, we implicitly placed the decimal point (or binary point, in base 2) after the least significant digit, and we limited ourselves to positive powers of our base. E.g., 1234 is really 1234.0000...

We could just move the decimal place, and use that as our system for representing real numbers:

In decimal:  $d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$  e.g., 123.45

$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

What range of numbers can we represent now?



$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

What range of numbers can we represent now? 0 to 999.99



$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

What range of numbers can we represent now? 0 to 999.99

What is the "precision" we can represent (i.e., how precise?)



$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

What range of numbers can we represent now? 0 to 999.99
What is the "precision" we can represent (i.e., how precise?)
we can represent five decimal digits of precision,
to the 100<sup>th</sup> place



$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

We can't represent some rational numbers exactly:

123.456

123.333...

1000 (overflow? Also, 999.991, or 999.9901, or 999.99001, or ...)

0.001 (underflow?)

We would have to round or truncate, or over/under-flow.

$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

Fixed-point arithmetic is pretty easy:

123.45

+678.90

802.35



$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

e.g., 123.45

Fixed-point arithmetic is pretty easy:

123.45 +678.90 802.35

```
100.22
* 1.08
  80176
 00000
1002200
1082376 = 108.2376
        = 108.24
        (rounded)
```



$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

Fixed point has its uses, but it is somewhat limiting. We can do regular arithmetic, and we know how many decimal places of precision we get.

However, the range is set by where we fix the decimal place, and we had hoped for a large range. If we set the decimal place to be to the left of the most significant digit for a five-digit number, our range would only be 0 to 0.99999.

## Floating Point

A different idea is to represent numbers in the form  $V=x\times 2^y$ 

In this form, we will break our number into two parts (actually, three, including a sign bit), with an exponent (y) and a fractional value (x).


Before we get into the details, let's investigate what fractional values in binary look like. Recall, in decimal:

$$d_2d_1d_0.d_{-1}d_{-2} = d_2 \times 10^2 + d_1 \times 10^1 + d_0 \times 10^0 + d_{-1} \times 10^{-1} + d_{-2} \times 10^{-2}$$

Digits after the decimal point are represented by negative powers of 10.

In binary, digits after the *binary* point are represented by negative powers of *two*:

$$b_2b_1b_0.b_{-1}b_{-2} = b_2 \times 2^2 + b_1 \times 2^1 + b_0 \times 2^0 + b_{-1} \times 2^{-1} + b_{-2} \times 2^{-2}$$



Online binary to decimal converter:

http://web.stanford.edu/class/cs107e/float/



Example: 101.11 in binary:

$$1 \times 2^{2} + 0 \times 2^{1} + 1 \times 2^{0} + 1 \times 2^{-1} + 1 \times 2^{-2} = 4 + 0 + 1 + \frac{1}{2} + \frac{1}{4} = 5\frac{3}{4}$$

What happens to your number if you shift the binary point to the left by one?



Example: 101.11 in binary:

$$1 \times 2^{2} + 0 \times 2^{1} + 1 \times 2^{0} + 1 \times 2^{-1} + 1 \times 2^{-2} = 4 + 0 + 1 + \frac{1}{2} + \frac{1}{4} = 5\frac{3}{4}$$

What happens to your number if you shift the binary point to the left by one?

The number is divided by two.



Example: 101.11 in binary:

$$1 \times 2^{2} + 0 \times 2^{1} + 1 \times 2^{0} + 1 \times 2^{-1} + 1 \times 2^{-2} = 4 + 0 + 1 + \frac{1}{2} + \frac{1}{4} = 5\frac{3}{4}$$

What happens to your number if you shift the binary point to the left by one?

The number is divided by two.

What happens to your number if you shift the binary point to the right by one?



Example: 101.11 in binary:

$$1 \times 2^{2} + 0 \times 2^{1} + 1 \times 2^{0} + 1 \times 2^{-1} + 1 \times 2^{-2} = 4 + 0 + 1 + \frac{1}{2} + \frac{1}{4} = 5\frac{3}{4}$$

What happens to your number if you shift the binary point to the left by one?

The number is divided by two.

What happens to your number if you shift the binary point to the right by one?

The number is multiplied by two.



Example: 101.11 in binary:

$$1 \times 2^{2} + 0 \times 2^{1} + 1 \times 2^{0} + 1 \times 2^{-1} + 1 \times 2^{-2} = 4 + 0 + 1 + \frac{1}{2} + \frac{1}{4} = 5\frac{3}{4}$$


What happens to your number if you shift the binary point to the left by one?

The number is divided by two.

What happens to your number if you shift the binary point to the right by one?

The number is multiplied by two.

What is represented by 0.111111...1?



Just like decimal with numbers like  $\frac{1}{3}$  and  $\frac{1}{6}$ , binary cannot represent exactly any numbers like  $\frac{1}{3}$  and  $\frac{1}{5}$ , nor even  $\frac{1}{6}$ :

```
#include "printf.h"
#include "ftoa.h"
void main() {
    char buf[256];
    float f = 0.1;
    // convert to a string,
    // with 20 decimal
    // places of precision
    ftoa(f,buf,20);
    printf("f: %s\n",buf);
```

```
$ ./testTenth
0.10000000149011611938
```

Fractional binary notation can only exactly represent numbers that can be written in the form:

$$x \times 2^y$$



# IEEE Floating Point

When designing a number format, choices need to be made about the format specification. In the late 1970s, Intel sponsored William Kahan (from Berkeley...) to design a floating point standard, which formed the basis for the "IEEE Standard 754," or *IEEE Floating Point*, which almost all computers use today. The standard defines the bit pattern (32-bit, 64-bit, etc.) as a number in the form:

$$V = (-1)^s \times M \times 2^E$$

#### Where:

- The sign s is negative (s == 1) or positive (s == 0), with the sign for numerical value 0 as a special case.
- The significand M (sometimes called the Mantissa), is a fractional binary number that ranges either between 1 and  $2-\epsilon$  or between 0 and  $1-\epsilon$ .
- The exponent E weights the value by a (possibly negative) power of 2.

### IEEE Floating Point Examples

$$V = (-1)^s \times M \times 2^E$$

Example: For s=0, M=1.5, E=9:  $V = (-1)^0 \times 1.5 \times 2^9 = 768$ 



## IEEE Floating Point


$$V = (-1)^s \times M \times 2^E$$

The bit representation of a floating point number is divided into three fields to encode these values:

- The single sign bit s directly encodes the sign s.
- The k-bit exponent field,  $\exp = e_{k-1} \dots e_1 e_0$  encodes the exponent E.
- The *n*-bit fraction field  $\operatorname{frac} = f_{n-1} \dots f_1 f_0$  encodes the significand M, but the value encoded also depends on whether or not the exponent field equals 0.

Single precision (float)

S	exp	frac
---	-----	------



#### Before We Continue

Single precision (float)


Single precision (float)

Single precision (float)

Right now, you're saying to yourself, "Uhh...this is going to be complicated."



#### Before We Continue



Right now, you're saying to yourself, "Uhh...this is going to be complicated."

Yes, it does take some time to learn. We want you to appreciate a few things about the IEEE floating point format:

- 1. It is based on decisions and choices that were made, with good reason (we will discuss those reasons).
- 2. It is efficient, and attempts to eek out as much as it can from those 32 or 64 bits computing is often about efficiency, and the people who came up with the standard really thought hard about it.
- 3. We don't want you to think "I could never come up with that!" rather, we want you to appreciate it for what it is.

#### Normalized Floats

Single precision (float)

Single precision (float)

Single precision (float)

- •A float is considered to have a "normalized" value if the exponent is not all 0s and it is not all 1s, and is the most common case (e.g., bits 23-30 are not the value 0 or the value 255).
- •The *exponent* is a *signed integer* in **biased** form. The exponent has a value exp bias, where the "bias" is  $2^{k-1}$  1, and where k is the number of bits in the exponent (k=8 for floats, meaning that the bias is  $2^7$  1 = 127). For floats, the exponent range is -126 to +127.
- •The *fraction* is interpreted as having a fractional value f, where  $0 \le f < 1$ , and having a binary representation of  $0.f_{n-1} \cdots f_1 f_0$ , with the binary point to the left of the most significant bit.
- •The significand is defined to be M = 1 + f. This is **an implied leading 1** representation, and a trick for getting an additional digit for free!



### An extra bit of precision for free?

Single precision (float)


Single precision (float)

s exponent (8 bits)

fraction (23 bits)

- •Yes! We can always adjust the exponent so that the significand is in the range  $1 \le M < 2$  (assuming no overflow), so we don't need to explicitly represent the leading bit, because it is always 1 (very cool!)
- •Remember, the designers of IEEE Floating Point wanted the best system, and this is a cool idea.

- Sign: 0 (positive)
- •Exponent: 011111110 = 126 (biased), so exponent of 2 will be 126 127 = -1
- •Fraction: 0, which is assumed to be 1.0 (binary), which is 1.0 decimal
- •Therefore, this number represents  $+1.0 \times 2^{-1} = 0.5$  (to the converter!)



- Sign: 0 (positive)
- •Exponent: 10000100 = 132 (biased), so exponent of 2 will be 132 127 = 5
- •Fraction: 0101, which is assumed to be 1.0101 (binary), which is:

$$1 \times 2^{0} + 0 \times 2^{-1} + 1 \times 2^{-2} + 0 \times 2^{-3} + 1 \times 2^{-4} = 1.3125$$

•Therefore, this number represents  $+1.3125 \times 2^5 = 42.0$  (to the converter!)

https://www.h-schmidt.net/FloatConverter/IEEE754.html

http://web.stanford.edu/class/cs107e/float/

- •Sign: 0 (positive)
- •Exponent: 10000100 = 132 (biased), so exponent of 2 will be 132 127 = 5
- •Fraction: 01011, which is assumed to be 1.01011 (binary), which is:

$$1 \times 2^{0} + 0 \times 2^{-1} + 1 \times 2^{-2} + 0 \times 2^{-3} + 1 \times 2^{-4} = 1.34375$$

•Therefore, this number represents  $+1.34375 \times 2^5 = 43.0$  (to the converter!)



Single precision (float)

Single precision (

- •Sign: 1 (negative)
- •Exponent: 10000101 = 133 (biased), so exponent of 2 will be 133 127 = 6
- •Fraction: 1001, which is assumed to be 1.1001 (binary), which is:

$$1 \times 2^{0} + 1 \times 2^{-1} + 0 \times 2^{-2} + 0 \times 2^{-3} + 1 \times 2^{-4} = 1.5625$$

•Therefore, this number represents -1.5625 x  $2^6 = -100.0$  (to the converter!)



Single precision (float)

Single precision (float)

s exponent (8 bits) fraction (23 bits)

•Example:

Sign: 0 (positive)

•Exponent: 01111010 = 122 (biased), so exponent of 2 will be 122 - 127 = -5

•Fraction: 1001, which is assumed to be 1.1001 (binary), which is:

$$1 \times 2^{0} + 1 \times 2^{-1} + 0 \times 2^{-2} + 0 \times 2^{-3} + 1 \times 2^{-4} = 1.5625$$

•Therefore, this number represents  $+1.5625 \times 2^{-5} = 0.048828125$ 

(to the converter!)



Take a look at this example:

```
void main()
{
    double a = 0.1;
    double b = 0.2;
    double c = 0.3;
    double d = a + b;
    printf("0.1 + 0.2 == 0.3 ? %s\n", a + b == c ? "true" : "false");
}
```

```
0.1 + 0.2 == 0.3? false
```

The rounding that happens during the calculation of 0.1 + 0.2 produces a different number than 0.3!

```
#include "printf.h"
#include "ftoa.h"
void main() {
   double a = 0.1;
   double b = 0.2;
   double c = 0.3;
   double d = a + b;
   char bufa[30],bufb[30],bufc[30],bufd[30];
   ftoa(a,bufa,20);
   ftoa(b,bufb,20);
   ftoa(c,bufc,20);
   ftoa(d,bufd,20);
    printf("0.1 + 0.2 == 0.3 ? %s\n", a + b == c ? "true" : "false");
    printf("0.1:\t%s\n",bufa);
   printf("0.2:\t%s\n",bufb);
   printf("0.3:\t%s\n",bufc);
    printf("a + b:\t%s\n",bufd);
```



Here is another example:



Here is another example:

```
16777224.0f == 16777225.0f ? true
```

It turns out that 16777225 is an integer that you cannot represent as a 32-bit float.




- The IEEE Floating Point Standard was a carefully thought-out way to get the most out of a discrete set of bits. It may not be simple, but it is a great study in good engineering design.
- Floating point numbers represent a very large range, in a limited number of bits. A 32-bit float can only hold a bit over 4 billion numbers and has a range of -3.4E-38 to +3.4E+38. Not only is this literally an infinite number of reals that the format must try and represent, but that is a phenomenal range of numbers. The 64-bit double range is -1.7E-308 to +1.7E+308 (!)
- Most numbers are, therefore, only represented approximately in float format, including many integers. Example:
  - 1 trillion = 1,000,000,000,000, and in 32-bit floating point, it is actually represented by the value 999,999,995,904, off by 4096!
  - You almost certainly don't want to use floats for currency!



## Floating Point Takeaways

- You have to be very careful with your arithmetic when you are dealing with floats:
  - Associativity does not hold for numbers far apart in the range.
  - Many numbers are not exact (e.g., 0.1, 0.4, etc.)
  - Equality comparison operations are often unwise.



#### References and Advanced Reading

- References:
  - IEEE 754: <a href="https://en.wikipedia.org/wiki/IEEE">https://en.wikipedia.org/wiki/IEEE</a> 754
  - IEEE Floating point: <a href="http://steve.hollasch.net/cgindex/coding/ieeefloat.html">http://steve.hollasch.net/cgindex/coding/ieeefloat.html</a>
  - Floating point arithmetic: <a href="https://en.wikipedia.org/wiki/Floating-point">https://en.wikipedia.org/wiki/Floating-point</a> arithmetic#Dealing with exceptional cases
- Advanced Reading:
  - Comparing floats using equality: <a href="https://stackoverflow.com/questions/">https://stackoverflow.com/questions/</a>
     1088216/whats-wrong-with-using-to-compare-floats-in-java
  - Floating point converter: <a href="https://www.h-schmidt.net/FloatConverter/">https://www.h-schmidt.net/FloatConverter/</a>
     IEEE754.html
  - What Every Computer Scientist Should Know About Floating-Point Arithmetic
  - Floating point rounding errors: <a href="https://softwareengineering.stackexchange.com/questions/101163/what-causes-floating-point-rounding-errors">https://softwareengineering.stackexchange.com/questions/101163/what-causes-floating-point-rounding-errors</a>
  - Why do we have a bias in floating point exponents?