#### CSC4200/5200 - COMPUTER NETWORKING


**Instructor: Susmit Shannigrahi** 

### **INTERNET PROTOCOL (IP)**

sshannigrahi@tntech.edu

GTA: dereddick42@students.tntech.edu






### So far...

- We are forwarding packets between different LANs
- Spanning tree algorithm for preventing loops

## **Switching**


- Switch
  - A mechanism to interconnect links to form a large network
  - Forward frames
  - Separate the collision domains
  - Filter packets between LANs
  - Connects two or more LAN segments Bridging



LAN 1
Collision domain 1

**Collision domain 2** 

LAN 2




Host E

Switch 2

Host F

## How do we create a spanning tree?

- Message (Y, d, X) (to, distance, from)
- 4 thinks it's the root
- Sends (4, 0, 4) to 3 and 5
- Receives (3,0,3) from 3
  - Sets it to as the root since 3 < 4</li>
- Receives (3,1,5) from 5
  - Sees that this is a longer path to 3
  - 2 hops vs direct path (1 hop)
  - Removes 4-5 link from the tree
- Does not scale!




## **ATM (Carries Cells, not Money)**

- ATM (Asynchronous Transfer Mode)
  - Connection-oriented packet-switched network
- Packets are called cells
- 5 byte header + 48 byte payload
- Fixed length packets are easier to switch in hardware
- · Why?

## **ATM (Carries Cells, not Money)**


- ATM (Asynchronous Transfer Mode)
  - Connection-oriented packet-switched netw
  - Packets are called cells
  - 5 byte header + 48 byte payload
- Fixed length packets are easier to switch in hardware
  - Simpler to design
  - Enables parallelism
- Still used in long distance private links




kurose/ross


### **IP Suite - From the First Lecture**

### **Network Topology**



#### **Data Flow**






wikipedia


### **Internet Protocol (IP)**

- What is an internetwork?
  - An arbitrary collection of networks interconnected to provide some sort of hosthost to packet delivery service



### **But that's what switches are for - No?**

- Switches create networks, Routers connect different networks.
- Typically switches are at Layer 2, Routers are at Layer 3
- Switches forward **FRAMES**, Routers forward **PACKETS**




### **But that's what switches are for - No?**

- This room → Point-to-point link
- This room + next room → Switch
- This room + next room + foundation hall → Switches with VLAN
- This university + Internet → Router
- Good for conceptualization not always as simple

## Internetworking Protocol (IP)

- What is an internetwork?
  - An arbitrary collection of networks
  - provide some sort of host-host to packet delivery service




# Every device has a MAC – Why do we need another address?

- Ethernet (MAC) addresses are flat
- Not the only link layer
- Not related to network topology
  - Remember we are still connecting to hosts!
  - How do we go from: 52:54:00:86:38:14 to tntech?
  - Other reasons?


# Global Address in IP – Each node has an unique address

- A 32 bit number in quad-dot notation
- Identifies an Interface
  - A host might have several interfaces!!!




### IP allows the network to scale!

• What if addresses were arbitrary?



## **Solution - Group hosts**

• What if addresses were arbitrary?



### IP addresses are in Network + Host


- 1.1.2.1 →
  - 1.1 → Network part
  - 2.1 → host part
- Each octet can range from 1- 255
- Hierarchical address

**129.82.138.**254

10000001.01010010.10001010.111111110

Network part (24 bits). Host part(8 bits)






# How do we know host vs network → Subnetting

**129.82.138**.254 (Address)


10000001.01010010.10001010.111111110 111111111.111111111.111111111.00000000

255.255.255.0 (Subnet mask)

#### 1.1.2.1 <del>5.1.6.7</del>



## Subnetting



#### Forwarding Table at Router R1

SubnetNumber	SubnetMask	NextHop
128.96.34.0	255.255.255.128	Interface 0
128.96.34.128	255.255.255.128	Interface 1
128.96.33.0	255.255.255.0	R2


## Subnetting

#### Three classes:

Class A: 129.0.0.0/8

Class B: 129.82.0.0/16


Class C: 129.82.2.0/14



SubnetNumber	SubnetMask	NextHop
128.96.34.0	255.255.255.128	Interface 0
128.96.34.128	255.255.255.128	Interface 1
128.96.33.0	255.255.255.0	R2

## Well, not really!

- CIDR: Classless Interdomain routing
- subnet portion of address of arbitrary length
- address format: a.b.c.d/x, where x is # bits in subnet portion of address
  - 129.82.13.0/23
  - More flexible



Subnet number: 128.96.33.0

SubnetNumber	SubnetMask	NextHop
128.96.34.0	255.255.255.128	Interface 0
128.96.34.128	255.255.255.128	Interface 1
128.96.33.0	255.255.255.0	R2

## Now routers can operate on Network address!!!!


129.82.138.254 (Address)

129.82.138.252

149.149.2.254

255.255.255.0 (Subnet mask)


**129.82.138.254** + **255.255.255.0** → **129.82.138.0**/24



## Address management is localized

No coordination needed for adding 129.82.138.251

No routing update needs to go out



149.149.2.254

## Address management can be automated


ARP:

Map IP address to MAC address

DHCP:

Learn IP address, gateway, DNS


More on these later.



# You have an address – Send data now. IP service model

- Packet Delivery Model
  - Connectionless model for data delivery
- Best-effort delivery (unreliable service)
  - packets are lost
  - packets are delivered out of order
  - duplicate copies of a packet are delivered
  - packets can be delayed for a long time
- Global Addressing Scheme
  - Provides a way to identify all hosts in the network

### **IP Packet**



Version (4): 4

Hlen (4): number of 32-bit words in header

TOS (8): type of service (not widely used)

Length (16): number of bytes in this datagram

Ident (16): used by fragmentation

Flags/Offset (16): used by fragmentation

TTL (8): number of hops this datagram has traveled


Protocol (8): demux key (TCP=6, UDP=17)


Checksum (16): of the header only


DestAddr & SrcAddr (32)

**Underlying Layer 2 limitations** 

- Ethernet 1500
- PPP 512
- Break packets into smaller chunk and reassemble later








wikipedia

**Underlying Layer 2 limitations** 

- Ethernet 1500
- PPP 512
- Break packets into smaller chunk and reassemble later



## **Next Steps**

Routing