Address Space Utilization

Kameswari Chebrolu

All the figures used as part of the slides are either self created or from the public domain with either 'creative commons' or 'public domain dedication' licensing. The public sites from which some of the figures have been picked include: http://commons.wikimedia.org (Wikipedia, Wikimedia and workbooks); http://www.sxc.hu and http://www.pixabay.com

Recap

- Hierarchical addressing based on classes (A,B,C) to handle scalability and different network sizes
 - IP address has a network part and a host part
 - Routers maintain entries corresponding to network portion
- What can potentially go wrong now?

Problem Statement

- Network part uniquely identifies a physical network
- Network with just 2 hosts needs Class C address
 - Efficiency: $2/2^8 = 0.7\%$
- Network with 256 hosts needs a Class B address
 - Efficiency: $256/2^{16} = 0.4 \%$

Problem Statement

- Class B addresses in high demand (keeping future needs in mind)
 - Host addresses \sim 4 billion (2³²)
 - Class B networks: 2¹⁴ (~16000)
 - Out of class B addresses, out of addresses to hand out
- Need to solve "Address assignment inefficiency"
 - Challenge: Within IP framework (using 32-bits)

"The gem cannot be polished without friction, nor man perfected without trials."

---Chinese proverb

"You see a mousetrap; I see free cheese and a ***** challenge!"

---Scroobius Pip

Specific Scenario –1

- An organization has 30 different physical networks, each network has about 2000 hosts
- Current Allocation: Allocate 30 class B addresses
 - Efficiency = $2000/2^{16} = 3\%$
- Will one class B address suffice?
 - Can support $2^{16} = 65536 \text{ hosts} > 30*2000$

Solution: Subnetting

- Introduce another level of hierarchy
 - Divide host part into subnet id and host id

| Network Number | Host Number | | | |
|----------------|--------------------|---------|--|--|
| Network Number | Subnet ID | Host ID | | |

16 host bits divided into 5 subnet bits (32 physical networks) and 11 host bits (2048 hosts)

- Address format: a.b.c.d/x, where x is # bits in net portion of address
- Example: 190.23.12.17, mask is 255.255.248.0 (/21)

• ifconfig eth0 190.23.12.17 netmask

- 255.255.255.240
 The bit-wise end of the IP address and the subnet mask give the subnet number of the host
- All hosts on a given physical network have the same subnet number and mask

Class B Address: 101111110. 000101111. *. *; 190.23.0.0/16

| | Subnet ID | Subnet No | Hosts |
|------------|-----------|--------------|-------------------------------|
| 32 Subnets | 00000 | 190.23.0.0 | 190.23.0.1 - 190.23.7.254 |
| | 00001 | 190.23.8.0 | 190.23.8.1 - 190.23.15.254 |
| | | | |
| | 11111 | 190.23.248.0 | 190.23.248.1 - 190.23.255.254 |

- All routers outside organization have one entry (190.23.0.0/16)
- Routers within organization have more detailed entries corresponding to different subnets

Forwarding at a Router

D = Destination IP Address

For each forwarding table entry

T = D & SubnetMask


If T == SubnetNum

Else

If Nexthop is an interface deliver datagram directly to destination

deliver datagram to NextHop (router)

Example



| kameswari@aste Kernel IP rout | | | | | | |
|----------------------------------|------------------|-------------|-------|--------|-----|-----------|
| Destination | Gateway | Genmask | Flags | Metric | Ref | Use Iface |
| TO: TEO: O: O | * | 255.255.0.0 | U | 1 | 0 | 0 eth0 |
| link-local | * | 255.255.0.0 | U | 1000 | 0 | 0 eth0 |
| default | router.it.iitb. | 0.0.0.0 | UG | 0 | 0 | 0 eth0 |
| kameswari@aste | rix:~\$ | | | | | |
| kameswari@aste | rix:~\$ | | | | | |
| kameswari@aste | rix:~\$ route -n | | | | | |
| Kernel IP rout | ing table | | | | | |
| Destination | | Genmask | Flags | Metric | Ref | Use Iface |
| 10.129.0.0 | 0.0.0.0 | 255.255.0.0 | U | 1 | 0 | 0 eth0 |
| 169.254.0.0 | 0.0.0.0 | 255.255.0.0 | U | 1000 | 0 | 0 eth0 |
| 0.0.0.0 | 10.129.250.1 | 0.0.0.0 | UG | 0 | 0 | 0 eth0 |
| kameswari@aste | rix:~\$ | | | | | |



Specific Scenario -- 2

- An organization has a physical network with 4000 hosts
- Current Solution: Give a class B address
- Efficiency: $4000/2^{16} = 6\%$
- How about assigning multiple class C addresses?
- Problem: 16 entries for same organization in the routing table

Solution--2

- Assign multiple contiguous class C addresses
 & aggregate
- 222.7.16.* through 222.7.31.*, top 20 bits in this range are the same (0001 bits, 20-bit network number)
 - Advertise 222.7.16/20 as the organization's network address
 - Goes by the name supernetting

Conclusions

- Subnetting: One class address shared among many physical networks
- Supernetting: Multiple class addresses shared among one physical network (Autonomous system -- AS)
- Network portion can take on any length

Classless Interdomain Routing (CIDR)

- Use a new notation to represent network numbers (also called IP prefixes)
- Address block represented as A/X, where A is the address prefix and X is the prefix length
 - X can range from 2 till 32
 - X is represented as a network mask as well
- E.g. 222.7.16/20 (Mask 255.255.240.0) represents addresses in the range 222.7.16.0 to 222.7.31.255

Longest Prefix Match

- Routers do a prefix match.
 - Does destination address fall in the range of addresses captured by prefix?
- Prefix match works if Internet topology is a tree
 - Shortest path between networks is unique
- Internet is a graph
 - Many networks multi-home
 - Many matching prefixes

Example

• Two prefixes in a forwarding table 190.23.8.0/21 and 190.23.0.0/16

• Go with the longest prefix match (e.g 190.23.8.0/21)

Address 190.23.8.1 matches both

• Challenge: Longest match between destination IP address and variable length prefixes in forwarding

Lot of research in this space

table

Summary

- Class based addressing was found not to be scalable
- Subnetting: Share a single class address among multiple networks
- Supernetting: Share multiple class addresses on a single network
- Lead to CIDR (classless addressing) and Longest prefix match --- widely used now