TCP Congestion Control Mechanisms

Kameswari Chebrolu

Seminal Paper: Congestion Avoidance and Control by Van Jacobson and Michael J. Karels

All the figures used as part of the slides are either self created or from the public domain with either 'creative commons' or 'public domain dedication' licensing. The public sites from which some of the figures have been picked include: http://commons.wikimedia.org (Wikipedia, Wikimedia and workbooks); http://www.sxc.hu and http://www.pixabay.com

Congestion Control: Challenge



- Need to estimate W (of sliding window) such that each flow gets its fair share
 - Estimate small → underutilization; Estimate large → Congestion
- W will vary over time
- Congestion Control: Preventing sources from sending too much data too fast and thereby 'congest' the network

Idea


- View network as a pipe
- Estimate Bandwidth-delay product (capacity) dynamically
 - Uses the variable Congestion Window (CW) to track it
- Use self clocking to pump packets into the network

Approach

- Getting to Equilibrium
- Conservation at equilibrium
- Adapting to Path


Getting to Equilibrium

- What value of CW to choose initially?
 - Too large: pushes network into congestion
 - Just right: bursty transmissions can lead to losses



Slow Start

- Add a variable cwnd (congestion window)
 - Captures the number of outstanding data in the network
- At start, set cwind=1
- On each ack for new data, increase cwnd by 1



Conservation at Equilibrium

- Don't put a packet unless a packet is removed
 - Particularly important when the network is congested
 - Can potentially happen on timeouts → proper RTT estimation crucial
 - Delayed packets should not be interpreted as lost

RTT Estimation: Original Algorithm

- Measure SampleRTT for sequence/ack combo
- EstimatedRTT = a*EstimatedRTT + (1-a)*SampleRTT
 - Small a heavily influenced by temporary fluctuations
 - Large a not quick to adapt to real changes
 - a is between 0.8-0.9
- Timeout = 2 * EstimatedRTT

Jacobson/Karels Algorithm

- Algorithm takes into account variance of RTTs
 - If variance is small, EstimatedRTT can be trusted
 - If variance is large, timeout should not depend heavily on EstimatedRTT

- Difference = SampleRTT EstimatedRTT
- EstimatedRTT = EstimatedRTT + (d * Difference)
- Deviation = Deviation + d (|Difference| Deviation)), where d ~ 0.125
- Timeout = u * EstimatedRTT + q *Deviation, where u = 1 and q = 4
- Exponential Timeout backoff: controls spacing between retransmits

Exponential Damping

- From control theory: An unstable system can be stabilized by adding exponential damping
- "A network subject to random load shocks and prone to congestive collapse can be stabilized by adding exponential damping to its primary excitation (Traffic sources)"

Adapting to Path

- Estimating process can over or underestimate W; need to correct this
- Available bandwidth also changes over time;
 need to adapt to this
- Need a feedback mechanism from the network that the estimate is wrong

Overestimation

- Overestimation leads to congestion
- Feedback: If losses are due to congestion and timers are working correctly → Timeout indicates congestion ✓
 - How to change the congestion window?
 - Additive decrease or multiplicative decrease?
 - Multiplicative decrease yields better stability

•
$$W_i = dW_{i-1}$$
 (d<1, typically 0.5)

Underestimation

$$\omega = 5^{-1}$$


• Underestimation leads to lower utilization

- Additive increase or multiplicative increase?
 - Exponential increase leads to instability; overestimation is inevitable
 - Additive increase
 - $W_i = W_{i-1} + u$ (u << W_{max} ; typical u is 1)
 - Increase window by 1 segment every RTT

Congestion Avoidance

- Additive Increase, Multiplicative Decrease
- On detecting congestion, set cwnd to half the window size (multiplicative decrease)
- On each ack of new data, increase cwnd by 1/cwnd (additive increase)

RTT- Cound by 1 segment ~



Time \rightarrow

Summary

- Congestion control is a difficult task
 - Prevent underutilization; ensure no congestion; ensure fairness
- TCP relies on a variety of techniques to achieve this
 - Slow start, RTT estimation, Congestion avoidance (AIMD)
- Ahead: Putting it all together in TCP versions