

PEOPLE SYSTEM

OVERVIEW

The People System handles keeping track of how many people the player has created, if there are enough residences for the people, and if there are enough employees for factories. Please note that the system that controls the little people that wander around the map is a separate system called the *People Movement System*. For information on that system, see [People_Movement_System.pdf](#).

The primary script involved in the people system is `PeopleManager.cs`. Other important scripts involved in the people's user interface include `PeoplePanel.cs` and `PressPeopleButton.cs`.

HOW THE PEOPLE SYSTEM WORKS

The `PressPeopleButton` script sits on the people button UI game object. It tracks when the people button is pressed down and allows the player to hold down the button. Whenever it's pressed, it calls the `PeopleButtonPressed()` function of the people panel.

The `PeoplePanel` class is in charge of updating all the information on the people panel, and whenever the people button says it's been pressed, the people panel tells the people manager to add a person and then updates all of the information displayed to the player. This means updating the people count, the flow fill amount, and the unemployment count.

The people manager keeps track of the maximum number of people there can be, based on how many activated residences there are. Every time a residence is activated or deactivated, it tells the People Manager to add or



subtract its residential capacity from the max people count. That way, when the People Manager is told to attempt to add a person when the people button is pressed, it can check to see if there is enough room to add the person. Only if there is will it increase the people count by one.

HOW EMPLOYEES ARE TRACKED

While people aren't tied to specific residences, they are tied to specific workplaces (there are currently two workplace tiles in the game by the way: coal plants and wind turbines). This is because if there aren't enough employees for all the workplaces, some workplaces must be disabled.

Every time the number of people or workplaces changes, the people manager redistributes the employees amongst all the workplaces. It does this by using the Tile Type Tracker System (see associated doc) to get a list of all the workplaces currently in the game. Starting with the current total number of people, it gives each workplace the number of employees it requires until the manager runs out of people; once it runs out, 0 employees are given to the remaining workplaces. The `CheckTileForActivation()` function is then run on each of the workplaces, which forces them to activate or deactivate depending on if they have enough employees.

INTERNAL API

PeopleManager.cs

The People Manager can be reached with this singleton: `PeopleManager.current`

```
public int NumberOfPeople
```

Returns the current number of people the player has added to the world.

```
public int NumberOfEmployees
```

Returns the current number of people that are employed in workplaces.

```
public void AdjustMaxPeople(int numOfPeople)
```

Adjusts how many people there are room for by the input “numOfPeople”. It’s called by residences whenever they’re activated or deactivated.

```
public void AttemptToAddPerson()
```

Checks to see if there’s room to add a person. If there is, it will add a person.

```
public bool CanAddMorePeople()
```

Returns true if there’s enough room to add more people; returns false if there’s not.

PeoplePanel.cs

The People Panel can be reached with this singleton: `PeoplePanel._peoplePanel`

```
public void PeopleButtonPressed()
```

Attempts to tell the People Manager to add a person. If that fails, it displays an error. This function is called by the people button.

```
public void EnablePeoplePanel()
```

Enables the people panel. This is called by the progression manager whenever people are unlocked.

-Graydon Bruyn, May 2026