LOG IN REGISTER SUBSCRIBE SHOP HELP 0 items Search

SOUND ON SOUND

NEWS FORUM

MAGAZINE REVIEWS

TECHNIQUES

PEOPLE

SOUND ADVICE

MUSIC BUSINESS

HOME > TECHNIQUES >

Practical Percussion Synthesis: Timpani

Synth Secrets

• Synthesizers > Synth Secrets, Synthesis / Sound Design

By Gordon Reid

Published December 2001

Building on the theory of what makes up the sound of timpani, this month's Synth Secrets reveals how to synthesize realistic kettle drums using a Korg MS20 and a Yamaha DX7.

Last month, I spent the whole of Synth Secrets introducing the various families of percussion instruments, and conducting a detailed analysis of one small sub-class of these: the pitched membranophones. This month, having primed you with all the theory of kettle drums (or timpani), I'll investigate a number of ways to translate what you have learned into practical synthesis.

More About Spectrograms

I'll start with last month's Figure 11, reproduced here as Figure 1. This is a simplified and idealised spectrogram of the sound of a single kettle drum being struck once.

Spectrograms are very useful because, although drawn in two dimensions, they represent all three dimensions of sound: time, frequency, and loudness. OK, it's easy to see the time and frequency axes, but where is the loudness information? Well, in my diagram it's represented by the brightness of the red at any given point on the chart. I'll give you an example: the point marked '1' in Figure 2 represents a sound of frequency 150Hz, measured 0.1 seconds after the start of the spectrogram, with an intensity of around 95 percent of maximum amplitude. Likewise, the point marked '2' represents a component of frequency 750Hz, 0.3 seconds after the start of the spectrogram, with an intensity of about 35




Figure 1: [top-left] A simplified spectrogram of the sound of a kettle drum. Figure 2: [top-right] Understanding the spectrogram. Figure 3: [bottom-left] Striking the same kettle drum three times.

percent. Of course, it's highly unlikely that all the components of the sound would start at the same amplitude, but I'll address that issue later.

Now that you understand what Figure 1 is telling you, you should be able to 'see' how a single strike of the kettle drum sounds. You should also be able to hypothesise that the sound produced by striking the drum three times (thus re-energising the sound on each occasion) will look like Figure 3.

Modelling Timps — Pitched Modes

These spectrograms give a strong clue about how to model the sound of timpani. As you can see, Figure 3 depicts five strong partials in the sound, plus a wash of frequencies that decay more quickly than those partials.

I don't know about you, but Figure 3 screams 'additive synthesis' to me. I first introduced this in part 14 of this series (see SOS June 2000), at the end of which I drew the block diagram shown

In this article...

- Introduction
- More About Spectrograms
- Modelling Timps Pitched Modes
- Table 1
- Table 2
- Modelling Timps Enharmonic Modes
- Table 3
- Sometimes Digital Is Best...
- The Korg MS20
- A Better MS20 Patch
- More Patching Ideas

In this Series

- Synth Secrets: all 63 Parts on Sound On Sound site
- What's In A Sound?
- The Physics Of Percussion
- Modifiers & Controllers
- Of Filters & Phase Relationships
- Further With Filters
- Of Responses & Resonance
- Envelopes, Gates & Triggers
- More About Envelopes
- An Introduction To VCAs
- Modulation
- Amplitude Modulation
- An Introduction To Frequency Modulation
- More On Frequency Modulation
- An Introduction To Additive Synthesis
- An Introduction To ESPs & Vocoders
- From Sample & Hold To Sample-rate Converters

 (1)
- From Sample & Hold To Sample-rate Converters (2)
- Priorities & Triggers
- Duophony
- Introducing Polyphony
- From Polyphony To Digital Synths
- From Springs, Plates & Buckets To Physical Modelling
- Formant Synthesis
- Synthesizing Wind Instruments
- Synthesizing Brass Instruments

in Figure 4. This architecture may look complex, but it's not. Starting from the left, there's a single trigger which, in the real world, will be provided by a keyboard. This trigger initiates the action of six contour generators. Four of these control the gain of Amplifiers 1 to 4, which pass the outputs from Oscillators 1 to 4. The other two control the cutoff frequency of a filter and the gain of an amplifier that, in turn, determine the tone and loudness of the contribution of a noise generator.




Figure 4: [left] An additive synthesizer, as introduced in Part 14 of this series. Figure 5: [top-right] The decay times of the first nine kettle drum partials. Figure 6: [bottom-right] An approximation to the relative amplitudes of the major kettle drum partials.

Let's now choose the frequencies and waveforms for the oscillators. This is simple: you know from last month that the relative frequencies of the first four radial modes are as shown in Table 1, so, if you know the frequency of the principal 1,1 mode, you can calculate the frequencies of the others.

Table 1

Table 1: The most important partials of a real kettle drum.

MODE	FREQUENCY relative to principal of Timpani
1,1	1.00
2,1	1.50
3,1	1.98
4,1	2.44

Measurements of real timpani show that the principal frequency of a large kettle drum is higher than you might expect. In these days of super-deep analogue thumps and almost subsonic bass, a kettle drum has a (not particularly deep) principal frequency of around 150Hz. This is all you need to work out the frequencies of the first four modes (they're shown in Table 2). Furthermore, because I'm talking about individual modes of vibration, the waveforms are sine waves.

Table 2

Table 2: The frequencies of the first four kettle drum partials.

MODE	FREQUENCY relative to principal of Timpani	FREQUENCY in Hz
1,1	1.00	150
2,1	1.50	225
3,1	1.98	297

- Brass Synthesis On A Minimoog
- Roland SH101 & ARP Axxe Brass Synthesis
- Synthesizing Plucked Strings
- The Theoretical Acoustic Guitar Patch
- A Final Attempt To Synthesize Guitars
- Synthesizing Percussion
- Practical Percussion Synthesis: Timpani
- Synthesizing Drums: The Bass Drum
- Practical Bass Drum Synthesis
- Synthesizing Drums: The Snare Drum
- Practical Snare Drum Synthesis
- Analysing Metallic Percussion
- · Synthesizing Realistic Cymbals
- Practical Cymbal Synthesis
- Synthesizing Bells
- Synthesizing Cowbells & Claves
- Synthesizing Pianos
- Synthesizing Acoustic Pianos On The Roland JX10 [Part 1]
- Synthesizing Acoustic Pianos On The Roland JX10 [Part 2]
- Synthesizing Acoustic Pianos On The Roland JX10 [Part 3]
- Synthesizing Strings: String Machines
- Synthesizing Strings: PWM & String Sounds
- Synthesizing Bowed Strings: The Violin Family
- Practical Bowed-string Synthesis
- Practical Bowed-string Synthesis (continued)
- Articulation & Bowed-string Synthesis
- Synthesizing Pan Pipes
- Synthesizing Simple Flutes
- Practical Flute Synthesis
- Synthesizing Tonewheel Organs: Part 1
- Synthesizing Tonewheel Organs: Part 2
- Synthesizing Hammond Organ Effects
- Synthesizing The Rest Of The Hammond Organ: Part 1
- Synthesizing The Rest Of The Hammond Organ: Part 2
- From Analogue To Digital Effects
- Creative Synthesis With Delays
- More Creative Synthesis With Delays
- The Secret Of The Big Red Button


SOS Competitions

WIN! Milab VIP-60 Microphone
WIN! Best Service The Orchestra Complete 2,
by Sonuscore
WIN! Apogee Duet 3 Bundle

4,1 2.44

Now let's consider contour generators 1 to 4. Looking at the spectrogram, it's clear that each should generate a simple Attack/Decay/Release contour with Attack = 0, and equal Decay/Release rates (ensuring that each contour completes its decay whether you hold the key or release it before each note is concluded). However, it's also clear that the four contours should have different values for the Decay/Release.

Figure 5 above shows idealised decay times for the first nine modes, of which the ones in red are the quasi-harmonic partials. Now, I happen to know (because I drew the diagram) that the relative decay/release times for the first four quasi-harmonic partials are approximately 45 percent, 73 percent, 91 percent, and 84 percent respectively. You might think that this is all the information you need before defining the precise contour for each mode, but before you can determine these, you need to know the relative amplitudes of each. For that, I refer you back to another of last month's diagrams, reproduced here as Figure 6.



Figures 7(a) to 7(d): The contours of the four most important modes.

This diagram suggests that amplitude ratios of approximately 5:4:3:1 would be appropriate for the first four modes. Knowing this, you can set your four contour generators as shown in Figures 7(a) to (d).

Modelling Timps — Enharmonic Modes

Now that you've defined the components supplying the pitched part of the sound, you need to define the burst of noise at its start.

Here's an admission: last month I was lazy. Instead of drawing myriad little lines of low amplitude to represent all the enharmonic modes generated when you hit a kettle drum, I used my graphics package to draw something similar: a burst of white noise. But that's not what you get when you strike a membrane. You get myriad enharmonic partials. So what can you do to emulate this correctly? The solution is surprisingly simple. You can use a ring modulator (a form of amplitude modulation, 'AM') or frequency modulation, 'FM'.

Let's consider ring modulation, simply because this is the means most likely to lie at your disposal. If you cast your mind back to part 11 of this series (see (see SOS March 2000), you'll remember that this is a special case of Amplitude Modulation. As such, it uses two signals (which I'll call '1' and '2'), and produces side-bands according to the complex equation shown below, where w1 is the frequency of signal 1, w2 is the frequency of signal 2, a1 is the amplitude of signal 1, and a2 is the amplitude of signal 2.


If the modulator and carrier signals are merely sine waves (which, remember, have no harmonics), the result is not very useful; it's simply the carrier, plus two signals of frequency (w1 + w2) and (w1 - w2). However, if you set both the modulator and the carrier to be harmonically rich sawtooth waves, the result is two complete harmonic series that interact according to that complex equation.

Let me demonstrate the consequences of this by calculating a matrix that shows the 50 partials generated by the interaction of just the first five harmonics of each waveform (see Table 3).

Table 3

Table 3: The first 25 partials generated by amplitude modulation of two signals with frequencies 100Hz and 87Hz.

		FREQUENCIES	OF FIRST	FIVE 100HZ	CARRIER	HARMONICS	
			100	200	300	400	500
FREQUENCIES	87	W1+W2	187	287	387	487	587



Readers' Ads

VIEW ALL ADS CREATE FREE AD

On the same subject

- The Secret Of The Big Red Button July 2004
- More Creative Synthesis With Delays June 2004
- Creative Synthesis With Delays May 2004
- From Analogue To Digital Effects April 2004
- Synthesizing The Rest Of The Hammond Organ: Part 2 March 2004

From the same manufacturer

- ARP 2600 M April 2022
- April 2022
- Korg Collection 3
 February 2022
- Korg Modwave
- September 2021
- Korg SQ-64 May 2021
- Korg Nautilus April 2021

SIGN UP TO SOS NEWSLETTERS

Latest SOS Videos



OF FIRST		w ₁ -w ₂	13	113	213	313	413
FIVE 87HZ	174	w ₁ +w ₂	274	374	474	574	674
MODULATOR		W1-W2	74	26	126	226	326
HARMONICS	261	W1+W2	361	461	561	661	761
		W1-W2	161	61	39	139	239
	348	w ₁ +w ₂	448	548	648	748	848
		W1-W2	248	148	48	52	152
	435	W1+W2	535	635	735	835	935
		W1-W2	335	235	135	35	65

If I show Table 3 as a chart of frequencies (as in Figure 8, below), you can see that the results are far from harmonic, with many clumps and clusters of partials. All this, and I only calculated the outputs generated by the first five harmonics in each signal. Given that, within the audible 20kHz audio spectrum, there are 230 harmonics of an 87Hz signal, and 200 harmonics of a 100Hz signal, there will be 46,000 partials in the modulated signal. Notwithstanding the tiny amplitudes of most of them, that should do the trick!




Figure 8: The 25 partials shown in Table 3.




Figure 9: Eliminating the unwanted low frequencies in the quasi-noise burst.

Figure 8: [top] The 25 partials shown in Table 3. Figure 9: [bottom] Eliminating the unwanted low frequencies in the quasi-noise burst.

There's just one problem with this result. You should know from last month's discussion that a kettle drum produces just one partial below the principal, but my — albeit arbitrary — choice of 100Hz and 87Hz has generated about a dozen components below 150Hz. Increasing the frequencies of the signals feeding the ring modulator does not alleviate this, so I will place an high-pass filter in the signal path to remove the offending low frequencies (as shown in Figure 9, above). Now you have only to make the Decay/Release of this contour generator suitably short, and you have the desired burst of closely spaced, enharmonic modes that decay quickly after the membrane is struck.

At this point, I should make it clear that the partials generated by ring modulation do not lie at the correct frequencies for a kettle drum. Nonetheless, the effect should be sufficient for your purposes.

It's now time to consider the strength with which the drum's membrane is struck. As explained last month, this affects only the loudness of the sound, so you can emulate this by adding a VCA at the end of the signal chain, perhaps controlling its gain using keyboard velocity (see Figure 10).



Cutting Vinyl At Abbey Road

4 days 23 hours ago.



Your Questions Answered

2 months 1 week ago.



Radiophonic Recording At Eve Studios

3 months 6 days ago.




Figure 10: [top] Controlling the loudness using keyboard velocity. Figure 11: [bottom] Controlling the pitch of the synthesized kettle drum.

Finally, the pitch of the sound must be controlled. You could use the keyboard to 'play' the sound in conventional semitones, but real timpani do not work this way. I therefore propose to use the pitch-bend wheel or a CV pedal to span a range of pitches (say, plus or minus a fifth) and restrict my playing to just one or two notes on the keyboard itself (see Figure 11).

You're now in a position to construct an analogue timpani synth, as shown in Figure 12. The eagle-eyed among you might notice that I've omitted the complex EQ bank that would follow the final amplifier to model the sound dispersion pattern of the real instrument, but I hope you'll forgive me that — it'll help to keep the graphics department at Sound On Sound on my side.

If Figure 12 looks complex, it isn't as bad as you might fear. The 'radial mode' generator comprises 12 modules, but these are just four sets of an oscillator/amplifier/contour generator setup. Likewise, the 'circular mode' generator, pitch controls and final gain are simply Figures 9, 10 and 11 incorporated into the patch.




Figure 12: An analogue kettle drum synthesizer patch.

Sometimes Digital Is Best...

Unfortunately, most of us do not have access to the powerful modular analogue synth needed to create the patch in Figure 12 (above). So, in a moment, I'll demonstrate how a simple and relatively cheap analogue synth can give you a surprisingly accurate imitation of the kettle drum. However, tens of thousands of us have an ideal synth for creating the patch.




Yamaha DX7 digital FM synthesizer.

You may not realise it... but if you own a DX7 or any other six-operator FM synth, you're in business.

Look at algorithm 31 on a DX7... it's the same as Figure 13. Now, remembering that each operator on a DX7 is a sine-wave oscillator with an associated pitch envelope generator, amplitude envelope generator, and amplifier, it's clear that you can use Operators 1 to 4 as the 'radial mode' generators in Figure 12. Indeed, so suiTable is the DX7 that you can type the 1.00:1.50:1.99:2.44 frequency ratios directly into the algorithm.

Similarly, Operators 5 and 6 are equivalent to the 'circular mode' generator in Figure 12. OK, so the DX7 algorithm uses FM to generate its enharmonic frequencies, whereas the analogue patch used a ring modulator, but the effect is much the same. Indeed, FM produces even more components with no harmonic relation to the pitched part of the sound, and is Figure 13: Algorithm 31 from the DX7. arguably even more suiTable than ring modulation.



Using my DX1, I created an approximation to the patch in Figure 12 in a little under five minutes. Even in its rough form, it was remarkably usable.

I then loaded Yamaha's own DX7 timpani patch. Ooh... this uses algorithm 16, has just one carrier, and sounds far better than my first attempt. The difference appears to lie in the realism of the initial part of thesound so, if you want to program the best possible imitation, you'll need to analyse the short-lived enharmonic components more accurately. Unfortunately (or

fortunately, depending upon your fondness for higher maths) a more detailed model of the sound is beyond the scope of Synth Secrets.

So let's now return to the analogue domain and see if it's possible to simplify the patch while still retaining the essence of the desired sound.

The Korg MS20




Figure 14: A simplified representation of the MS20 control panel.

Figure 14 shows in simplified form the control panel of that most popular of vintage synths, the Korg MS20. Normally associated with the squeaks and squeals of modern dance music, this is an under-rated synth for careful, imitative synthesis. The reason for this generally lies in its rather lacklustre 12dB-per-octave filters, which are not ideal for powerful sounds such as brass. Nevertheless, the filters need not always be a limitation, as you will see.

Since the MS20 has just two oscillators, and neither of these produces a sine wave, you can't create the pitched part of Figure 12 as drawn. Nor can the MS20 produce slightly detuned partials. So you must compromise... you need to choose a waveform with just a few strong harmonics, and filter off the rest of them. You can do this by choosing the triangle wave for Oscillator 1, ignoring Oscillator 2, and reducing the low-pass filter cutoff frequency (see Figure 15).

However, you can do better. If you refer back to Figure 6, you'll see that the relative amplitudes of the first three partials are only slightly different. So you can use the MS20's twin filters to sculpt the '1/n2' amplitude relationship of the triangle wave (shown in Figure 16) into something far more akin to the desired shape (see Figure 17).




Figure 15: The MS20 oscillator setting for the kettle drum patch.

Notice in particular how this removes the fundamental of the triangle wave, and ensures that the first four partials have the required 1:1.5:2:2.5 relationship seen in Table 1, rather than 1:2:3:4, as would be the case if the fundamental survived filtering.

You can improve this even further by adding resonance (or 'peak' in Korg-speak) to the filters' cutoff frequencies, further enhancing the contributions from the partials contained in the narrow band of frequencies between the two cutoff frequencies.

But what of the non-pitched partials in the kettle drum sound? You can use Oscillator 2 to provide these if you select the Ring Modulator option and the lowest footage, and then detune the oscillator so that it produces a suitably clangorous tone (I find that something




Figure 16: [left] Applying high-pass and low-pass filters to sculpt the harmonic content of the sound. Figure 17: [right] The output from the filters defined in Figure 16.

in the region of +2 works quite well). You can then mix a little of this with Oscillator 1 to create the desired timbre.

You now create a simple Attack/Decay/ Release envelope using EG2 to shape the amplitude of the note. Remember to set the decay and release times to be equal, so that the sound decays consistently whether you release the key or not. Finally, feed a little of the CV from EG2 to the low-pass filter cutoff frequency. This makes the sound brighter at the start, and reduces the brightness as the volume decays. This is correct: remember that the higher partials in Figures 1, 2 and 3 decayed more rapidly than some of the lower ones, so applying the EG to the low-pass filter overcomes the lack of independent VCAs. The resulting patch appears in Figure 18.




Figure 18: A simple kettle drum patch for the Korg MS20.

Figure 18: A simple kettle drum patch for the Korg MS20.

A Better MS20 Patch

The patch in Figure 18 is very sensitive to tiny changes in certain parameters — particularly the VCO2 pitch and the filter settings — but once set correctly, it can give the impression of a kettle drum. Nonetheless, it's not particularly satisfying. Indeed, considering the care with which I've followed the theory, it's remarkable just how unconvincing it is. I suspect that this is due to the limitations of the MS20's ring modulator, which gives no control over the input signals, so let's cast theory to the wind and see whether another method can produce more convincing results.

If you study Figure 19, you'll see that my next patch (which is Korg's 'factory' timpani patch) uses a pulse wave as its starting point, and that the ring modulator is not detuned. This makes the basic timbre much less clangorous than the patch in Figure 18. Other parts of Figure 19 are more familiar: both filters again have resonance, further emphasising the second, third and fourth harmonics, and EG2 again affects the low-pass filter cutoff frequency.




Figure 19: A more complex kettle drum patch for the Korg MS20.

However, if you play this part of the patch alone, you'll find that it sounds nothing like a kettle drum... it's just a simple bass sound, and not a very good one, at that. But now have a look at the semi-modular patch matrix provided by the MS20, shown on the right-hand side of the diagram.

Look closely, and you'll see that the noise generator is feeding pink noise to the input of the External Signal Processor. This type of noise is already deficient in high frequencies, and the high-pass filter in the ESP is removing the low frequencies, so the result is a narrow band of noise. Furthermore, at the settings shown, the input of the ESP is distorting, so the result is a very 'rough' timbre. This is then directed to the input of the MS20's main filters, where it is even further narrowed and emphasised by the overlapping resonant filters.

The result is a band of highly tuned, somewhat distorted noise that takes the place of the ring-modulated sound in Figure 12, and does so very effectively. Indeed, it sounds remarkably similar to the unpitched sound produced by the kettle drum. If you now add back the pitched partials from the oscillators, the result is extraordinarily life-like, with the sound from the oscillators providing the characteristic 'ringing' of the kettle shell as the sound decays.

Having got this far, you could go on to patch the CV Wheel to the oscillator pitches (as suggested in Figure 12) and develop a number of small performance enhancements. However, lack of space precludes me from doing so here, and this is something that you'll just have to try for yourself.

More Patching Ideas

If you look back to the start of this article, you'll see that I've gone full circle. Having admitted that, in Figure 1, the 'noise' representation of the enharmonic modes is the result of my laziness, it turns out that using a noise generator is indeed a highly satisfactory way to model a kettle drum. But why stop there...?

As I discussed last month, timpani are far from the only pitched membranophones so, if you own an MS20, you should consider using these ideas to create a wide range of pitched drum sounds. This is simply done: take the patches in Figures 18 and 19, and experiment with the pitches, filter settings and envelope times. You should easily create other pitched percussion sounds. However, you must take care not to stray too far from the initial settings; do so, and the character of your sounds will change into something else entirely.

Of course, you can try all of this on other synthesizers, but among low-cost instruments, the MS20 is particularly suiTable because it offers a powerful combination of pitched oscillators, a ring modulator, a noise source, and four filters. Consequently, you won't get the same quality of results from the Minimoog, ARP Axxe or Roland SH101 that I used so successfully for brass patches a few months ago.

So there you have it... proof that the MS20 is good for far more than dancefloor bleeps and bloops. Give it a try!

Previous article		Next article
New forum posts		Active topics
Re: OK? Genelec 8010's.		Need mic help
ef37a Recording: Gear & Techniques	28 Mar 2022, 10:41	Boz Digital Labs The Hoser 71% OFF Ex
Re: New album Rose Garden o	out in a fev	Is Logic Pro backwards compatible?
Arpangel Self-Promotion	28 Mar 2022, 10:41	Using a spare MacMini for soft-synths
Re: Apple unveil Mac Studio a	nd Studio	Roland BTM-1
ien Mac Music	28 Mar 2022, 10:39	Electric Guitar T, Fender's legendary Tel
Re: Using a spare MacMini for	soft-synth	lan Boddy recognition
Folderol		Cutting vinyl at Abbey Road.



Recently active forums

- Forum FAOs
- Recording: Gear & Techniques
- Mixing, Mastering & Post Production
- New Products & Industry News
- Music Business
- Mac Music
- Windows Music
- Apps & Other Computers/OS
- Guitar Technology
- Keyboards & Synthesis
- DIY Electronics & Studio Design
- Live Sound & Performance
- Music Theory, Songwriting & Composition

Practical Percussion Synthesis: Timpani

Mac Music	28 Mar 2022, 10:31	Analog tape transfer to digital	•	User Reviews
Re: Need mic help		Spotify news		Remote Collaboration
				Self-Promotion
blinddrew				Feedback
Recording: Gear & Techniques	28 Mar 2022, 10:18		-	recuback

Contact Us Cookie Policy Help Privacy Policy Terms of Use

All contents copyright © SOS Publications Group and/or its licensors, 1985-2022. All rights reserved.

The contents of this article are subject to worldwide copyright protection and reproduction in whole or part, whether mechanical or electronic, is expressly forbidden without the prior written consent of the Publishers. Great care has been taken to ensure accuracy in the preparation of this article but neither Sound On Sound Limited nor the publishers can be held responsible for its contents. The views expressed are those of the contributors and not necessarily those of the publishers.

Web site designed & maintained by PB Associates & SOS