LOG IN REGISTER SUBSCRIBE SHOP HELP 0 items Search

SOUND ON SOUND

NEWS FORUM

MAGAZINE

REVIEWS TECHNIQUES

**PEOPLE** 

**SOUND ADVICE** 

**MUSIC BUSINESS** 

**HOME > TECHNIQUES >** 

# **Modifiers & Controllers**

Synth Secrets

• Synthesizers > Synth Secrets, Synthesis / Sound Design

By Gordon Reid

Published July 1999

We move on from discussing the <u>harmonic</u> components of sound to explaining how they change over time, and some of the tools subtractive synths give you to emulate this process.

If you have stuck with me for the past two months, you'll know that most natural sounds have complex harmonic structures, and that these derive from the nature of the object making the sound. You'll also appreciate that, no matter how you play them or what you do when you record them, percussion instruments will have significantly different tones from strings, pipes, and other 'conventional' instruments. But this knowledge is far from sufficient to allow you to understand and create the sounds you want artificially, with a synthesizer; you also need to know about the controllers and modifiers that shape the sounds you hear. Look at it this way... if you could define a sound purely by listing all the harmonics it was composed of, manufacturers wouldn't waste money putting all those 'unnecessary' filters and envelope generators and stuff in their products. So let's move on, and find out about how you can tailor a series of synth-derived oscillations into something more musical.

# **Modifying A Sound**

There are no sounds that you can define purely in terms of their harmonic spectra. Even if a sound seems to exhibit a consistent tone and volume, there must have been a moment when it began, and a moment when it will end. This implies that the loudness of the sound is contoured in some fashion.

Ignoring the start and finish for a moment, unvarying tones are called *static* or *stationary* sounds, and they are almost always musically uninteresting. Since no natural sounds are stationary over any significant timescale, the only time you are likely to encounter them is when they have been created by a *signal generator* (such as those found in analogue synthesizers, for example). You can think of these as devices that generate a tone by outputting a fluctuating voltage that is passed through an amplifier and then onwards to a speaker, which converts the voltage into sound that you can hear (see Figure 1).

Let's try to make this idea a bit more meaningful. Imagine that the amplifier in Figure 1 is your hi-fi amp, and that — although the tone generator is generating a signal — the volume knob is turned fully anticlockwise so that you hear no sound. Imagine you now turn the control fully clockwise while the sound is




Figure 1.

playing, and then turn it back anticlockwise again until silence returns.

If you look at Figure 2, you will see that you have added a controller (your manipulation of the knob) that causes the amplifier to modify the audio signal presented to it. But twisting a knob every time you want a non-static sound is hardly sensible, nor are the results precisely reproducible. Moreover, it's quite inappropriate if you are looking to use your tone generator to produce conventional sounds and notes. So you need to replace your fingers with a controller signal that gives predictable, reproducible results each time it is used. And it is this that brings us to the important concept of Voltage Control.

#### In this article...

- Introduction
- Modifying A Sound
- Envelopes
- Low Frequency Oscillators And Tremolo
- And The Point Is ...?

#### In this Series

- Synth Secrets: all 63 Parts on Sound On Sound site
- What's In A Sound?
- The Physics Of Percussion
- Modifiers & Controllers
- Of Filters & Phase Relationships
- Further With Filters
- Of Responses & Resonance
- Envelopes, Gates & Triggers
- More About Envelopes
- An Introduction To VCAs
- Modulation
- Amplitude Modulation
- An Introduction To Frequency Modulation
- More On Frequency Modulation
- An Introduction To Additive Synthesis
- An Introduction To ESPs & Vocoders
- From Sample & Hold To Sample-rate Converters
- From Sample & Hold To Sample-rate Converters
  (2)
- Priorities & Triggers
- Duophony
- Introducing Polyphony
- From Polyphony To Digital Synths
- From Springs, Plates & Buckets To Physical Modelling
- Formant Synthesis
- Synthesizing Wind Instruments
- Synthesizing Brass Instruments
- Brass Synthesis On A Minimoog
- Roland SH101 & ARP Axxe Brass Synthesis
- Synthesizing Plucked Strings
- The Theoretical Acoustic Guitar Patch
- A Final Attempt To Synthesize Guitars
- Synthesizing Percussion

Imagine that the Controller in Figure 2 is another fluctuating voltage of some form. This is called a Control Voltage, or CV. Don't worry, for the moment, about how it is generated; just consider that, for any given voltage applied at the amplifier's 'Controller' input, the Amplifier applies a defined Gain to the signal. This describes a Voltage Controlled Amplifier, or VCA. Now, let's see what you can use to generate these CVs.





Figure 2.

# **Envelopes**

Let's return to the idea of modifying a sound using the volume knob on the front of a hi-fi amplifier. Let's say that, if the knob is turned fully anticlockwise, the applied CV is 0 Volts, and the amplifier's Gain is zero. In other words, silence reigns. At the other extreme, let's say that, if the knob is rotated fully clockwise, the CV is 10V, and the Gain is maximum — ie. the



sound is at its loudest. You could then imagine using the knob to apply varying voltages to create a loudness 'contour' for our sound. For example, the CV could start at 0 Volts, rise to 10V, drop to 5V, linger there for a while, before returning to 0V some time later. This profile is shown in Figure 3.

As you can see, the contour of the CV is identical to the loudness contour. In other words, you have defined the loudness of the sound at any given time using the CV. The shapes in Figure 3 are called Envelopes, so one of the devices that you can use to control our amplifier is, not surprisingly, called an Envelope Generator. EGs may be basic or complex, but (if they are not themselves modified in some way by another signal) they all share one attribute: each time they are initiated (or 'triggered') they provide a consistent contour, both in terms of the CVs produced and the times taken for them to change.

The most famous, and for a long time the most common envelope generators, are called ADSRs. The acronym stands for Attack/Decay/Sustain/Release, and these names represent the four stages of the EG. Three of them — Attack, Decay, and Release — are measures of time, while the fourth — the Sustain — is a voltage level. (See Figure 4.) The ADSR is, in many ways, a stroke of genius and, despite its great simplicity, it provides approximations to the contours of the sounds generated by a huge number of natural instruments.




Figure 4.

For example, imagine the sounds produced by things as different as a pipe organ, a trombone and a thunderclap. Now consider how the loudness contour of each of these can be described in terms of its A, D, S and R stages. Remember:

- The Attack time determines the speed at which the sound reaches its maximum loudness.
- The Decay time determines the speed at which the loudness drops until it reaches...
- ...the <u>Sustain Level</u>, the level the loudness maintains until...
- ...it decays to its final level (usually silence) in a time determined by the Release time.

The organ has a rapid attack and maintains its full volume before dropping to silence when the player releases the key. Hence its loudness contour is almost precisely rectangular. Indeed, this shape has become so closely associated with organs that it is often referred to as an 'organ envelope', even when it is used in sounds that bear no relation to organ itself.

By contrast, the trombone 'speaks' more slowly, and its loudness usually peaks at the end of the attack stage before falling back to a lower, sustained level. When the player stops blowing,

- Practical Percussion Synthesis: Timpani
- Synthesizing Drums: The Bass Drum
- Practical Bass Drum Synthesis
- Synthesizing Drums: The Snare Drum
- Practical Snare Drum Synthesis
- Analysing Metallic Percussion
- Synthesizing Realistic Cymbals
- Practical Cymbal Synthesis
- · Synthesizing Bells
- Synthesizing Cowbells & Claves
- Synthesizing Pianos
- Synthesizing Acoustic Pianos On The Roland JX10 [Part 1]
- Synthesizing Acoustic Pianos On The Roland JX10 [Part 2]
- Synthesizing Acoustic Pianos On The Roland JX10 [Part 3]
- Synthesizing Strings: String Machines
- Synthesizing Strings: PWM & String Sounds
- Synthesizing Bowed Strings: The Violin Family
- Practical Bowed-string Synthesis
- Practical Bowed-string Synthesis (continued)
- Articulation & Bowed-string Synthesis
- Synthesizing Pan Pipes
- Synthesizing Simple Flutes
- Practical Flute Synthesis
- Synthesizing Tonewheel Organs: Part 1
- Synthesizing Tonewheel Organs: Part 2
- Synthesizing Hammond Organ Effects
- Synthesizing The Rest Of The Hammond Organ: Part 1
- Synthesizing The Rest Of The Hammond Organ: Part 2
- From Analogue To Digital Effects
- Creative Synthesis With Delays
- More Creative Synthesis With Delays
- The Secret Of The Big Red Button

#### **SOS Competitions**

WIN! Milab VIP-60 Microphone WIN! Best Service The Orchestra Complete 2, by Sonuscore WIN! Apogee Duet 3 Bundle the sound rapidly falls back to silence.

Quiet different from either of these, the loudness of a thunderclap often develops relatively slowly, and there are no decay or sustain stages; once it has peaked, the loudness dies away slowly.

As you can see from Figure 5, these contours are fundamentally different from one another. Let's take the trombone envelope first. This requires all four ADSR parameters, with moderate attack, decay and release times and a moderate sustain level. The organ envelope is clearly simpler, and requires just three of the ADSR envelope's parameters, with virtually instantaneous attack and release, and a maximum sustain level. In contrast, the thunderclap only utilises two parameters. It has no Sustain or Release values (actually, this isn't always true, but we'll discuss that in a later Part of this series).

However you set the parameters of the envelope generator in your synth, if it is connected to the VCA, it has simply replaced the general term 'controller' in Figure 2. Provided that you can trigger it at will, you have a device that will shape this aspect of your

sound whenever you want (Figure 6).

frequency that is the simplest mode of vibration of the oscillator producing it. If this

fundamental lies in the range of approximately

#### Amplifier **Low Frequency Oscillators And** Tremolo Envelope Let's return for a moment to the concepts Generator relating to oscillators, described in Part 1 of this series (see SOS May 1999). You will remember that every harmonic sound has a fundamental

Figure 6.

20Hz (20 vibrations per second) to 20kHz (20,000 vibrations per second) you should hear the sound as an audible tone.

Now consider again the hi-fi amplifier and its volume knob. If you swing the control from side to side once or twice per second you will introduce a new, periodic effect to the sound: that of tremolo. You are, in essence, applying an oscillator to the hi-fi's volume. And although the frequency of this oscillator is much less than 20Hz, its effect is clearly musically important.

It should come as no surprise, therefore, to find that most synthesizers have dedicated devices — Low-Frequency Oscillators (LFOs) generating low-frequency signals that control many of the synth's other functions. On most instruments, the LFO(s) produce oscillations in a range of frequencies lying between about 0.1Hz (one cycle every ten seconds) and 20Hz. These are suitable for producing relatively simple sonic effects, and as you can see in Figure 7, tremolo is just a more specific




Figure 7. The LFO controls the gain of the amplifier.

example of the setup shown earlier in Figure 2: in this case, it's an LFO rather than an EG controlling the gain of the amplifier.

Trivial though Figure 7 may be to most readers, it also demonstrates the three types of modules present in all synthesizers. In this configuration:

- The Tone Generator is a Signal Generator it produces the basic audio tone;
- The Voltage Controlled Amplifier is an example of a Modifier it changes the audio signal in some way;
- The LFO Sinewave generator is acting as a Controller it is directing the signal-modifying action of the Modifier itself.

But simple as this example is, you can use this architecture to produce some extremely complex sounds. You just need to change one detail in the setup...

#### Modifiers & Controllers





Figure 5: [top-bottom] Trombone, Organ and Thunderclap envelopes.

Trigger



#### Readers' Ads

VIEW ALL ADS **CREATE FREE AD** 

#### On the same subject

- The Secret Of The Big Red Button July 2004
- More Creative Synthesis With Delays
- Creative Synthesis With Delays May 2004
- From Analogue To Digital Effects April 2004
- Synthesizing The Rest Of The Hammond Organ: Part 2 March 2004

#### From the same manufacturer

- ARP 2600 M April 2022
- Korg Collection 3 February 2022
- Korg Modwave September 2021
- Korg SQ-64 May 2021
- Korg Nautilus April 2021

SIGN UP TO SOS NEWSLETTERS

#### Latest SOS Videos



The LFOs on more powerful synths are often capable of producing higher-frequency oscillations that stray well into the audio range. Furthermore, these LFOs often offer a wide range of waveforms. But if you can modulate a signal with an audio-frequency LFO, why can't you use another Tone Generator to do so? Of course, there's no reason why you shouldn't, and the architecture in Figure 8 allows you to create the complex sounds alluded to above.




Figure 8.

# AT ABBEY ROAD

**Cutting Vinyl At Abbey Road** 

4 days 23 hours ago.



**Your Questions Answered** 

2 months 1 week ago.



Radiophonic Recording At Eve Studios

3 months 6 days ago.

### And The Point Is ...?


Although this article has never strayed from the basics, three major concepts have been introduced: Control Voltages, Envelope Generators, and Low Frequency Oscillators. But these are not the most important lessons to learn.

Look again at the diagrams in this article. In each of these the audio signal has been represented by the horizontal arrows, while controlling signals have been shown as vertical arrows. I like to think of these as (i) signals that you hear, and (ii) signals that control what you hear. Obvious, huh? But on the other hand, you must also recognise that in voltage terms, there is actually no difference between these signals. Consequently, many synth modules can act equally as signal generators, modifiers, and controllers, depending only upon where they are placed (and how they are used) within the sound-generating architecture.

In other words: an analogue synth uses fluctuating voltage to represent audio signals and other fluctuating voltages to shape and control them. But it's not a signal's source that is important, it's the destination that determines whether it is best viewed as an audio signal or a controller.

And that is one of the most important synth secrets of them all.

Previous article Next article



New forum posts

Re: OK? Genelec 8010's.

ef37a

Recording: Gear & Techniques 28 Mar 2022, 10:41


Re: New album Rose Garden out in a fev

Arpangel

Self-Promotion 28 Mar 2022, 10:41

Re: Apple unveil Mac Studio and Studio

ien



# Recently active forums

- Forum FAQs
- Recording: Gear & Techniques
- Mixing, Mastering & Post Production
- New Products & Industry News
- Music Business
- Mac Music
- Windows Music
- Apps & Other Computers/OS
- Guitar Technology

| Mac Music                                | 28 Mar 2022, 10:39 | Electric Guitar T, Fender's legendary Tel |
|--|--------------------|---|
| Re: Using a spare MacMini for soft-synth |                    | lan Boddy recognition                     |
| Folderol                                 |                    |   |
| Mac Music                                | 28 Mar 2022, 10:31 | Cutting vinyl at Abbey Road.              |
| Re: Need mic help                        |                    | Analog tape transfer to digital           |
| blinddrew                                |                    | Andrew Cape Consider to digital           |
| Recording: Gear & Techniques             | 28 Mar 2022, 10:18 | Spotify news                              |
|  |                    |   |

- Keyboards & Synthesis
- DIY Electronics & Studio Design
- Live Sound & Performance
- Music Theory, Songwriting & Composition
- User Reviews
- Remote Collaboration
- Self-Promotion
- Feedback

Contact Us Cookie Policy Help Privacy Policy Terms of Use

All contents copyright © SOS Publications Group and/or its licensors, 1985-2022. All rights reserved.

The contents of this article are subject to worldwide copyright protection and reproduction in whole or part, whether mechanical or electronic, is expressly forbidden without the prior written consent of the Publishers. Great care has been taken to ensure accuracy in the preparation of this article but neither Sound On Sound Limited nor the publishers can be held responsible for its contents. The views expressed are those of the contributors and not necessarily those of the publishers.

Web site designed & maintained by PB Associates & SOS