


Rollback to a Standard lets you choose a standard, and then reduces any monitor observations exceeding the standard to the level of the standard:



5.3.1 Example: A Single Rollback in One Region

To apply a monitor rollback, first click the **Create Air Quality Grids** button. On the **Air Quality Grid Creation Method** window, choose *Monitor Rollback*. Click **Next**.


There are three steps to the *Monitor Rollback* method.

1. Select Monitors. Choose the **Rollback Grid Type** from the drop-down list. This allows you to determine how detailed the rollback scenario may be. If the whole region (e.g., United States) will have the same type of rollback then you may simply choose a

grid outlining the area of interest. If you are interested in different rollbacks within a region, then you should choose a more finely detailed grid definition (e.g., states).


If you use data from an existing dataset, then choose the **Library** tab, and from the drop-down list choose the **Monitor Dataset** and the **Monitor Library Year**. If you want to use your own data, then choose the **Text File** tab. The file should have the monitor data format specified in Chapter 4: Loading Data.

When you have finished making your choices, click **Next**.



2. Select Rollback Regions and Settings. In this section, you can specify the type of the rollback method(s) that you would like to use, as well as the location of the monitors that you want to roll back.


Click the **Add Region** button to display the three rollback options: *Percentage Rollback*, *Incremental Rollback*, and *Rollback to a Standard*.



Choosing the **Rollback Type** and click **OK**. Then, specify the amount of the rollback and the region to which you want to apply it. You can click on the map to select and deselect the states (or other defined areas depending on your rollback grid type) to add to the region.

At the top of the map are five GIS toolbar icons, typically seen in mapping programs. The first four tools allow you to zoom in and zoom out, and to focus on the particular groups of grid cells that interest you. The fifth tool allows you to select grid cells graphically, by clicking or dragging a box over them.

In this example, we specified a 10 percent reduction, a background of 0 ppb, and applied it to all monitors in the state of California (by clicking on the particular state in the GIS window).



To apply the rollback to all the states, you can simply click on the **Select All** button. To clear the selections, click the **Deselect All** button. At any time, you can change the grid cells that you have selected. To remove a region from the selection, click the “X” button next to the region ID. This particular example is quite simple, so we will use a more complicated example below.

If you want to export your monitor data to a CSV file, click the option for *Export After Rollback*. The exported data will be formatted in the same specific format required of BenMAP-CE **Monitor Data** import files discussed in Chapter 4.

After defining the **Rollback Regions** and setting the **Rollback Parameters**, click on the **Next** button. BenMAP-CE will then perform the rollback you specified on the monitors in the grid cells that you have chosen.

3. Additional Grid Settings.

The third stage is similar to the *Monitor Data* grid creation method. As with monitor data, you need to specify the **Interpolation Method** (*Closest Monitor*, *VNA*, or *Fixed Radius*) and the **Grid Type**.

By checking the option for *Make Baseline Grid (in addition to Control Grid)* you tell BenMAP-CE to create a baseline grid at the same time as the control grid. The baseline grid uses the same parameters as the control grid, with the exception of the rollback. That is, the baseline uses the same monitor data, interpolation method, and the same grid type. The two resultant grids will serve as both baseline and control scenarios and are automatically selected in the “Air Quality Surfaces” stage of the analysis.