DYEING TEXTILES: GENERAL MORDANT AND DYE PROCESSES

Adapted from Jo Kirby et al, *Natural Colorants for Dyeing and Lake Pigments: Practical Recipes and their Historical Sources* (Archetype, London, 2014)

MORDANT BATH		DYE BATH	
Materials: Mordant Water Textiles Scale Hot plate Glass beaker	☐ Thermometer ☐ Stirring stick ☐ Plate ☐ Strainer ☐ Paper towels	Materials: ☐ Dyestuffs ☐ Mortar and pestle ☐ Drawstring bag ☐ Water ☐ Textiles ☐ Scale	 □ Hot plate □ Glass beaker □ Thermometer □ Stirring stick □ Plate □ Strainer □ Paper towels
Procedure: Measure out water into glass beaker Add mordant and stir Place beaker onto hot plate and turn on to medium-low Using the thermometer, note the temperature. Stir to dissolve mordant in the water Pre-wet textiles with water and wring them out carefully to remove as much water as possible When the mordant solution has reached 70 °C, add the textiles Heat the textiles for 30 minutes at 80-90 °C, stirring occasionally to ensure homogenous absorption by the textiles NOTE: monitor the temperature of the bath, adjusting the hot plate settings as necessary After 30 minutes, remove the textiles from the bath using the strainer Being careful not to damage or felt the textile, wash them with clean water to remove any mordant that has not bound to the textiles Wring out excess water		 Using mortar and pestle, crush dyestuffs to a fine powder or into small pieces Measure out crushed dyestuffs and, using a small utensil, add to the drawstring bag. Close the bag tightly Measure out water into glass beaker, and add dyestuffs bag to the water and "stir" as if you are steeping tea Place beaker onto hot plate, at medium-low Heat the bath (without the textiles) at 80-90 °C for 30 minutes, stirring occasionally NOTE: monitor the temperature of the bath, adjusting the hot plate settings as necessary After 30 minutes, add the textiles If using mordanted textiles, add the wet textiles If using un-mordanted textiles, pre-wet with water and wring them out carefully NOTE: it is common to remove the dyestuffs bag at this point, but you can also leave it in Dye the textiles at 80-90 °C for 30 minutes, stirring occasionally to ensure homogenous dyeing After 30 minutes, remove the textiles from the bath using the strainer Being careful not to damage or felt the textile, wash them with clean water to remove any dye that has not bound to the textiles When the water runs clear over the textiles and no color comes off the textiles, wring out excess water Lay out the textiles on paper towels to dry 	