# Introduction to Networking and Systems Measurements

Lecture 2: Basic Network Measurements




Andrew W. Moore andrew.moore@cl.cam.ac.uk

## Time flies

• 1ns = 20cm in fibre

 10Gb/s is about 10 bits per nanosecond



so at 10Gb/s a 512byte packet is ~ 8meters long

# Ping

- Ping is basically a "are you still there" test
- "connectivity" test
- "how long does it take to get there" test
- "loss approximation" test


```
$ ping www.stanford.edu
PING www.stanford.edu (54.192.2.121): 56 data bytes
64 bytes from 54.192.2.121: icmp_seq=0 ttl=242 time=3.730 ms
64 bytes from 54.192.2.121: icmp_seq=1 ttl=242 time=3.845 ms
...
^C
--- www.stanford.edu ping statistics ---
8 packets transmitted, 8 packets received, 0.0% packet loss
round-trip min/avg/max/stddev = 3.730/3.808/3.849/0.047 ms
```

## PING traps

- Uses ICMP (control messages of the Internet)
- Might not follow the same path as normal packets
- Might be filtered
- A ping test is not the actual round trip time for an application – merely the host-host IP control layer
- One way delay is not simply half round trip time
- Learn by doing (run tcpdump at the same time)

### Recall the Internet federation

- The Internet ties together different networks
  - > >18,000 ISP networks



We can see (hints) of the nodes and links using traceroute...


## Traceroute: Internet debug thy self

- Recall the Internet Zombie plan Time-To-Live (TTL)
- Each router decrements TTL; when TTL =0 send error
   Traceroute artificially sets low TTL and receives the error
   Each step of the path is iteratively discovered



• • •

### Traceroute as we wish...



## But **ONLY** one direction

### "Real" Internet traceroute

traceroute: rio.cl.cam.ac.uk to munnari.oz.au

(tracepath on windows is similar)


Three delay measurements from rio.cl.cam.ac.uk to gatwick.net.cl.cam.ac.uk traceroute munnari.oz.au traceroute to munnari.oz.au (202.29.151.3), 30 hops max, 60 byte packets 1 gatwick.net.cl.cam.ac.uk (128.232.32.2) 0.416 ms 0.384 ms 0.427 ms trans-continent 2 cl-sby.route-nwest.net.cam.ac.uk (193.60.89.9) 0.393 ms 0.440 ms 0.494 ms 3 route-nwest.route-mill.net.cam.ac.uk (192.84.5.137) 0.407 ms 0.448 ms 0.501 ms link 4 route-mill.route-enet.net.cam.ac.uk (192.84.5.94) 1.006 ms 1.091 ms 1.163 ms 5 xe-11-3-0.camb-rbr1.eastern.ja.net (146.97.130.1) 0.300 ms 0.313 ms 0.350 ms 6 ae24.lowdss-sbr1.ja.net (146.97.37.185) 2.679 ms 2.664 ms 2.712 ms 7 ae28.londhx-sbr1.ja.net (146.97.33.17) 5.955 ms 5.953 ms 5.901 ms 8 janet.mx1.lon.uk.geant.net (62.40.124.197) 6.059 ms 6.066 ms 6.052 ms 9 ae0.mx1.par.fr.geant.net (62.40.98.77) 11.742 ms 11.779 ms 11.724 ms 10 ae1.mx1.mad.es.geant.net (62.40.98.64) 27.751 ms 27.734 ms 27.704 ms 11 mb-so-02-v4.bb.tein3.net (202.179.249.117) 138.296 ms 138.314 ms 138.282 ms 12 sg-so-04-v4.bb.tein3.net (202.179.249.53) 196.303 ms 196.293 ms 196.264 ms 13 th-pr-v4.bb.tein3.net (202.179.249.66) 225.153 ms 225.178 ms 225.196 ms 14 pyt-thairen-to-02-bdr-pyt.uni.net.th (202.29.12.10) 225.163 ms 223.343 ms 223.363 ms 15 202.28.227.126 (202.28.227.126) 241.038 ms 240.941 ms 240.834 ms 16 202.28.221.46 (202.28.221.46) 287.252 ms 287.306 ms 287.282 ms 17 \* \* \* \* means no response (probe lost, router not replying) 18 \*\*\* 19 \* \* \* 20 coe-gw.psu.ac.th (202.29.149.70) 241.681 ms 241.715 ms 241.680 ms

21 munnari.OZ.AU (202.29.151.3) 241.610 ms 241.636 ms 241.537 ms


# Traceroute traps – a bit like ping

- Uses UDP or ICMP (but traffic is often TCP)
- Might not follow the same path
- Might be filtered
- Only infers one direction of the path
- Replies can be very weird
- One way delay is **not** simply half round trip time (networks may have many paths)
- Learn by doing (try with and without the –I option)

## Traceroute doesn't always know



## Traceroute lies



## Beyond traceroute

Paris traceroute
 Uses many probes to identify multiple paths
 <u>www.paris-traceroute.net</u>


Reverse traceroute
 Uses a remote server to probe reverse path

## Link capacity.....

- Recall capacity is a property of where and what we measure
- Nominal network capacity is physical
- eg 100BaseTX Ethernet: 100 Mbps WiFi 802.11g: 54 Mbps
- IP-layer capacity < nominal capacity</li>
  - Coding schemes
  - Framing bits, overhead
  - Medium access control


# Link capacity & utilization

- Link capacity (C(Δt)) ≈ IP-layer capacity
  - Maximum IP-layer rate of maximum-sized packets
  - IP-layer capacity depends on size of packet relative to layer-2 overhead
- Link utilization (u(Δt))
  - $\triangleright$  u( $\triangle$ t) = Average bits transmitted on the link during  $\triangle$ t
  - Percent utilization =
  - % link capacity that is utilized



# **Available Capacity**

- Available bandwidth (A(Δt))
  - Maximum unused bandwidth
  - $\rightarrow$  A( $\Delta t$ ) = C( $\Delta t$ ) u( $\Delta t$ )



# End-to-end capacity and End-to-end effective bandwidth

Router1 ----- Router2 ----- Router

u1: 80 Mbps u2: 3 Mbps

A1: 20 Mbps A2: 27 Mbps

End-to-end capacity: min{C1, C2}=30 Mbps

End-to-end available bandwidth: min{A1, A2}=20 Mbps

## Probing method

#### **Flooding**

Issue enough probes to "fill" A number of methods in path

- Pro
  - Measure what users can get
- Con
  - Large overhead impacts network and users

#### Advanced methods

literature:

Packet pair, size-delay, selfinduced congestion

- Pro
  - Less overhead than flooding
- Con
  - Rely on assumptions that don't always hold in practice

# Effective Bandwidth Measurement

- How much capacity in my network?
  - > Is it working at spec.? Am I getting my money's worth?
  - > Systems can adapt to change of Effective Bandwidth

## Considerations

#### TCP versus UDP

- UDP not biased by congestion/flow control
- Flooding with UDP may create too much congestion and bias results
- Multiple TCP connections reduces bias

#### Multi-threaded TCP

- How many threads?
- Which size transfers?

#### UDP


How to pick sending rate?

# iperf versions and other tools for measuring available bandwidth

- iperf/iperf3
  - Control of client and server
  - Configurable tests
- iperf2 for UDP
- iperf3 is a rewrite with different/improved TCP Others: eg.
- NetPerf is yet another TCP and UDP tool
  - NetPerf implicitly codes ideas of confidence, sample size, etc.

## iperf Vantage points

Runs application at both client and server



## An Example iperf Output


```
$ iperf3 -u -t 10 -b 100Mbit --get-server-output -c 192.168.1.174
Connecting to host 192.168.1.174, port 5201
[ 4] local 192.168.1.231 port 51069 connected to 192.168.1.174 port 5201
[ ID] Interval
                 Transfer
                            Bandwidth
                                          Total Datagrams
[ 4] 0.00-1.00 sec 10.8 MBytes 90.2 Mbits/sec 1379
[ 4] 9.00-10.00 sec 12.0 MBytes 100 Mbits/sec 1532
                                          Jitter Lost/Total Datagrams
[ ID] Interval
                 Transfer Bandwidth
[ 4] 0.00-10.00 sec 118 MBytes 9 9.0 Mbits/sec 0.839 ms 2034/15114 (13%)
[ 4] Sent 15114 datagrams
Server output:
Accepted connection from 192.168.1.231, port 58542
[ 5] local 192.168.1.174 port 5201 connected to 192.168.1.231 port 51069
[ 5] 0.00-1.00 sec 7.05 MBytes 59.2 Mbits/sec 1.190 ms 226/1129 (20%)
[ 5] 9.00-10.00 sec 11.4 MBytes 95.9 Mbits/sec 2.670 ms 74/1537 (4.8%)
```

# Effective bandwidth traps or

how to do Effective effective-bandwidth measurement

- Bulk transfer capacity depends on many factors
- Transfer size
- TCP variant and configuration
- Cross traffic
- Congestion on reverse (ACK) path

## Consideration: Transfer size



## Consideration

#### TCP versus UDP

- UDP not biased by congestion/flow control
- > Flooding with UDP may create too much congestion and bias results
- ➤ Multiple TCP connections reduces bias

#### Multi-threaded TCP

- ➤ How many threads?
- Which size transfers?

#### UDP

How to pick sending rate?

Thanks to Renata Teixera for inspiring this slide

# **Conclusion and Compromise**

- Identify what you want to measure (why?)
- Consider the hidden model of measurement
  - > (independence, statistical validity, known and unknown)
- 75% functional is better than 0% perfect
  - Even better if you know/acknowledge/show the error