

Endpoint reference

Each second-level section describes one endpoint. The first table of a section is its basic information, which the overview page reads into a summary table; the tables that follow describe parameters and the response. Error responses share one shape and are listed separately under [Error codes](#).

All endpoints are served from `https://api.northlight.example` and answer `GET` only. Requests carry these headers:

Header	Required	Description
<code>Authorization</code>	yes	<code>Bearer</code> followed by a live or test key.
<code>Accept</code>	no	<code>application/json</code> , the only representation; any other value is answered with <code>406</code> .
<code>If-None-Match</code>	no	The <code>ETag</code> of an earlier response; a <code>304</code> means it is still current.
<code>X-Request-Id</code>	no	Your own correlation id, echoed back; one is generated when absent.

List endpoints paginate with a cursor: a response that has more rows carries `page.next`, and passing it as `cursor` returns the next page. Cursors are opaque and expire after ten minutes.

Current conditions

Returns the latest observation from one station.

Method	Path	Auth
GET	<code>/v1/weather/current</code>	Bearer

Parameter	Type	Required	Description
<code>station</code>	string	yes	The station code, such as <code>0SL-01</code> . One station per request.
<code>units</code>	string	no	<code>metric</code> (default) or <code>imperial</code> .

The response is one observation object. Readings older than fifteen minutes carry `stale: true`; a station that has not reported for six hours is answered with `503 upstream_delayed` instead.

Field	Type	Description
<code>station</code>	string	The station code as requested.
<code>observedAt</code>	string	The reading's instant, ISO 8601 in UTC.

Field	Type	Description
<code>temperature</code>	number	Air temperature two metres above ground.
<code>windSpeed</code>	number	Ten-minute mean wind speed.
<code>windGust</code>	number	Highest three-second gust in the same ten minutes; absent without a gust sensor.
<code>windDirection</code>	integer	Degrees clockwise from north.
<code>humidity</code>	integer	Relative humidity in percent.
<code>pressure</code>	number	Pressure reduced to sea level.
<code>precipitation</code>	number	Precipitation in the last ten minutes.
<code>conditions</code>	string	A summary word; see Read the response .
<code>stale</code>	boolean	<code>true</code> when <code>observedAt</code> is more than fifteen minutes old.
<code>units</code>	object	The unit of every numeric field.

Responses are cached at the edge for sixty seconds and carry an `ETag` .

Hourly forecast

Returns up to 48 hourly forecast points for one station.

Method	Path	Auth
GET	<code>/v1/forecast/hourly</code>	Bearer

Parameter	Type	Required	Description
<code>station</code>	string	yes	The station code.
<code>hours</code>	integer	no	1 to 48, default 24. Values above 48 are clamped, not rejected.
<code>units</code>	string	no	<code>metric</code> (default) or <code>imperial</code> .
<code>fields</code>	list	no	<code>temperature</code> <code>wind</code> <code>precipitation</code> - Probability and amount <code>cloudCover</code>

`fields` narrows the response to the named groups; without it every group is returned. The response carries the model run that produced the points and the points themselves:

```
{
  "station": "OSL-01",
  "issuedAt": "2026-09-22T05:05:00Z",
  "points": [
    {
      "validAt": "2026-09-22T07:00:00Z",
      "temperature": 12.1,
      "windSpeed": 4.0,
      "windDirection": 250,
      "precipitationProbability": 0.15,
      "precipitationAmount": 0.0,
      "cloudCover": 0.9
    }
  ],
  "units": {
    "temperature": "C",
    "windSpeed": "m/s",
    "precipitationAmount": "mm"
  }
}
```

Beyond 24 hours the Community plan receives no points; the other plans receive up to 48. See [Plans compared](#).

Daily forecast

Returns one forecast summary per calendar day, up to seven days ahead.

Method		Path		Auth
GET		/v1/forecast/daily		Bearer
Parameter	Type	Required	Description	
station	string	yes	The station code.	
days	integer	no	1 to 7, default 5. Days are calendar days in the station's time zone.	
units	string	no	metric (default) or imperial .	

Each day carries `temperatureMin`, `temperatureMax`, `precipitationTotal`, `precipitationProbability`, the dominant `conditions` word, and `sunrise` and `sunset` in UTC. The first day is today in the station's local time, which may already be partly in the past; its minimum and maximum cover the whole day.

Daily summaries are derived

A day's summary is computed from the hourly points of the same model run, so the two forecast endpoints never disagree about the same run. They can differ when a new run has landed between two requests; compare `issuedAt`.

Observation history

Returns past observations from one station in a time range, oldest first.

Method	Path	Auth
GET	<code>/v1/weather/history</code>	Bearer

Parameter	Type	Required	Description
<code>station</code>	string	yes	The station code.
<code>from</code>	string	yes	Start of the range, ISO 8601, inclusive.
<code>to</code>	string	no	End of the range, exclusive; defaults to now.
<code>step</code>	string	no	<code>10m</code> (default), <code>1h</code> or <code>1d</code> . Coarser steps return means, with min and max for temperature.
<code>limit</code>	integer	no	Rows per page, 1 to 1,000, default 500.
<code>cursor</code>	string	no	<code>page.next</code> from the previous page.

How far back `from` may reach depends on the plan's history retention; a range that starts earlier is answered with `400 range_too_wide` rather than being silently clipped. A range that spans more than 31 days at the `10m` step is rejected the same way; use `1h` or `1d` for long ranges.

```
{
  "station": "OSL-01",
  "step": "1h",
  "rows": [
    {
      "observedAt": "2026-09-21T00:00:00Z",
```

```
    "temperature": 9.8,
    "temperatureMin": 9.1,
    "temperatureMax": 10.4,
    "windSpeed": 2.1,
    "precipitation": 0.0
  }
],
"page": { "next": "eyJvIjoimjAyNi0wOS0yMVQwMTowMDowMFoifQ" },
"units": { "temperature": "C", "windSpeed": "m/s", "precipitation": "mm" }
}
```

Station directory

Lists the stations a key may read, with their location and status.

Method	Path	Auth
GET	/v1/stations	Bearer

Parameter	Type	Required	Description
region	string	no	An ISO 3166-2 code to narrow the list, such as NO-03 .
status	string	no	active , maintenance or retired .
limit	integer	no	Rows per page, 1 to 200, default 50.
cursor	string	no	page.next from the previous page.

Each row carries the code, the site name, coordinates, elevation, status and the instant of the last observation. Retired stations are included only when `status=retired` is asked for, so a client that lists stations sees them disappear rather than fail.

```
{
  "stations": [
    {
      "code": "OSL-01",
      "site": "Oslo",
      "latitude": 59.9423,
      "longitude": 10.7203,
      "elevation": 94,
      "status": "active",
      "lastObservedAt": "2026-09-22T06:00:00Z"
    }
  ]
}
```

```
    },
    {
      "code": "BG0-02",
      "site": "Bergen",
      "latitude": 60.3982,
      "longitude": 5.3241,
      "elevation": 320,
      "status": "maintenance",
      "lastObservedAt": "2026-09-19T14:10:00Z"
    }
  ],
  "page": { "next": null }
}
```

Station detail

Returns one station's metadata, including its sensors and time zone.

Method	Path	Auth
GET	/v1/stations/{code}	Bearer

Parameter	Type	Required	Description
code	string	yes	The station code, in the path.

The detail adds to the directory row the station's IANA time zone, its sensor list with the make and the installation date of each, the date it first reported and, for a retired station, the date it stopped. Metadata changes rarely; cache it for a day.

Field	Type	Description
timezone	string	IANA zone name, such as Europe/Oslo .
sensors	list	- temperature - wind - humidity - pressure - precipitation
since	string	The date the station first reported.
retiredAt	string	Present only for a retired station.

Weather alerts Beta

Lists active severe-weather alerts for a region, relayed from the national service.

Method		Path		Auth
GET		/v1/alerts		Bearer
Parameter	Type	Required	Description	
region	string	yes	An ISO 3166-2 code.	
severity	string	no	yellow , orange or red ; lower levels are excluded.	

Each alert carries event (wind , rain , snow , ice or flood), severity , onset , expires and a headline in the region's language. The endpoint is in beta: its shape may change with thirty days' notice rather than ninety, and it is available on the Business and Enterprise plans.

Not a warning service

Alerts are relayed with a delay of up to five minutes and may be withdrawn. Use them to annotate a forecast, not to trigger safety-critical actions.