

Reference Manual

GRiNS Editor for RealOne and GRiNS Pro Editor for SMIL 2.0 Windows-98/2000/XP February, 2002



© 2002 Oratrix Holding bv. All rights reserved.

 ${\sf GR}{\it i} {\sf NS} \ {\sf Editor} \ {\sf Reference} \ {\sf Manual} \ {\sf for} \ {\sf Windows-98/2000/XP}. \ {\sf February,} \ {\sf 2002}.$

The software described in this manual is furnished under license and may be used only in accordance with the terms of that license.

No part of this publication may be reproduced, stored in a retrieval system or transmitted in any form without the written permission of Oratrix Holding by or its subsidiaries.

GRINS, GRINS Editor for Real, GRINS Editor for IE, GRINS Editor for 3Gwireless, GRINS/Pro and GRINS/SMIL are trademarks of Oratrix.

RealAudio, RealVideo, RealText, RealPix, RealMedia and RealOne Player are trademarks of RealNetworks, Inc. Windows, Windows-2000, Windows-95, Windows-98 and InternetExplorer are registered trademarks of Microsoft Corporation.

Important Notices

This document is the GRiNS Editor Reference Manual. All of the information presented in this publication has been verified, but incremental product updates may impact part of this guide.

This version of the GR*i*NS Editor *Reference Manual* has been produced for use as an off-line reference. Images and page layout have been optimized for printing on a 600-dpi (or greater) laser printer. For best reproducibility, the use of a color printer is recommended, although every effort has been made to make illustrations readable on other printers as well. If you wish to use it as an on-line reference via a PDF reader, we recommend that you increase the level of display magnification when viewing images.

The images used in this publication were taken from the GRiNS Editor for RealOne build 2.0-win32-136 for Windows 2000 and/or GRiNS/Pro build 2.2-win32-135. While the look of other versions of GRiNS are slightly different because of adherence to common conventions on those other environments, the functionality described is similar for all versions of GRiNS. In order to reduce document size, only images from the Windows version have been included in this document.

We welcome your questions on GRiNS Editor for RealOne and comments on this documentation. Please submit all questions and comments to our support desk at <code>grins-support@oratrix.com</code>. We maintain a list server dedicated to sharing experiences among GRiNS Editor for RealOne users. See the on-line release notes that come with the software distribution for details of this listserver. Finally, if you wish to submit your own SMIL files as examples for other users, please send a request for submission to: <code>grins-examples@oratrix.com</code>.




Table of Contents	٧
Introduction	1
About this manual	1
Published Formats	1
PDF	1
HTML	1
Program Interface	1
Text Formats	1
Code	1
Hyperlink	1
IMPORTANT	1
General User Interface	3
Toolbars	3
Previewer Control Panel	3
File and General	3
New	3
Open	3
Save	3
Restore	3
Close	3
Close window	3
Zoom in/out	3
Help	3
Containers	4
Par	4
Seq	4
Switch	4
Excl	4
Priority Class	4
Media Item	4
Brush	4
Top Layout	4
Region	4
Timing and Linking	5
Internal Link Source	5

Table of Contents			· .
	正 采 東 東		2
Table of Contents	v	Internal Link Destination	
Introduction	1	Context Link	
About this manual	1	Browser Link	
Published Formats	í	Event source	5
PDF	1	Create begin event	5
HTML	1	Create end event	
Program Interface	1	Align / Distribute (GRiNS/Pro Only)	5
Text Formats	1	Left edges	
Code	1	V-Centers	5
Hyperlink	1	Right edges	5
IMPORTANT	1	Top edges	
		H-Centers	
General User Interface	3	Bottom edges	5
Toolbars	3	Distribute horizontal	5
Previewer Control Panel	3	Distribute vertical	5
File and General	3		
New	3	Pull-Down Menus	7
Open	3	General Information	7
Save	3	Pull-Down Menu Sets	
Restore	3	File Menu	
Close	3	New	
Close window	3	Open	
Zoom in/out	3	Open URL	
Help	3	Open recent	
Containers	4	Close	
Par	4	Save	
Seq	4	Save as	
Switch	4	Revert to saved	
Excl	4	Publish	
Priority Class	4	Document Properties	
Media Item	4	Preferences	
Brush	4	Exit	
Top Layout	4	Publish Sub-Menu	
Region	4	Publish for RealOne	
Timing and Linking	5	Publish for RealOne and upload	
Internal Link Source	5	Publish for HTML+TIME	8

Publish for RealPlayer 8	8	Create full link source and edit	11
Publish for GRiNS SMIL 2 Player	8	Use as event source	11
Publish for GRiNS /PocketPC	8	Create begin event	
Prune and Publish for 3GPP/PSS4	8	Create end event	
Prune and Publish for SMIL 2.0	8	Create simple link source	
Publish as GRiNS Template	8	Finish simple link source	12
Edit Menu	9	Tools Menu	
Undo	9	Check bandwidth usage	
Redo	9	RealPix to SMIL 2.0	
Cut	9	Enable animation	
Copy	9	Mark on Timeline	
Copy properties	9	Clear marks	
Paste	9	Align	
Paste special	9	Distribute	
Paste Properties	9	SMIL 2.0 to RealPix	
Delete	9	Select node from source	
Delete, but keep content	9	View Menu	
Properties	9	Toolbars	
Edit content	9	Expand/ Collapse	
Find	9	Expand all	
Find next	9	Collapse all	
Replace	9	Zoom	
Insert Menu	10	Show Timeline/ Bandwidth	
Media	10	Show Animation Path	
Immediate text	10	Window Menu	
Brush	10	Close	
Parallel	10	Cascade	
Sequential	10	Tile horizontally	
Switch	10	Tile vertically	
Exclusive	10	Previewer view	
Priority Class	10	Structured Timeline	
Region	10	Layout view	
Toplayout	10	Source view	
Preview Menu	11	Assets	
Preview	11	Hyperlinks	
Pause	11	CustomTests	
Stop	11	Transitions	
Preview single object	11	Error messages	
Preview from object	11	Help	
Custom tests	11	Contents	
Linking Menu	11	Context Help	
Create link to context window	11	GRiNS on the web	
Create link to browser window	11	Quick Start Guide	
			. •

Tutorial	15
Template Guide	15
GRiNS Reference manual	15
Check for GRiNS update	15
Register GR/NS	15
About GR/NS	15
About Giving	13
Structured Timeline	17
Overview of the Structured Timeline	17
Containers and Icons	17
Containers (Groups)	17
Sequential	17
Parallel	17
Switch	17
Exclusive	18
Priority	18
Brush	18
Information/Interaction Icons	18
Playstate	18
Drag handles	18
Freeze field	18
Expand/ Collapse	19
Events	19
Warnings	19
Time, Structure and Bandwidth	20
Show Time	20
Show Bandwidth	20
Green	20
Amber	20
Red	20
Layout	21
Layout Overview	21
Layout View Panes	21
Browser Pane	21
Top-layout	21
Region	21
Media	21
Visible/ Invisible key	21
Layout Pane	22
Region selection/Resizing	22
Region/media positioning	22
Property Pane	23
Cit	23

Z	23
Properties	23
x/y/w/h	23
Animation	23
Transitions View	25
Transitions Overview	25
Transitions Definition Options	25
,	
Source View	27
Source Viewing and Editing	27
Overview	27
GRiNS/RealOne	27
GRiNS/Pro	27
Editing Commands (GRiNS/Pro Only)	27
Apply	27
Revert	27
Find	27
Find next	27
Replace	27
Select node from source	27
Select node from source	27
Select node from source	27 29
Asset View	
	29
Asset View	29 29
Asset View	29 29 29
Asset View	29 29 29 29
Asset View Assets Overview Asset View Options Show template assets Show all media	29 29 29 29 29
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard	29 29 29 29 29 29
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name	29 29 29 29 29 29 29
Asset View	29 29 29 29 29 29 29
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used	29 29 29 29 29 29 29 29
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used	29 29 29 29 29 29 29 29
Asset View	29 29 29 29 29 29 29 29 29
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands	29 29 29 29 29 29 29 29 29
Asset View	29 29 29 29 29 29 29 29 29 31
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands Anchor source Links	29 29 29 29 29 29 29 29 29 31 31 31
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands Anchor source	29 29 29 29 29 29 29 29 29 31 31 31 31
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands Anchor source Links	29 29 29 29 29 29 29 29 29 31 31 31 31 31
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands Anchor source Links Anchor destination	29 29 29 29 29 29 29 29 29 31 31 31 31 31
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands Anchor source Links Anchor destination All internal	29 29 29 29 29 29 29 29 29 31 31 31 31 31 31 32
Asset View Assets Overview Asset View Options Show template assets Show all media Show clipboard Name Type Used URL Hyperlink View Linking Overview Link Management Commands Anchor source Links Anchor destination All internal Dangling	29 29 29 29 29 29 29 29 29 31 31 31 31 31 32 32


External	32	Preferences (GRiNS/Pro Only)	40
Keep list	32	GRiNS Preferences	40
Creating Anchors on Media	32	Synchronous playback	40
		Tolerance	41
Custom Tests (GRiNS/Pro only)	33	Template builder	41
Custom Test Overview	33	Save open views	
Associating a Custom Test	33	Show initial dialog	
Previewing a Custom Test	33	Previewer Switch Settings	
Manage Custom Tests		General Property Tab Controls	
New		Advanced	42
Edit		Follow selection	
Delete		OK/Cancel	42
Create/Edit Custom Tests	34	Apply	42
Custom Test Name		Builder/Advanced	
Custom Test Title		Media/Time Container Properties	
Initial State:		Info	
User Override		System Properties	42
UID	34	Begin / End	
		Active Duration	
Source File Error Messages	35	Subregion	
Message Management (GRiNS/Pro)	35	Transition	
Durante Dialone	0.7	Geometry	
Property Dialogs	37	Conversion	
Overview	37	Miscellaneous	
Document PropertiesInfo		Common Container Tabs	
		Info Tab	
Title		Name	
Author		Title	
Copyright		Abstract	
Upload Server		Alternate text	
Host		Long description (URL)	
User name	38	Author	
Directory		Copyright	
URL	38	URL	
Host		Begin/End Tabs	
User name			
Directory		New	
URL		Delete	
Template Settings (GRiNS/Pro Only)	39	Cause	
Name	39	Logical association	
Description		Event	
Snapshot	39	Offset	
HTML Template (GRiNS/Pro Only)	40	Restart node	
HTML template		Active Duration Tab	
•		Duration	44

RepeatCount	44
RepeatDur	44
Fill	44
Min	45
Max	45
EndSync	45
Erase	45
Additional Media Container Tabs	45
System Properties Tab	45
Bitrate	45
Language	45
Transition Tab	46
In-transition	46
Out-transition	46
Subregion Tab	46
Fit	46
Z-index	46
Background color	46
RegPoint	47
RegAlign	47
Region	47
Advanced Media Container Tabs	47
Geometry	47
Media Conversion	48
Convert Data	48
Target Audience	48
Video Type	48
Audio Type	48
Miscellaneous	48
Background opacity	48
Media opacity	48
Chroma key color	48
Chroma key opacity	48
Tolerance	48
Reliable transmission	48
Streaming bitrate	48
Event sensitivity	48
Transition Properties Tabs	49
Transition Type Tab	49
Name	49
Transition type	49
Subtype	49
Transition Direction Tab	49

Transition direction	49
Transition Timing Tab	49
Start value	49
End value	49
Duration	49
Repeat Tab	49
Horizontal repeat	49
Vertical repeat	49
Border Width Tab	50
Border width	50
Effect Color Tab	50
Effect color	50
Region Property Tabs	50
General	50
Layout	50
Basic Region Property Tabs	51
General Tab	51
Region ID	51
Title	51
Alternate Text	51
Long description URL	51
Region name	51
Region Layout Tab	52
Background color	52
Show background	52
Z-index	52
Sound level	52
Opacity	52
Advanced Region Property Tabs	52
Region Geometry Tab	52
Builder/Advanced Media Container Tabs (GRiNS Pro)	53
Synchronization	53
Sync master	53
Default	53
Sync tolerance	53
Default	53
MIME types	53
Read Index	53
Template Options (GRiNS/Pro Only)	54
Per-Object Template Setting	54
Thumbnail Icon	54
Scale Thumbnail	54
Drop Icon	54
Child template asset	54

Default duration	54
Allowed MIME types	54
Empty Settings	54
Icon file	54
Text	54
Color	54
Duration	54
Non-Empty Settings	55
Icon file	55
Text	55
Color	55
Anchor Property Settings	55
Info	55
System properties	55
Begin	55
Active duration	55
End	55
Anchor settings	55
More anchor settings	55
Anchor Settings Tab	56
No hyperlink	56
Internal link	56
External link	56
Show	56
Source play state	56
Destination play state	56
Access key	56
Send to	56
Actuate:	56
More Anchor Settings Tab	57
Shape	57
Coordinates	57
Source level	57
Destination level	57
	57
Fragment	57 57
Tab index	57 57
Target	31
Background Information on SMIL 2.0	59
Design Goals	59
SMIL: what it isn't (and what it is!)	60
Structure, Timelines and SMIL	61 62

SMIL 2.0 Timing and Synchronization	64
Begin, End and Dur	64
What goes around, comes around	66
Synchronization behavior	66
XML integration	66
Events and Hyperlinking	66
Content Control Elements and Attributes	67
Transitions and Animation	67
Layout	68
GRiNS Quick Reference Information	69
SMIL Compliance Information	69
Supported Media Table	69 70
RealOne Media Conversion References and Links	70
Neierences and Links	70



About this manual

This manual is a reference document that explains the functionality of the core features of GR*i*NS. It is not intended to be tutorial in nature. Readers should also consult other GR*i*NS documentation:

- the *Quick Start Guide*, which contains installation and initial use instructions;
- the *Templates Guide*, which describes the basic GRiNS template set;
- the *HowTo Guides*, which gives a step-by-step overview of how GR*i*NS can be used to solve particular design tasks

Readers should also consult relevant documentation for each of the players to be used: the RealOne IQ Guide (for the RealOne player), Microsoft's Knowledge Base (keyword: time2) (for the IE-6.0 HTML+TIME SMIL implementation), the 3GPP consortium (for 3GPP/Wireless+Mobile SMIL) and, as a final authority, the official W3C SMIL 2.0 Specification (available at: http://www.w3.org/AudioVideo/). Note that all of the SMIL 2.0 functionality provided by the GRiNS editor is also available in the GRiNS family of players.

Published Formats

GRiNS documentation is available in the following formats:

PDF The PDF version, to be used with the Adobe

Acrobat 4.0 and later viewer, is intended as an off-line reference document, suited for printing

on a 600-dpi or greater printer.

HTML An HTML version, installed in the GRiNS home

directory, suited for on-screen viewing.

Program Interface

Contents of this Reference manual will be linkable through the GRiNS help system (via the Help pull-down menu). This requires a connection to the Internet as it accesses the latest in documentation.

Note that not all versions may be available in early product releases.

Text Formats

A series of type faces are employed to distinguish information groups.

Code Text used to show SMIL coding is in a Courier

format. This is an example.


Hyperlink Hyperlinks are used to navigate to other docu-

ments. They are bold, blue and underlined. *This*

is an example.

IMPORTANT

The GRiNS editor comes in a variety of configurations. This Reference Manual describes all of the features available in all of the GRiNS implementations. Where appropriate, functions that are only available in limited configurations will be labelled. Unless otherwise stated, functionality is available in all GRiNS versions.



Toolbars

The GRiNS user interface provides a set of control panels and toolbars that contain short-cut icons for common operations. Toolbars can be anchored to the GRiNS main window or floating. Toolbar visibility is controlled through the View->toolbars pull-down menu. See also "Toolbars" on page 13.

Previewer Control Panel



The previewer control panel controls the GRiNS internal preview of a document. It always has buttons for the Play, Pause, and Stop commands. You may also select control

over synchronous playback: if selected, the value of the SMIL syncMaster attribute is used to control synchronization during playback in the Previewer.



If Bandwidth Use Monitoring has been selected from the View menu, the Previewer will evaluate all Bitrate switch settings with the displayed value.




including systemCaptions.

If one or more nodes have the System Test *Language* attribute set, the Previewer will evaluate all switch settings with the displayed value.

Note: GRiNS/RealOne allows systemLanguage and systemBitrate to be set. GRiNS/Pro allows all SMIL test attributes to be set/evaluated,

File and General

This toolbar contains single-click buttons to the File menu items:



Containers

This toolbar contains items that can be dragged to the structured timeline to create a container (group) node or media object. The same result also can be achieved through menubar commands or using the right-click contextual menus. All of the icons below are also available in the Insert pull-down menu.

The container icons are active only when in the structured timeline. For more details about the behaviors of these objects "Containers (Groups)" on page 17.



Par Create a Parallel container; all children share a common time base, starting at the beginning of the parallel.

Seq Create a Sequential container; each component is scheduled after its predecessor.

> Create a Switch container; at most one of the children will be activated, based on Language or Bitrate settings on the items.

Create an Exclusive container; at most one child will be active, based on event behavior or scheduled start times.

Priority Class Create a Priority container; define a priority grouping for contained nodes. (May be used inside an Excl only.)

Media Item Create an empty Media object; the media node's properties will determine when and how it is rendered.

Brush Create a Brush object; fills an area with the color based on the node's properties.

The following icons are only active when in the Layout view:

Top Layout Create a new Top-Layout. "Top-layout" on page 21. (*Note:* GRiNS/Pro *Only.*)

Region Create a new region that is a child of the parent region/layout. "Region" on

page 21

Switch

Timing and Linking

Context Link



This toolbar allows synchronization and timing events to be added to containers and media objects in any view where presentation objects (media, nodes) can be selected. They are single-click buttons that apply to the currently selected object. Only those icons that are relevant to the current editing context are active. For instance, a begin event or hyper link destination cannot be created unless the source has been created and selected first

una sciecte	a mot.	
Internal Link Source	Use the selection as the source of a hyperlink to an internal node. (GRiNS/Pro	<u>Q</u>
	Only; not supported by HTML+TIME.)	

Internal Link Use as the destination of a hyperlink to Destination an internal node. (GRiNS/Pro Only; not supported by HTML+TIME.)

External Link Use the selection as the source of a hyperlink to an external node. See "Create full link source and edit" on page 11.

Use the selection as the source of a trigger to place content in the RealOne Context window. "Create link to context win-

dow..." on page 11. (Only supported by RealOne player.)

Browser Link Use the selection as the source of a trigger to place content in the RealOne Browser window. "Create link to browser window..." on page 11. (Only supported by RealOne player.)


Event source Use the selection as the source of an event. "Use as event source" on page 11.

Create begin Create a begin event on the selection event using the previously selected event source. "Create begin event" on page 11.

"Create end event" on page 12. Align / Distribute (GRiNS/Pro Only)

Create end

event



Create an end event on the selection.

These single-click buttons are active when two or more objects are selected in the layout view ("Layout Overview" on page 21) for purpose of physical arrangement.

The align/distribute toolbar is active only for the Layout view and is only available in the GRiNS/Pro product.

Left edges	Align left edges of 2 or more items.	計
V-Centers	Align vertical centers of 2 or more items.	+[]+
Right edges	Align right edges of 2 or more items.	ᆀ


Top edges Align top edges of 2 or more items.

H-Centers Align horizontal centers of 2 or more items.

Bottom edges Align bottom edges of 2 or more items.

Distribute Divide available horizontal space horizontal between 3 or more items.

Distribute Divide available horizontal space vertical between 3 or more items.



General Information

All commands in the GRiNS Editors are available via the menu bar. (The only exceptions to this rule are commands that have meaning only in the context of a single dialog.)

Many common commands are also available in a contextual popup menu on the object, invoked with the right mouse button, but these contextual menus are only a subset of the full command set available in the menu bar.

Many commands also have keyboard shortcuts which can be seen in the pull-down menu, or toolbar buttons (See "Toolbars" on page 3), but again these are a subset of the complete command set.

Commands are active only if they make sense given the current selection, state of the document, etc.


Pull-Down Menu Sets

File Menu

New...

The structure for the File menu is shown at right.

Create a new document from a template. (The template selection dialog is shown as a result of this command.) A filename will be requested upon creating the new document.



Open... Open an existing presentation. The presentation can be a GRiNS project file (*.grins* or *.xgrins*) or a standard SMIL file (*.smi* or *.smil*).

standard Sivile life (.smi or .smir)

Open URL... Opens an existing presentation by giving a URL, allowing you to read in presentations from a web server. However, since you cannot save the presentation back to the web, so you will be

prompted to use Save as....

Open recent A submenu of the most recent presentations

edited, for quick access.

Closes Closes the current presentation and all its views.

Save Save the current presentation.

Save as... Save the current presentation to a new .grins file

or .xgrins binary-coded presentation file. Use

Publish to produce a .smil file.

Revert to saved Discards all the changes made to the document since the last save.

Publish

A submenu providing exports of a GRiNS presentation. (See

Document Properties This shows the document properties dialog (See "Info Tab" on page 43). Top-level document properties can be set such as Author and Copyright information, as well as FTP addresses for uploading to the server that will host the data.

Preferences...

Document specific preferences that allow the author to set options such as synchronous playback or template creation. (GRiNS/Pro Only.)

Publish for RealOne..

Publish for RealOne and upload.

Publish for GRiNS SMIL 2.0 Player...

Publish for GRiNS/PocketPC Player.

Prune and publish for generic SMIL 2.0.. Publish as GRiNS Template...

Publish for IE-6 HTML+TIME.

Exit

Exit the GRiNS Editor session.

Publish Sub-Menu

The structure of the File->Publish menu is shown at right. Note that as part of presentation publishing, media objects are copied into a single distribution directory and a file name prompt is given.

Publish for RealOne ...

Takes the current

project and creates a *.smil* file that is compatible with the RealOne player. (Media objects may be converted as part of the publish; see "Media Conversion" on page 48.)

Publish for RealOne and upload ... Same as *Publish for RealOne*, except that the resulting presentation is uploaded to a server based on the properties defined for the project. See "GRiNS Preferences" on page 40.

The following commands are active when using the GRiNS/Pro Editor only. (Note that not all commands are supported in all versions.)

Publish for HTML+TIME

Converts the syntax of the project to the XHTML+SMIL profile, as adapted by Microsoft for HTML+TIME. (Not all SMIL constructs are supported by IE-6; GRiNS/Pro Only.)

Publish for RealPlayer 8 Converts the presentation to a SMIL 1.0 format, as supported by RealPlayer 8. (Special editions of GRiNS/Pro Only.)

Publish for GRINS SMIL 2 Player ...

Creates a presentation in full SMIL 2.0 (Language Profile) compliance format. Will work with any fully compliant SMIL 2.0 player, such as the GRiNS/SMIL-2.0 Player. (GRiNS/Pro Only.)

Publish for GRiNS / PocketPC Creates a presentation that is compatible with the GRiNS scalable PocketPC Player. (GRiNS/Pro Only; special versions support device enahancements.)

Prune and Publish for 3GPP/PSS4 Creates a presentation that is compatible with the 3GPP Mobile SMIL profile (version PSS4). Will remove any options and conditional content not compatible with that profile. (GRiNS/Pro Only; special versions support device enhancements.)

Prune and Publish for SMIL 2.0 Similar to Publish for GRiNS SMIL 2.0 Player, except that it will remove any options and conditional content not compatible with that profile. (GRiNS/Pro Only.)

Publish as GRiNS Template Allows the current project to be saved in a template format, with all template settings enabled. See also "Per-Object Template Setting" on page 54. (GR*i*NS/Pro Only.)

Edit Menu

The structure of the Edit menu is shown at right:

Undo

Undo the last edit operation. Edit operations are operations that modify the presentation (or the clipboard); non-editing operations, such selecting a different node are not undoable. The undo stack is accessible until saving the document.



Redo Redo the operation most recently undone.

Cut Remove the currently selected object and place it on the clipboard. References to and from the item on the clipboard (begin events, hyperlinks, etc.)

will continue to point to that object.

Copy Create a copy of the selection and put this copy

on the clipboard.

Copy properties Shows a dialog that lists all properties on the currently selected item. Highlight the desired properties and they are copied to the clipboard. This is very useful for quickly duplicating special properties to many places (such as duration or region placement).

Paste Put the contents of the clipboard back in the doc-

ument, using paste after semantics.

Paste special Similar to paste but with an object placement

submenu that allows paste before, paste within

and/or paste after semantics.

Paste **Properties** Used to paste the Copied Properties onto the cur-

rently selected object.

Delete Remove the currently selected object from the document.

Delete, but keep content

Deletes the container currently selected, but leaves the media objects that were contained within the container in the parent container.

Properties... Show the properties dialog for the current selec-

tion. In the properties dialog you can set such things as duration (for media items) or background color (for regions). See "Property Dia-

logs" on page 37 for more information.

Edit content Open an external media editor for the media item

in the current selection. This only works if the item resides on the local disk, and if a media editor is known for the specific media type.

The following commands are active during editing in the source view. (GRiNS/Pro only.)

Find... Search for text.

Find next Find the next occurrence of the search string.

Replace... Search for text and replace it.

Insert Menu

Insert commands are used for inserting new containers and objects and regions into a presentation.

The insert media commands have three varieties that dictate where the new object will be inserted. These positions are *before*, *after* and *within*. The latter is only available if the selection is a container such as a sequential or parallel node.

The structure of the Insert menu is shown at right:

Media Insert an empty media item.

Use drag and drop or the property dialog to select the

media file.

Immediate text

A media item that will hold an amount of text. This is a convenience item for small text

items such as captions.

Brush A media item that puts a solid color in a region.

The *insert container* commands have an additional sub-command *parent* which creates the new container node as the parent of the current selection. When selected, a dialog is shown highlighting properties of the current selection that will propagate (move) to the new parent node. The remaining properties are left on the child node. This can be used to ensure that certain events and attributes continue to function as desired.

Parallel

A container item that plays all its children (the items contained within itself) relative to the same time base and (by default) finishes playing when all its children are finished.

Sequential

An item that plays its children in sequence, with each successor scheduled relative to its predecessor. The seq ends when the last child is done or when the container itself has a set duration. Switch

A group that selects one of its children, based on system test attributes such as the bitrate of the internet connection.

Exclusive

A group that plays at maximum one of its children at any given time. *Exclusives* can be used to control presentation flow by event-based user interaction.

Priority Class

Immediate Text

Parallel group

Switch group

Excl group Priority class group

Region

Sequential group

Brush

A sub-group of the *Exclusive* node. Each priority class defines a priority container with contents that can interrupt a low-priority exclusive member. The interruption can be temporary or permanent, based on priority class attributes.

Region

Insert a new region within the current selection.

Toplayout

Create a new main window in which regions can be created. (GRiNS/Pro only.)

Preview Menu

These commands pertain to the integrated GRiNS/SMIL-2 preview player. Some are also available from the right-click contextual menus and from the Preview Control Panel.

The structure of the Preview menu is shown at right:

Preview Start playing the presenta-

tion from the beginning.

Pause Pause the presentation.

Stop Stop playing the presentation.

The Preview menu also allows you to selective preview part of a document. This can be a single node, such as a media node, or a group of nodes.

Preview single object

Play the current selection only. This is only meaningful for nodes (either single media or a sub-group) that resolves to an explicit duration.

Preview

Preview single object

Preview from object

Preview from object

Play the presentation starting at the current selec-

Custom tests Select and preview the document using the cus-

tom tests that are specified in the document. (GRiNS/Pro only; only available when using the GRiNS family of players or other players with

full SMIL 2.0 Language support.)

Linking Menu

These commands are specific to the interaction of objects and timing of the document. They are available only in the structured timeline. (See the notes at the end of this section for important information on linking functionality.)

The structure of the Linking menu is shown at right:

context window...

Ctrl+P

Create link to Creates a link to an HTML page that is to be

displayed in the Real-

One context window. The content is displayed without user interaction.

Create link to context window...

Create link to browser window...

Create full link source and edit..

Use as event source

browser window...

Create link to Creates a link to an HTML page that is to be displayed in the RealOne browser window. The content is displayed without user interaction.

source and edit

Create full link Use the currently selected media item as the source of an external hyperlink.

Use as event source

Use the currently selected item as the source of a begin or end event. By default this creates an event triggered by the viewer clicking the media item. This can later be changed in the property dialog when the event is completed.

Create begin event

Create a begin event on the currently selected item. The item will only start to play when the event is triggered. This function is only active when an event source has been created previously. Details of the event, such as the activation method, such as delay can be modified through the node properties (See "Begin/End Tabs" on page 43).

Create end event

Similar to Create begin event but an end event is created on the currently selected item. The item will stop playing when the event is triggered.

The following pull-down menu entries are available on in the GRiNS/Pro Editor:

link source

Create simple Creates a the source for a hyperlink that can be used to reference an internal or external document or object.

Finish simple Creates the destination to the source of a simple link source

Important Notes:

- 1. When defining Context and Browsers links in documents that are rendered with players other than RealOne, the associated Web content is displayed in the operating system's default HTML player.
- 2. When publishing to HTML+TIME, be aware that the IE-5.5/6 implementations do not support hyperlinks to any SMIL 2.0 construct. A warning is generated on publish.

Tools Menu

The structure of the Tools menu is shown at right:

Check bandwidth usage

Checks that the bandwidth usage by the media elements in the document is consistent with the system bitrate as set in the player control panel (See "Previewer Con-



trol Panel" on page 3). A short report is shown giving presentation startup delay (preroll time) and the number of times the presentation will pause and rebuffer (stall). Individual media items will get a bandwidth icon that shows whether the item caused any bandwidth problems (See "Show Bandwidth" on page 20).

RealPix to **SMIL 2.0**

Convert a RealPix media item to the corresponding sequence of images and transitions using SMIL 2 and RealOne syntax. This command is used when converting legacy RealPlayer documents to SMIL 2. (Currently supported as Beta functionality.)

Enable animation

Active only in the Layout view if the current selection is a media item. Allows animation of the items position, size, background color, etc. See "Animation" on page 23 regarding using the animateNode facility.

line

Mark on Time- Allows a marker to be placed on the timeline during playback. A typical use-case is to place markers on the timeline during playback of an audio object; images or text captions can be synchronized to the audio by aligning them with the markers. (Note: works best when previewing a single node. May not function correctly if timeline discontinuities exist. See also: "Time, Structure and Bandwidth" on page 20. Note that Marks are temporary objects that will be reset on close and open.)

Clear marks Remove all markers from the timeline.

The following pull-down menu entries are available only in the GRiNS/Pro Editor:

Align Aligns two selected objects together according to the option selected.

Distribute Distribute two objects with equal horizontal or vertical space. The outermost two elements stay where they are, the other elements are positioned so that all elements are equally spaced. This command works best if all items are the same size

and non-overlapping.

SMIL 2.0 to The reverse of RealPix to SMIL 2.0 where a RealPix sequence of images can be converted to a single base64 encoded RealPix object. (GRiNS/Pro

only; currently supported as Beta functionality.)

Select node Active only in the source view. This focus in the from source StructuredTimeline is set to the object containing

> the text cursor in the source view. (GRiNS/Pro only.)

> > Toolbars

Expand all

Collapse all

Show Timeline/Bandwidth Usage

View Menu

The structure of the View menu

is shown at right: **Toolbars** Shows or hides the

> toolbars various and the player control panel. See "Toolbars" on page 3 for an

explanation of the individual toolbars.

Expand/ Collapse Expand or collapse a container item, showing and hiding its contents. Useful for complex presentation to un-clutter the structure view.

Expand all

Expand the selected container item and all collapsed child container items.

Collapse all

Collapse the selected container item and all container items contained within it.

Zoom

In the timeline-enabled structure view, this enlarges or diminishes the timeline. In the layout view it magnifies the preview canvas. (A rollover menu provides a zoom factor selector.)

Show Timeline/ Bandwidth Toggle the display of time in the structure view. Showing the timing of your media objects in a display that is governed by length of time rather than purely by structure. It is particularly useful for adjusting media durations and delays. Not showing time can display more items on the screen at the same time, and is the preferred mode of viewing when editing the high-level structure of a presentation. Show time also turns on the begin/duration drag handles for objects in the structure view (See "Show Time" on page 20).

Show Animation Path

Available only in the Layout view, shows a dotted line that represents the path in which a media object is animated. The path follows the top-left point of the animated media object.

Window Menu

The structure of the Window menu is shown at right:

Close Closes the topmost view or dialog window.

Cascade Place windows independently on the

screen.

Tile Stack all open views horizontally horizontally. Note that this also tiles the pre-

> window, if viewer

open.

Tile vertically Stack all windows vertically.

The use of tiled window configurations is not recommended because of its interaction with the Previewer. It is supported for legacy reasons only.

Ctrl+W

F5

F6

F7

F8

Error

Cascade

Tile Horizontally

Structured timeline

Tile Vertically

Previewer

Lavout

Source

Assets

Hyperlinks

Custom tests

Transitions

The following options select a GRiNS editing view:

Previewer Shows the previewer window. view

Shows the structured timeline, the main editing Structured **Timeline** view of GRiNS (See "Structured Timeline" on

page 17).

Layout view Show the layout view, where region layout, placement of media and animation editing occurs (See "Layout" on page 21).

Source view Show the source view, where the raw smil source is viewable in XML format (See "Source View" on page 27). Source editing is available only in the GRiNS/Pro product.

The following views are for special-purpose editing windows.

Assets Show the assets view, where an index of used/ unused media items and code snippets are kept for re-use in the document (See "Source View" on page 27).

Hyperlinks Shows the hyperlink editor, which allows navigation and creation of advanced hyperlinks (See "Hyperlink View" on page 31).

CustomTests Allows the definition and manipulation of SMIL's Custom Test Attributes. (GRiNS/Pro only; only supported by the GRiNS family of players.)

Transitions Shows the transition view, which allows creation and modification of media transitions (See "Transitions View" on page 25).

Opens a subwindow that is available only when messages the document currently opened contains errors in the SMIL code. (See "Source File Error Messages" on page 35.) (GRiNS/Pro only.)

Help

The structure of the Help menu is shown at right:

Contents

Opens a web-browser which connects to the GRiNS online documentation set. This directs to the main index for the documentation regarding the particular product in use.



Context Help

Opens a web-browser which connects to the GRiNS online documentation set. This directs to the informative help regarding the view which is currently in the foreground such as the structure view, layout view, etc. (Available in GRiNS/Pro only.)

web

GRiNS on the Opens a web-browser which connects to the homepage of the Oratrix web site.

Quick Start Guide

Accesses the Quick Start Guide that is installed to the local machine. Viewing requires Adobe Acro-

Accesses the Tutorial document that is installed to the local machine. Viewing requires Adobe Acrobat.

Template Guide

Tutorial

Accesses the Template Design Guide that is installed to the local machine. Viewing requires Adobe Acrobat.

GRiNS Reference manual

Accesses the GRiNS Reference manual that is installed to the local machine. Viewing requires Adobe Acrobat. (You are currently reading this manual!)

Check for **GRiNS** update...

Opens a web-browser which connects to the Oratrix web site to check for a newer version or upgrade to the particular product in use.

Register GRiNS...

Opens a web-browser which connects to the Oratrix web site to register the product. This is only appropriate for license-holders who have purchased their copy from an official reseller of GRiNS products, such as Real Networks. Those who have purchased from Oratrix will not need to register.

About GRiNS Displays information on the version and build of the GRiNS product

16	
10	




Overview of the Structured Timeline

The structured timeline is the main editing interface for GR*i*NS. The following text outlines the fundamentals of using this view.

Each object in the Structured Timeline is identified by a color and a type icon. The state of the object is also identified by the color of its playstate icon.

The following image identifies the main components of a node in the structure view:



In addition, media items also have special visual properties, to be described below.

Containers and Icons

Containers (Groups)

Containers are structure buckets that hold a series of objects. The type of container dictates how child objects are scheduled and activated. The structured timeline uses a variety of visual concepts to denote the playable structure of a document.

Sequential

All children of the sequential container are played one at a time in the order that they appear in the container. Scheduling within a sequential container is *relative*.



Parallel

All children of the parallel container are played according to the same time base. Scheduling within a parallel container is absolute with respect to the start of the parallel.



Switch

A switch container defines a collection of one or more children, of which at most one will be activated. (It is also possible that none of the children are activated.) Each



child of the switch must have either a system test attribute that triggers the playing of that one child. In GRiNS/RealOne, these attributes may only be a language and/or bitrate setting. In GRiNS/Pro, all possible system test and custom test attribute settings are allowed. When the switch is played, the first child that fits the profile of the setting is activated.

Exclusive

The exclusive container is used for manual interaction in a presentation. Children of the exclusive container are played only if they are referenced by a parent object of the



exclusive container. This allows user control of the presentation such as menu selected navigation. (Not recommended for use with RealOne.)

Priority

Priority containers determine the relative priority among a set of priority class containers in an exclusive. If a priority class is used by one child of an exclusive, all children of



that exclusive container must be priority containers. The priority class provides a layer of logic that deals with interrupt and pause actions among the children of the exclusive. One practical application is the use of banner ads in a presentation that should change when users are interacting with higher-level parts of the document. For the most part, priority class containers are timeline transparent. (Not recommended for use with RealOne.)

Brush

This is a pseudo media item containing a color, a layout region reference and a duration. The color of the box in the icon shows the color of the brush element.



Information/Interaction Icons

Each container is displayed with a set of icons that give feedback on activation and state information. The purpose is to visually aid content-creation rather than bog the user down with endless text strings.

Playstate

When playing a document, the playstate icons feedback the current status and position of the playing. When user interaction in a presentation occurs, certain containers are played, others are ignored. The three playstate indicators are as follows:


- Playing: When a parent container or media object is currently being played, the playstate indicator illuminates a bright green.
- **Skipped**: If a parent container or media object did not play for any reason, it turns grey to show it was skipped. This is very useful for showing errors an navigational choice in a presentation.

Drag handles

Drag handles allow the (relative) begin time and forced duration of an object to be specified graphically. The right handle governs duration and the left governs the begin offset. In *constrained mode*, you may only alter the start of an object between the predecessor's end and the successor's begin. If you depress the Ctrl key while moving the drag handle, you may push back successor objects during drag operations.


Freeze field

If a node has a fill attribute with a value of freeze, a grey/yellow background is drawn at after the end of the active duration of the object. The



yellow bar against the grey background represents the duration that the object remains on the screen after its scheduling duration has ended.


Expand/ Collapse Each type icon in the top-left corner also serves as an expand/collapse toggle. Clicking on the icon will show or hide the contents



of that container, allowing more detail, or more work space. This is useful for complex presentations that often get visually cluttered, especially when work is being done on a different part of the document. Closing containers can also improve the general performance of the Editor with manipulating large documents.

Events

Event icons serve two purposes. They denote the presence of an event, and the connection of that event. When creating an event, and finishing that connection, the two objects involved have the icons that indicate the presence of the event, and then



clicking on one of those icons will show the connection that was made and the direction.

Warnings

Warning icons notify the user that an error has occurred in the presentation. They appear when the document is played and the error has occurred. They most often denote that an object will




not be played because of attribute problems. Clicking the warning icon will show the error message.

Time, Structure and Bandwidth


Show Time

Show time enables the presentation timeline and is enabled by default. GRiNS extends the functionality commonly found in timelines by adding a self-scaling timescale and by adding features that show streaming performance on the timeline axis. In general, the non-linear timeline provided by GRiNS is intended to make editing more efficient and representative of the SMIL model.

The following image depicts a standard timeline:



When exclusive and priority class containers are used in a presentation or when the presentation contains large numbers of embedded structure containers, breaks in the timeline may occur. In this case, the timeline breaks into pieces called *timeline discontinuities* — these are intervals that take up space but do not take up any time in the presentation.



(Note: interactive event-based timing is ignored for the timeline; objects that start on events are shown as started at the time the event is evaluated.)

Show Bandwidth

Amber

Red



The bandwidth strip computes expected bandwidth usage and displays it underneath the main timeline. The computation is done based on the bitrate set in the Player control panel (see "Previewer Control Panel" on page 3). The computation is a conservative approximation of what may happen during playback: some problems shown may not occur during real playback, but if the bandwidth strip show no problems, your presentation is probably in good shape.


The following colors are used in the three representations of bandwidth:

Green No problems. The bandwidth is adequate to fit the media objects through the pipeline.

Could be a problem. Amber color in the main part of the presentation denotes a potential stall. Amber used in the very beginning (before the zero second marker of the timeline) is the preload time. This does not indicate a stall, but the amount of time required to download the initial part of the presentation. An amber color in the middle of a presentation indicates a stall which coincides with a wait for user interaction — this is typically not a performance problem.

Definitely a problem. Red indicates that in most likelihood there will be a stall. When stalls occur, the streaming player goes into a state of re-buffering which means the presentation stops and data is recollected before it continues to play.

The GRiNS Previewer software does *not* have streaming capabilities enabled. The purpose of the bandwidth indicator is specifically designed for use with RealOne and HTML+Time exports.



Layout Overview

Where the structured timeline is used to create temporal behavior in a presentation, the layout view is used to create the spatial behavior. This is done by creating *regions* which are rectangular planes to which data is rendered.

Each region is created with a series of co-ordinates, a Z-index and a fit behavior that determines how media fill the presentation canvas. The follow view illustrates a generic Layout view structure:




The Layout view is divided into three parts: the *browser*, *layout* and *property* panes.

Layout View Panes

Browser Pane

This is a hierarchical view (tree widget) containing the media objects in the presentation and their region assignment. The browser pane has full drag/drop functionality. This view is especially useful for moving media between regions. It also has a number of informative icons to help with visual arrangement:



Top-layout The outer document window. All of the regions and media assets in the presentation are nested in this layout except HTML content in the Browser and

Context windows..

Region The icon denoting a region. It will contain

the media children.

Media Icons denoting the different media items. Each have an eye icon (it

changes color when the object is selected for view) and a type icon.

The name (if any) is also shown.

Visible/ If you click on the eye icon, a lock hivisible key key appears, to indicate that the

associated item will be locked into view even if another object is

selected in the tree. Click again to unlock. (Used when aligning media in different regions.)

17

Layout Pane



The layout pane is where all regions and their content are displayed. Most often, the region/media to be displayed will be selected in the Browser pane. Selecting a region in the Layout pane has the following semantic:

- if no other object is selected, then the object with the highest z-order under the mouse will be selected;
- if another object is already selected, clicking within that object retains its selection, and click outside the object, it follows the rule above.

Using the ctl+click method will allow the selection of multiple regions, as in the browser pane.

When working with regions, you can manipulate either a region outline (resulting in changes being applied to all media objects using that region) or on a single media item selected via the browser pane (resulting in changes made only that media item).

Resizing a region will only resize the associated media items if the value of the *fit* attribute allows such resizing.

When working with regions, some functions can be achieved by using mouse clicking and dragging actions:

Region selection/ Resizing


The currently selected region will show drag handles, allowing positioning and resizing of the region. Note that when working with hierarchical regions, reposi-



tioning a parent region will also reposition its children.

positioning

Region/media Content media within regions are clipped to their parent. Positioning can occur with both regions and media. Therefore, a media or region child object can be positioned outside of its parent



region, rendering part of it invisible. This is denoted by drawing the child with a dotted line. (This is particularly useful for animations that appear to pan in from a direction.)

Property Pane



The property pane contains common properties for the currently selected region or media object. Right clicking an object in either the browser pane or layout pane will allow the complete property window to be shown. Less often used region attributes are accessible via the properties box.

Fit The fit attribute determines the scaling of the media object within its region. In the case of regions, the fit attribute will specify the default fit for all child media objects unless overridden on the object.

The z-index attribute specifies the top-to-bottom Z layering of regions and media. A higher z-index value means that the object is more to the front.

Properties Opens the main property window for the currently selected object. The property tabs and attributes are described later in this manual.

x/y/w/h Positioning coordinates that can be a pixel value. Positioning via percentages is possible via the geometry tab on the properties sheet (accessed via the property button). When using percentage-based placement, relationships among items are preserved if the containing window is resized in the RealOne player.

Animation



When a media object is selected, the animate checkbox becomes active, allowing for animations to be applied to that object's region.

The animateNode functionality allows a media node or its containing region to be moved and resized over time. When a media object has the animate checkbox enabled, multiple key frames can be defined along a motions path. To use animation effectively:

- **1.** Enable the animate check for the currently selected object.
- **2.** The red arrow indicates the currently selected keyframe.
- 3. If the media object in the layout pane is currently positioned in the desired starting position, drag the progress bar to the far right so it is positioned at 100%. This will specify that the end animation position will be recorded. Also note that the last keyframe becomes red.
- 4. When the 100% keyframe indicator is illuminated red, drag the media object to its desired destination.
- **5**. Press the play on the right of the progress meter to watch the animation in action.
- 6. Should additional key frames are to be added, stop the playback and position the progress bar to an new point somewhere between and end.
- 7. Position or size the media object in the layout pane and note that a new red keyframe appears.
- 8. Playback the animation again and note that additional movements have been added.



Transitions Overview




The *Transition view* shows the set of transitions that have been defined for the current presentation. Each of the GRiNS design templates contain a set of transition, which may be extended by a presentation author.

Each transition has a standard set of properties, such as type, sub-type, duration, and direction. The properties can be manipulated via the transition view's Edit button. Once a transition is defined, it can be applied to a media object as an *input* or *output* transition. When relevant, an object's property box will contain a tab called *Transitions* where the transition used for the begin and end of that object can be defined.


Transitions Definition Options


The set of properties associated with a transition are illustrated in the following figure:



NOTE: While the transitions architecture has been standardized in SMIL 2.0, the supported set of transition sub-types has not. All SMIL players are required to support at least one of each of the four primary SMTE transition classes, but most players do not support the hundreds of sub-types. Consult the RealOne and IE-6 documentation for the current set of supported transition classes.

See "Transition Properties Tabs" on page 49 for the description of each property tab.





Source Viewing and Editing

Overview

Since SMIL is an XML-based language, the actual creation of presentations can be done in a text editor. Of course, the power of GRiNS is that all of this work is done visually, with embedded preview and bandwidth monitoring. (This enables authors to spend a fraction of the time otherwise required with a text editor.)

While a visual interface is useful in most cases, there are times when viewing the SMIL source generated by the editor also can be useful — such as during debugging or when learning the language. Therefore GRiNS also has a source view that allows the author to view what the actual end result will be.

The functionality provided by the source view is differentiated by product.

GRiNS/ A plain source view. It has no editing capabilities and merely displays the source.

GRiNS/Pro This source view includes full source editing

capabilities as well as search and replace features.

Editing Commands (GRiNS/Pro Only)

This section denotes associated commands for the GRiNS/Pro editor product only.

Apply When doing manual edits to the source, the changes must be applied before the document is affected. The reason for this is that GRiNS' internal parser provides error checking that a normal text editor does not. Should errors occur, the

author is notified by a dialog box.

evert When editing the source, should the author want to revert back to previously before making the changes, this command-button will erase the changes. However, this does not work if the


changes were applied.


The following commands apply to source editing:

Find See "Find..." on page 9
Find next See "Find next" on page 9
Replace See "Replace..." on page 9


Select node See "Select node from source" on page 13

from source





Assets Overview



When authoring large and complex presentations, it is usually important to be able to manage the media objects that are used in that presentation. GRiNS provides an Assets view, which holds media objects and presentation sub-structures; these may be integrated into a template or a document.

In GRiNS/Pro, you may create composite asset templates containing the structure for a (potentially) complex sub-structure, such as a news story. During editing, this structure can be imported into the document and filled with media content by the document author. Several standard GRiNS templates make use of this facility.

Asset View Options

The asset view has three options for organizing various kinds of media used during a presentation and identifying where where they are kept. A radio widget is supplied at the bottom of the window to change organizational view.

Show	Show the media/structure items that are avail-
template assets	able for re-use in the presentation. These frag-
	ments are stored locally in the .grins file. You car
	add new assets via drag and drop from the struc-
	tured timeline view, or by dropping items from
	vour system directly into the asset view window

	media	A full listing of all media used in the document. This view is read-only.
ı		

Show Showing contents of the clipboard. Structure can also be kept here. This view is read-only.

Each of the organizational views has up to four columns:

Туре	The media type of the file
Used	Whether or not the media object has been used in


the presentation and how often.


The name of the object.

URL The fully qualified pathname of the object on the local filesystem. This can also be URLs to the


source objects.

Name





Linking Overview



Hyperlinks provide a facility to associate one part of a presentation with an internal or external link to another (part of) a document.

Unlike HTML links, SMIL-based links also allow the activation and termination of links to be automatic (self-firing) and to be constrained by temporal attributes. The RealOne player also provides two HTML windows (the *context* and *browser* windows), which can contain Web content synchronized to the SMIL player content.

GRiNS provides a comprehensive management interface to maintain links in the presentation.

Link Management Commands

Hyperlinks source and destination can be visually created in the structured timeline, but they cannot be edited from that view. Modification and deletion of hyperlinks can only be done in the Hyperlink view. The view is divided into three sections: source anchor, links and destination anchors.

Anchor

The left pane of the view identifies the source of the hyperlink. By default when creating a hyperlink, they are unnamed. But in this view, the anchors can be given names. Generally the anchor name should reflect the action that is desired by the hyperlink, rather than the name or the source or destination.

Links

The center section of the view that denotes a connection between source and destination. This link can be any of three directions, but that the most general usage is forward.

Anchor destination

The right pane of the view that shows the destination of the link. Both anchor panes do not actually show if a connection is present, but show a list of qualified anchors that may or not be connected.

The anchor destination pane also comes equipped with a toggle button that will filter the types of anchors by their used relation:

All internal

A full listing of all internal anchors, whether used or unused. Should a connected source and destination be selected in the appropriate panes, the Links pane will reflect that the connection

Dangling

Show anchors that have no hyperlinks attached to them yet.

focus

Follow global Show anchors on the objects currently selected in the structure view.

All related anchors

This list shows only the existing connection to the anchor that is selected in the anchor source pane. If there are no connections from the source, this pane is empty.

No anchors, links only

Keep list

Makes the right pane empty, but shows all links that originate from the anchor that is selected in the left pane.


External Similar behavior to the All related anchors option except that it relates to external links only. This is

Freezes the current contents of the pane.

used to create links to external documents such as other presentations or web-pages.

Creating Anchors on Media

Anchors on media are created in the Layout view.



Links in SMIL can be associated with whole nodes or with 'hot-spots' that cover only part of a node. To create partial node anchors, open the layout view and select an object from the browser pane's selection tree. Next, perform the following steps:

- 1. Select Linking->Create Full Link Source and Edit...
- 2. "Open" the image in the layout selector, and click on the anchor symbol.
- 3. Using the drag handles in the layout view, create an anchor shape.


(You may also set anchor coordinates by hand under the More Anchor Setting property tab. See "Anchor Property Settings" on page 55.)



Custom Test Overview


Custom tests allow users to create their own document test parameters. Unlike system test parameters in SMIL, custom tests can be designed to meet the need of the application, rather than the characteristics of the environment.

Associating a Custom Test



A defined custom test variable can be associated with an object via the Properties->System properties tab. Enter the name of the desired custom test attribute in the space provided. If the value of the custom test attribute is True when the object is (to be) activated, it will be rendered.

Previewing a Custom Test




A custom test that has been defined to be VISIBLE may have its state changed during previewing via the Preview->Custom test menu.

To set a custom test to TRUE, select the appropriate label.

Note that SMIL does not support mutually exclusive custom tests automatically.

Manage Custom Tests



The set of custom tests for a document may be managed via the Windows->CustomTest menu. The options available are:


New ... Create a new custom test variable

Edit ... Change the settings for an existing (highlighted)

custom test variable.

Delete Remove the custom test variable.

Create/Edit Custom Tests



The Edit Custom Test property box is available from the Window->CustomTest menu. It has the following properties:

Custom Test The name given to the CustomTest attribute. **Name**

Custom Test A text string used as a label in the Preview->Cus-

tomTest menu selector.

Initial State: One of the following values:

RENDERED: evaluate the test to TRUE NOT RENDERED: evaluate the test to FALSE

User Override Does the user have the ability to override the cus-

tom test at run-time (assuming the user agent can

support setting custom test values): VISIBLE: allow the user to override

HIDDEN: do not allow the user to override

UID Identifier than can be used to set the value of the

custom test.




Message Management (GRiNS/Pro)

The Error Messages view provides an interactive interface to finding and fixing errors in SMIL source files. A scan of the source file is made at parse time (when the document is loaded). If any errors are found, they are listed in an error window managed by the Error Messages view. If you select an error in this view, the source editor is activated so that you can correct the problem. (You may also select automatic correction.)



As this view is closely coupled to the GRiNS Source Editor, it is only available for the GRiNS/Pro product. Users of GRiNS/RealOne are given the option of accepting automatic error corrections for problems found during document parsing.

36	
I	



Overview

Property dialogs contain all attributes that control the behavior of an object in the presentation. Property dialogs contain a set of tabs, arranged in a series of classes.


All property dialogs are contextually sensitive to the object that is currently selected; as a result, not all property dialogs will always contain the same set of tabs. In addition, the tabs available in a property box are grouped into *Basic* and *Advanced* sets. (For common template-based editing, most users can turn off the Advanced setting.)

The general architecture of the property dialog is shown below:

A good understanding of the elements, attributes and legal attribute values in SMIL 2.0 is highly recommended in order to gain full benefit from the property dialogs in GRiNS.

In this chapter, a comprehensive list of the available tabs will be explained, although not necessarily in the order of appearance in the consecutive tabs.


In each of the sections below, the various attributes on a particular tab are illustrated and described. In some cases, the number of attributes available on a tab will depend on the setting of the Advanced toggle. In these cases, both the Basic and Advanced mode will be illustrated. (In GRiNS/Pro, the Advanced mode button is labelled *Builder/Advanced*.)



Document Properties

The Document Properties dialog provides copyright and author information, and allows the (experienced) user to set information used during presentation upload to a media server. (See "Publish for RealOne and upload ..." on page 8.) Many of the values for the properties must be obtained from the system administrator of your media server.

Info



This tab contains general information on the presentation and is placed in the published .smil document.

Title The name of the presentation. The default value


is taken from the template used.

Author The name of the author. The default value is

taken from the template used.

Copyright The copyright date.

Upload Server



This tab contains information used during a "publish with upload" request. (See: "Publish for RealOne and upload ..." on page 8.)

Media Server settings:

Host The (ftp) name of the Real server for the presen-

tation.

User name The (ftp) login name for the user. (A password

promt will be requested.)

Directory The (ftp) directory where the smil file will be

put. (A sub-directory will be created for the

data.)

URL The URL of the .smil document on the server. (Note a .smil file name is required; it is usually

the same as the name used during publishing.)

Web Server settings:

Host The (ftp) name of the Web server for the presen-

tation. (Defaults to the name of the media server.)

User name The (ftp) login name for the user. (Defaults to the

user name for the media server; a password may

be requested.)

Directory The (ftp) directory where the .ram file, the HTML

page generated, and Web pages used in the Real-One *context* or *browser* windows will be put.


URL The URL of the directory containing the Web

> pages used in the RealOne context or browser windows as seen from the .smil file. This URL will be prepended to all RealOne context or browser window page references that are defined as local

HTML pages during GRiNS editing.

Note: When a user associated content in a presentation with the RealOne context or browser windows, he may reference either a global HTML file (that is, one starting with http://...), or a local HTML file (that is, one consisting of a local name). During upload, local HTML pages are copied to the Web server, and the references in the .smil file generated by GRiNS are changed to reflect the new location.

Template Settings (GRiNS/Pro Only)



When Template Builder mode is selected (see: "Template builder" on page 41), this property box defines the basic attributes of a new template.

Name The name displayed in the template selection box

at startup.


Description The descriptive text displayed in the template

selection box at startup.

Snapshot The icon (in BMP format) displayed in the tem-

plate selection box at startup.

HTML Template (GRiNS/Pro Only)




When Template Builder mode is selected (see: "Template builder" on page 41), this property box defines the name of an HTML template for generating a Web page announcing the presentation. A sample template is included with the distribution.

HTML template The name of an HTML template that is used to generate a Web page announcing your presentation. The default HTML template is defined in the presentation template.

Preferences (GRiNS/Pro Only)

GRiNS/Pro has a number of user preferences that are saved to the document that are specific to GRiNS. These special attributes can be modified by the File-Preferences pulldown menu.

GRiNS Preferences



playback

Synchronous Because the GRiNS player does not stream media such as the RealOne player, computation of events may not be timed precisely against the playback of natural duration media such as audio and video. The result is that manually timed events that are synchronized to cues in an

audio or video media item can drift and appear to playback incorrectly. This check will cause the clock to stop the playback of media items in order to be 'frame accurate' to the events that were programmed. The side effect is that audio and video may be jerky, but it ensures that the export of the presentation to a commercial player will be accurate.

Tolerance

The value of drift in seconds allowed when the synchronous playback check is enabled.

Template builder

(GRiNS/2 Pro) This check enables many attributes to appear in the property dialog sets. They are attributes that would generally be needed by an author whose intention is to create templates for content authors.


Save open views

Records the positioning of windows in the GRiNS workspace for user convenience.

Show initial dialog

The default setting of the first pop-up dialog asking to open or create a project.

Previewer Switch Settings



This property box allows all of the system test variables to be set for the current project. Note that only objects that have test variables associated with them will be impacted by any of the settings.

These settings also determine how .smil files are generated during pruning and publishing. If Prune is selected from the Publish menu, only the items that correspond to the setting in this box will be inserted into the file.

General Property Tab Controls

Every property dialog contains a set of 2 checkboxes and a series of three command buttons.



Advanced

This checkbox provides access to advanced attributes and property tabs. For most common editing functions, this can be left unchecked (to Basic mode).

Follow selection This allows for the modal snapping of the property dialog to objects that are currently selected. The property dialog will follow focus to objects being selected in other views.

OK/Cancel

Commit/cancel changes and close the property dialog.

Apply

Commits changes leaving the property dialog open. Note: when using the follow selection option, changes should be applied before moving focus to the next object. If this is not done, the user is notified by a popup dialog if they want to commit the changes first.

In GRiNS/Pro (only), when the template option has been selected from the Preferences dialog, the bottom checkboxes are shown as follows:



Builder/ Advanced If selected, extra properties are shown. These include all properties normally under Advanced, plus extra options for creating templates.

Media/Time Container Properties

All media and time container (that is, PAR, SEQ, EXCL) share the following set of property tabs:

Info System properties | Begin | Active duration | End

Info

A tab containing general information on the node (such as name, copyright, etc.), plus (if a media node) the URL of the associated media object.

System **Properties** A tab containing the language and bitrate settings associated with the media or time con-

tainer.

Begin / End

Timing attributes that control when a node starts and ends.

Active Duration Timing attributes that control node duration, whether it repeats and where the object remains on the screen after the active duration expires.

In addition to the general properties, media containers also have the following property tabs available:

Layout Transition

Subregion

Layout properties of the media object as a child

of its parent region.

Transition

Attributes for setting input/output transitions.

In Advanced mode, media object also have the following tabs exposed:



Geometry

Advanced sub-region positioning attributes

Conversion

Attributes to control media conversion to Real-


Media formats

Miscellaneous Control over attributes speciality attributes and attributes used on export to the RealOne player.

Common Container Tabs

Info Tab

Providing values of all Info attributes is optional.



Name

The name given to the object. This is not required, but can be used for descriptive purposes. If events or links are used in a document, then names are automatically generated if not supplied by the user. If non-unique names are used (for instance, as a result of node copying and pasting), GRiNS will automatically make names unique on export.

Title Descriptive text. **Abstract** Descriptive text.

Alternate text Similar to the ALT attribute in HTML.

Long description (URL)

Pointer to extensive descriptive text.

Author Informative dialog for the author's name of the

object. (Not on all objects.)

Copyright Informative dialog for the copyright of the object.


(Not on all objects.)

URL The physical location of the media object. Can be

set to a Web URL, FTP site or a local objects. (Only local objects are copied upon publish.)

Begin/End Tabs

The begin and end attributes control the object's scheduled and event-based activation and termination. Since most of the attribute values are similar for begin and end, we describe them together in this section. Note that multiple begin events may be defined per object. The object will become active as soon as any of its begin conditions are satisfied.



New This command button creates a begin or end event. The default delay is 0s; use Offset to define

another value.

Delete This command deletes the selected begin/end

condition.

Cause The class of begin/end offset:

Delay: a time value specifying seconds

Node: an object selection box appears; the source

event type box becomes enabled.

TopLayout: An event may be associated with the opening and closing of the topLayout window(s). Indefinite: a delay of indefinite specifies that the object remains active until its parent terminates Access Key: indicate that a UI access key can be

used to generate an event. (You must specify the

Wallclock: the Entry field contains an absolute time.

The circled area is a function-sensitive box that allows information relevant to the event type to be defined.

Logical association Creates an internal X-Pointer value; if the node containing this link is copied, the link is saved as a relative value.

Event

The type of event that is the result of the Cause. This is a drop-down list of event types that can be applied to the object, such as firing when the user clicks or when the referenced node starts/ stops.

Offset

A numerical value that offsets the cause's event. Usually a time setting that is used as a delay time prior to the event firing. (Negative values result in a negative scheduling offset, but not in an earlier starting time for an object.)

Selecting the Advanced box will expose the following attributes (begin tab only):



Restart node

Determines whether a node should restart if a second begin event references it when its already playing.

Active Duration Tab

The Active Duration tab provides basic scheduling information for the node. (The values for this tab are often set by UI actions rather than direct editing.)



Duration

An explicit time-value that overrides the object's default timing. If left blank, the object will either use the intrinsic value of the media or inherit the duration of its parent.

RepeatCount

The number of times the object will repeat its duration before it is considered to have ended.

RepeatDur

The total amount of time that the object should repeat for. This overrides the time calculated by

Duration*RepeatCount.

Fill

This attribute determines of a media object is left on the rendering surface after its active duration

The following additional attributes are exposed in Advanced mode:



Min The minimum duration time of the object.

Max The maximum duration time.

EndSync For use with parallel and exclusive container. This attribute specifies if the first, last or a named

child should terminate the time container.


Erase An attribute that forces the object to be erased

after its active duration has completed.

Additional Media Container Tabs

System Properties Tab

The System Properties tab contains test attribute settings for any node. The node is only played if the current player setting match the value of the attributes.



Only the circled test attributes are available in all versions of GRiNS.

Bitrate The bitrate setting for the node and its children.

Setting this will cause the object to skipped if the client's connection is slower than the attribute

value.

Language The language setting for the node and its chil-

dren. Functions as a gate similar to bitrate.

In the GRiNS/Pro editor, all additional attributes (as defined in SMIL 2.0) may be set.

Transition Tab

The transitions tab allows an input and/or output transitions to be attached to a media object.



These attributes are selectable as per the transition definitions in the transition view:

In-transition

The transition to be used when the media object begins. The Property button to the right leads to the Transition property dialog (See "Transition Properties Tabs" on page 49).

Out-transition The transition to be used when the media object ends. The transition time is subtracted from the total duration of the object.

Subregion Tab

The Subregion tab provides access to the principal layout attributes for the object; these can be used to override the values for the associated region for rendering this object.

Most layout editing will occur via the Layout view and the associated properties. (See "Region Property Tabs" on page 50.)



Should these be left blank or default, the properties of the region will apply to the object.

Fit The visual behavior of the media object as it is rendered to the region.

Z-index The top-to-bottom layering of the media object relative to other objects in the same region.

Background A radio group that sets the color used as the color background to the media object.

Important note: these values override the global region values only for this instance of this object. The actual region values are not effected.

The following attributes are exposed in Advanced mode:



RegPoint A point on the media object that serves as the reference point for alignment.

RegAlign The place within the region at which the object's RegPoint is placed.

Region The region in which the media object is rendered. The property button to the right leads to the Region property dialog (See "Region Property Tabs" on page 50).

Advanced Media Container Tabs

Geometry

The Geometry tab specifies sub-region placement attributes. These attributes allow media to be positioned within the current region; all attribute values are relative to the containing region.



Note that values can be specified as a pixel or percentage value. By default, set to Auto; placement corresponds according to W3C CSS-2 absolute placement semantics.

Media Conversion

The conversion tab controls media conversion from native format to RealMedia. (Conversion only takes place if publishing to the RealOne player.)



Convert Data A checkbox that determines whether this media node is converted to RealMedia upon export.

Target A set of common bitrates that determine which RealProducer codecs are used to encode the media. If multiple values are selected, a RealNetworks SureStream file will be produced.

Note: SureStream technology is only recommended if a presentation is hosted on a Web site

and not on a RealServer.

Video Type For video data, the type of image material. (Used

to optimize encoding.)

Audio Type For audio data, the type of audio material. (Used

to optimize encoding.)

Miscellaneous

These attributes cover a range of RealNetworks extensions to the SMIL language plus other speciality attributes. GRiNS will include these values in the published document, but the Previewer *may not* render the associated behavior.



Background The percentage of opacity applied to a transparent background. (Valid for RealOne only.)

Media opacity The percentage of transparency applied to an opaque media object. (Valid for RealOne only.)

Chroma key The color used for chroma keying. in which a particular color of a media object is rendered as

transparent. (Valid for RealOne only.)

Chroma key The opacity percentage for the chroma keyed color. (Valid for RealOne only.)

Tolerance The tolerance color value set in Red-Green-Blue

allowing a differential to the chroma key color set to a media object. (Valid for RealOne only.)

Reliable A directive to the streaming server to force relitransmission able transmission even if this results in presenta-

tion delays. (Valid for RealOne only.)

Streaming bitrate that should be assigned to this object during streaming from a RealServer.

Event An opacity percentage that determines if events sensitivity are caught or passed to another media object.

Transition Properties Tabs

Transitions are defined in the Transitions view. These table control the various properties associated with transitions.

Note that the GRiNS preview does not support all of the transition types, but allows all types to be defined and exported to the RealOne player.

Transition Type Tab

This tab allows a name, type and sub-type to be defined for a transition:



Name The name for the transition definition. Must be unique.

Transition

type

The major transition type used. The rendering of this effect depends entirely on the implementation of the player the document is exported to. The list as shown is fully supported by the GRiNS player.

Subtype A secondary transition type, defined by SMPTE. (Not all types are previewed.)

Transition Direction Tab

A single attribute to determine the direction of the transition, if applicable:



Transition direction

The playing direction of the transition, whether it be forward or reverse. Support depends entirely on the implementation of the target player.

Transition Timing Tab

This tab allows the duration of the transition to be defined:



Start value Used to define where the transition should start

as a percentage of the transition's effect. (Default

End value Used to define where the transition should start

as a percentage of the transition's effect. (Default

is 1.)

Duration The timed duration of the transition definition.

The default value is 1 second.

Repeat Tab

Two attributes are available on this tab to control the repeat behavior of the transition:



Horizontal The number of times that the transition will be repeat repeated in its horizontal axis.

Vertical repeat The number of times that the transition will be repeated in its vertical axis.

Border Width Tab

A single attribute to set the width of a Wipe transition border:



Border width This attribute applies only to the *wipe* transition. It controls the border size in pixels.

Effect Color Tab

This single-attribute tab is used to specify the color associated with certain transitions:



Effect color

This attribute is used in conjunction with the *fade* transition and the *fadeToColor* or *fadeFromColor* subtype.

Region Property Tabs

When a region is created or edited in the layout view, the author is given access to two sets of tabs in Basic mode:



General A set of informational attributes on the region or

topLayout, some of which are only visible in

Advanced mode.


Layout Properties of the region, some of which are only

visible in Advanced mode.

Basic Region Property Tabs

General Tab

The general tab for regions is similar to the Info tab for other objects.



Region ID

The referenced name of region that media objects will be assigned to in the presentation layout. If left as a null value, GRiNS will automatically

generate a name.

Title An informative title that can be added to the

region.

Alternate Text Alternative information that can be used to

describe the region.

Long description URL

A pointer to a text string that can be used to describe the purpose of the region.


The following additional attribute is exposed in Advanced mode:



Region name A non-unique region name that is a synonym for the Region ID. Used in presentations that have multiple layouts embedded in a switch. The region is selected based on the name rather than the ID, since regions IDs must be unique.

Region Layout Tab

This tab provide basic information on the structure of the region:



Background color

The default background color assigned to the region. This behavior of this attribute depends on the value set for *Show Background*. (Only if SMIL Advanced Layout is supported.)

Show background

Determines whether the background color of a region is rendered when the contents are *not* active.

Z-index

The top-to-bottom layering of the region in relation to the master *Top-Layout* region. Higher values specify content that is more towards the front.

Sound level

(For use with regions that contain audio objects.) A percentage value that controls the level of audio playback. Default is 100%.

In Advanced mode, the following attribute is exposed:



Opacity

A percentage reduction of background color opacity. A default of 0% is equivalent to transparent.

Advanced Region Property Tabs

A single extra tab is exposed when in Advanced mode: the Geometry tab.

Region Geometry Tab

The Geometry tab allows basic region positioning to be defined.




Note that values can be specified as being pixels or percentages. If percentages are used, the relative placement of objects will be preserved in the RealOne player when the view is magnified.

By default, values have the value of Auto, and placement corresponds according to W3C CSS-2 absolute placement semantics.

Builder/Advanced Media Container Tabs (GRiNS Pro)

Synchronization

The Synchronization tab contains attributes that affect the way media objects are scheduled and synchronized with respect to their parent.



Sync master Enables the currently selected media object to

become the synchronization master for its sibling

Default The default sync master value for all children of


the currently selected object or container.

Sync The tolerance value in seconds that an object is tolerance allowed to be out of sync from its master.

Default The default sync tolerance value for all children

of the currently selected object or container.

MIME types



The MIME type of the currently selected media object can be overridden by this field.

Read Index




When a presentation is viewed using special devices for disabled viewers, this field dictates the position in the media at which the descriptive text is read.

Template Options (GRiNS/Pro Only)

Three tabs are available to define default UI behavior associated with templates.

Per-Object Template Setting



Thumbnail The icon (in .tif/.tiff format) displayed on a closed structure container.

Scale Set if the thumbnail should be scaled along with

Thumbnail the structure view.

Drop Icon The icon used to indicate when new media items

can be dropped

Child template Select an asset type for constrained content. asset (Unused.)

Default The default duration of all children of this object.


Allowed MIME types

duration



Template builders may wish to create blank media objects that allow a specific MIME type to the object placed there. This option is an override to the server response for the media object.

Empty Settings



The Empty Group setting specifies how an object can be drawn when its structure container is open, but when it is not filled with any media. The attributes are:

tify the type of the media to be placed in the con-

tainer.

Text A line of text that is displayed when the con-

tainer is open, but empty

Color The background color of the text area.

Duration The (rendered!) duration when the object is


closed. This does not impact the actual scheduled duration of the node, just the drawing space allo-

cated for the object.

An example of an empty container is shown below:



Non-Empty Settings



When a structure container in a template has content, a template author may still specify extra icons that invite users to add even more content. The attributes are:

Icon file The name of an image that can be used to iden-

tify the type of the media to be placed in the con-

tainer.

Text A line of text that is displayed when the con-

tainer is open and not empty

Color The background color of the text area.


An example of a non-empty container is shown below:



Anchor Property Settings

Whenever a Link is created, the associated anchor has properties than can be set by the editor.

In Basic mode, the set of property tabs associated with Anchors is illustrated in the following image:




In Advanced/TemplateBuilder mode, the set of property tabs associated with Anchors is illustrated in the following image:



See "More Anchor Settings Tab" on page 57. More anchor settings

Anchor Settings Tab



This tab is used to set the properties of link anchors.

Hyperlink Destination properties:

No hyperlink Set on to effectively remove link.

Internal link A link to another node in the same (SMIL) presentation. (GRiNS/Pro only; not supported on

export to HTML+TIME.)

External link The name or URL of a file. The target may be either an HTML file or a SMIL file. If a full URL is

given, this URL is preserved on 'Publish'. If a local file name is give, the file is copied during 'Publish and Upload', and prepended with the URL specified in the Upload tab, as described in

"Upload Server" on page 38.

Other properties:

Show Select the effect of following the link. Options:

New: create a new presentation, keep the old Pause: create a new presentation, pause the old

Replace: create a new presentation, end the old

Source play Determine what happens to the old presentation state (if NFW was selected for Show):

(if NEW was selected for Show): *Play*: keep the source presentation going *Pause*: pause the source presentation

Stop: end the source presentation

Destination The initial state of the destination of the link:

Play keep the source presentation going

Play: keep the source presentation going *Pause*: pause the source presentation.

Access key Defines the key used to actuate an anchor

(default is the mouse key for Activate events).

Send to The name of the window in the presentation to

receive the destination:

rpcontextwin: the context window in the RealOne

player,

rpbrowserwin: the browser window in the Real-

One player,

osdefaultbrowser: the media browser listed in the

player's OS to handle that media type,

rpengine: the media player window in the Real-


One player.

Actuate: Specifies when the link gets actuated:

onLoad: when the media object is schedule to run, onRequest: when the object is selected via the

access key or pointer device.

More Anchor Settings Tab



This tab defines additional properties of the anchor.

Shape The basic shape of the anchor. Choices:

Rect: a rectangle (specify coordinates as x,y,x,y) Circle: a circle (specify coordinates as x,y,r) Poly: a collection of points (x,y,x,y,...,x,y)

Coordinates The points defining the anchor, in the formats

above.

The audio output level of the source after follow-Source level

ing the link (defined a percentage value)

The audio output level of the destination after Destination

following the link (defined a percentage value)

Fragment The fragment ID (within the destination)

Tab index A numeric index used to tab through the select-

able objects.

Target The name of the top-level window that will

receive the destination.

58	

Background Information on SMIL 2.0

The W3C's SMIL format for encoding multimedia presentations for delivery over the Web is a little-known, but widely used standard. First released in mid-1998, SMIL has been installed on approximately 200,000,000 desktops world-wide, primarily because of its adoption in RealPlayer G2/7/8, Quicktime 4.1, and Internet Explorer 6. In August, 2001, the W3C released a significant update to SMIL: version 2.0.

Design Goals

The goals for SMIL 2.0's design can be partitioned across three broad categories:

- extend the functionality of SMIL 1.0: the designers of the first version of SMIL purposefully kept the language simple and relatively frills-free. SMIL 2.0 provides some desirable additions, including: support for increased interaction, enhanced timing semantics, extended content control and layout facilities, plus new animation and transitions primitives.
- maintain a declarative, XML format: while the integration of multimedia content is often the province of scripted or other programmed definition, SMIL 2.0 was developed to remain a fully declarative rather than a procedural format. In this way, a SMIL description doesn't define how a presentation is implemented, but rather what it is that the author wants the implementation of the

- specification left up to the SMIL player. Also, in keeping with the first version of SMIL, SMIL 2.0 is fully XML compliant.¹
- introduce a module-based structure: where SMIL 1.0 was a simple, single 29-page specification, SMIL 2.0 has been defined in terms of over 50 modules that can be partitioned into 13 functional groups, described in over 500 pages. By using a module structure, key aspects of SMIL 2.0 can be integrated into other XML-based languages without requiring support for the entire SMIL 2.0 specification. Even before the release of the SMIL 2.0 Language specification, the modularization policy bore fruit: parts of SMIL have been integrated into several other XML languages such as SVG and more examples of module reuse are expected.

As of the summer of 2001, several commercial versions of SMIL 2.0 were available (the first of which, Oratrix's GRiNS/SMIL 2.0 player, was released in September, 2000), and major mass-market media companies such as RealNetworks and Microsoft had announced support for all or some of SMIL 2.0's features. The 3GPP consortium, the standardization body coordinating the deployment for next-generation wireless devices, has

^{1.} SMIL 1.0 was not only an XML-compliant language, it was the *first* XML language released by the W3C when it was published in 1998.

also recommended that SMIL 2.0 be used as the basis for wireless multimedia devices.

SMIL: what it isn't (and what it is!)

Often, multimedia presentations are characterized by their content, rather than their composition. In this sense, there has been some confusion as to what a SMIL presentation is, and what it isn't.

To begin with the latter, it is fairly easy to summarize what SMIL 2.0 is *not*:

- SMIL 2.0 is not a Flash substitute: Flash is a proprietary content media type that is primarily used for small animations. SMIL 2.0 is not a content media type, in the sense that it does not define any particular type of media (such as vector or raster images, videos, text or audio data). Instead of media content, SMIL defines XML-based media composition. A SMIL presentation can include Flash objects.
- SMIL 2.0 is not an MPEG-4 substitute: MPEG-4 is a highly touted (but lightly implemented and deployed) format for describing the contents and interactions of media objects. More precisely, MPEG-4 is a family of protocols that covers a wide range of media-related concerns, but not a specific solution to any one class of media presentation. As we will see, there has been considerable work done to coordinate the development of SMIL 2.0 and MPEG-4 through the XMT specification.
- SMIL 2.0 is not a D-HTML substitute: Dynamic HTML (D-HTML) was introduced as a way of introducing local time- and animation effects into a

static HTML web page. While some of the animation primitives in SMIL 2.0 resemble the functionality of some uses of D-HTML, SMIL's scope is much broader than the local nature of D-HTML.

What, then, is SMIL 2.0? It is a collection of XML elements and attributes that can be used to describe the temporal and spatial coordination of one or more media objects. SMIL 2.0 allows a user to define how independent media objects are to be integrated during the lifetime of a presentation. That presentation may be delivered via a streaming server, or it may be played locally.

SMIL 2.0 defines 10 major functional groupings of elements and attributes. (See Figure 1.) Of these, *Timing and Synchronization* is the core of the SMIL specification. The functional groupings represent collections of individual SMIL 2.0 modules, each of which defines elements and attributes intended to address specific multimedia issues in a reusable manner. The number of modules per functional grouping varies from 2 to about 20. In general, the more modules per grouping, the finer the granularity of each module.

The modularization of SMIL 2.0 was intended to not only facilitate the reuse of SMIL functionality in other XML languages, but to also help define a number of SMIL *profiles*, each of which would provide a collection of modules that could be customized to the primary goal of the profile.

Figure 2 shows the initial partitioning of SMIL 2.0 profiles. Of these, the SMIL 2.0 Language and Basic




Figure 1: SMIL 2.0 Functional grouping of module sets.

profiles completed the required review and implementation requirements of the W3C for the summer 2001 release of SMIL 2.0. The XHTML+SMIL profile, which seeks to integrate SMIL timing, animation and transitions modules (among others) into XHTML, was not completed and remains under development by the W3C. In addition to the three SMIL profiles, a version of SMIL Animation was also released by W3C in July 2001 for final review by W3C members.




Figure 2: SMIL 2.0 Profiles.

Structure, Timelines and SMIL

A SMIL presentation is a structured composition of autonomous media objects. As illustrated in Figure 3,

there are three basic timing containers that can be used in a SMIL presentation:

- *seq sequential time container*: the children of a *seq* container are rendered in such a way, that a successor child never can begin before its predecessor child completes. A successor child may have an additional start delay, but this delay cannot resolve to be negative in relation to the end time of its predecessor.
- par parallel time container: the children of a par container are all rendered in "parallel". In terms of SMIL's timing model, this does not mean that they get rendered at the same time, but rather that they share a common timebase defined by the par container. It also means that any or all of the children can be active at any time that the parent par is active. The *par* is the most general SMIL time container.
- *excl exclusive time container*: only one of the children of an excl can be active at a time. The order of activation of the children depends on the begin

attribute of the *excl*'s children. Typically, each will have an event-based start condition such as:

begin="button1.activateEvent"

that allows one of the children to start on demand. The *excl* container is new in SMIL 2.0.

The three basic time container types can be nested in a presentation hierarchy. That is, any child of either a *par*, *seq* or *excl* can be a simple media object or an embedded *par*, *seq* or *excl* container. As in SMIL 1.0, the hierarchy can represent relatively static presentation timing. The introduction of event-based activation/termination in SMIL 2.0 also allows a dynamic activation path to be defined. Note that most other multimedia formats only

support a *par*-like semantic, not the *seq* or *excl* semantics.

Timeline Definition

A fundamental property of multimedia presentations is that they contain media objects requiring some notion of *time* for correct presentation. In order to model presentations, a timeline metaphor is often used. To understand SMIL 2.0, the *timeline* metaphor can be applied to containers that hold only static objects for which all timing (including activation time, termination time and object duration) are known at the time of authoring. For containers like the *excl*, where the




Figure 3: SMIL 2.0 Temporal Groups.

- (a) shows a SMIL seq container, plus a SMIL 2 code fragment. Note that begin times are relative to the predecessor end.
- (b) shows a par container, with the same timing offsets. Note that begin times are relative to the containing par.
- (c) shows an excl container. Object a starts at time 0 of the excl and whenever object x (not shown) is activated.
- Objects b and c are started only when objects y and z (not shown) are activated.

Since the actual activation times depend on event activity, a common timeline cannot be used to model the relationships among a, b and c.

activation or termination time is unknown until the object actually starts, or for par's containing objects with unresolved begin or end times, the timeline metaphor is essentially useless. While this presents a challenge to authoring software designers, it provides a SMIL 2.0 document with unprecedented temporal flexibility and adaptability because the effective presentation timeline is determined at runtime, based on the individual media objects activated and their activation order.

Unlike media formats which force the user to explicitly define when each object begins and ends relative to a single timeline, SMIL provides a logical timing framework in which the structured relationship of objects can be used to define most timing relationships among objects. When writing a SMIL file, the author does not have to worry about the exact starting or ending times, since these can be gleaned from the presentation's par/seq/excl structure. In a SMIL specification, the timeline is determined by the structured composition of objects, rather than the timeline being the basic compositional unit.

The decoupling of timing resolution from presentation specification allows, for example, the entire timing of a presentation to be changed based on the dynamic associations of content. Consider the following SMIL 2.0 code fragment:

```
<par endsync="select">
  <img id="btn_a" src="..." dur="10s" /
<img id="btn_b" src="..." dur="5s" />
  <excl id="select">
    <text src=".../todays_txt.html" be-</pre>
gin="btn_a.activeEvent" dur="25s"/>
    <video src=".../todays_video.mpg" be-</pre>
gin="btn_b.activeEvent" />
  </excl>
  <audio src=".../todays_tune.mp3" repeat="indefi-
nite"/>
</par>
```

The outer *par* contains two button images (*btn_a* and *btn_b*), an audio object reference, and an *excl* container (named select). The excl contains a text object reference and a video object reference. Note that each of the media object references is indirect: they point to external data that can change on a hourly, daily or weekly basis.

The button images are displayed for 10 and 5 seconds, respectively, when the par starts. The background music also begins, and repeats indefinitely — that is, it repeats until the containing par ends. Since the par contains the directive:

```
endsync="select"
```

it will end when the *select* object ends. The *select* object ends when either the text or the video object ends, depending on which one is activated by the presentation viewer. (If the viewer selects btn_a, the text object will be shown for 25 seconds; if the viewer selects btn_b, the video object will play for the intrinsic duration that object, whatever that is.) All the while, the background music keeps repeating.

Drawing the presentation timeline is left as an exercise to the reader.

Timing Control - begin

- end
- dur

Extended Activation

- endsync
- min
- max

Object Persistence

- fill

Repeating Control

- repeatCount
- repeatDur

Synchronization

- syncBehavior
- syncTolerance
- syncMaster

XML Timing Integration

- timeContainer
- timeAction

Figure 4: Primary SMIL 2.0 timing and synchronization attributes.

SMIL 2.0 Timing and Synchronization

The timing and synchronization functional group represents the core of SMIL 2.0 functionality. The group is divided into 19 modules, each of which defines a collection of XML elements and attributes that control some aspects of timing.

The three basic SMIL 2.0 timing elements seq, par and excl were introduced above. Each of these elements form parent timing containers in which media objects or other timing containers can be placed. For any content within a container (whether a media object or structure container), the primary issues to be addressed are:

- when does the element begin?
- how long is it active?
- what happens to it when it is no longer active?
- other than strict temporal, are there other conditions that cause an element to end?

These questions are 'answered' by specifying a set of attribute values on either the parent time container or any of its children. SMIL 2.0 has an extensive set of attributes to control timing, most of which carry sane defaults so that basic timing and synchronization operations can be accomplished easily.

The basic collection of timing and synchronization attributes are shown in Figure 4. Note that not all of the SMIL 2.0 profiles support all of the attributes, and the syntax of defining and setting the attribute values may vary, but the core functionality of timing, extended activation control, object persistence and repeating element control are reasonably universal. A design objective of SMIL 2.0 was that each attribute should have a well-defined semantic that remains constant across profiles.

Begin, End and Dur

The begin and end attributes are very similar in terms of syntax and semantics. The primary differences between these attributes in SMIL 1 and SMIL 2.0 is that SMIL 2.0

allows multiple values to be specified for begin and end. (An example of this was shown in Fig. 3.) The first begin/end value that is satisfied will cause a corresponding element to start or end. It is possible to mix both scheduled and event-based activation/ termination in one attribute. For example:

begin="3s; button.activateEvent" will cause the associated element to start either at 3 seconds after the default time at which the element would otherwise be able to start, or when the activateEvent event associated with another element with an ID of button occurs (typically via a mouse click). The 'default' begin time varies with the parent time container: for a par and excl, it is when the container starts; for a seq, it is when the previous element in the seq ends (or at the start of the *seq* for the first child element).

Once started, an element will have a certain duration, which may be determined in several ways (see Figure

5). In general, so-called discrete media — media without an inherent notion of time, such as images or a page of text—have a default duration of 0 seconds, while continuous media—media with an inherent notion of duration, such as an audio or video object use that inherent duration as default. (Some implementations of SMIL 1.0 used 5 seconds for the default duration of a discrete media item. All SMIL 2.0 implementations should use the "real" default value of 0.)

An object with a duration of 0 seconds would ordinarily not be visible during a presentation. Such objects can be displayed if the *fill* attribute is set to a value of *freeze*. A frozen object is displayed after the end of its active duration until its parent time container ends — for discrete media, this will be the image or text, for continuous media, it will be the last frame/sample. The following:




Figure 1: Various SMIL 2.0 duration concepts

The inherent duration is the duration of the media object, if any. The simple duration is the inherent duration modified by the dur attribute. The active duration is the simple duration modified by the repeatCount (and repeatDur) attributes. The perceived duration is the visual behavior of an element after its active duration, before its parent time container ends.

will display an image 3.5 seconds after the parent par begins. The active duration of the object will be 0 seconds, but the object will remain visible for 6.5 seconds (until the parent par ends). Two values of fill define a rendering duration that extends beyond the parent: transition and hold.

As in SMIL 1.0, if a *par* has multiple children active, it can specify that the entire *par* ends when the first child ends, when the last child ends or when a named child ends. This is done via the *endsync* attribute. (The default is: endsync="last".)

SMIL 2.0 has two new attributes that provide extra duration control: *min* and *max*. These attributes, which developed out of the SMIL 2.0/MPEG-4 integration work, can be used to define a lower or upper bound on the active duration, regardless of that element's timing characteristics.

What goes around, comes around...

The default behavior of all elements is that they play once, for either an implicit or explicit duration. The SMIL 2.0 *repeatCount* attribute allows an iteration factor to be defined that acts as a multiplier of the object's simple duration. A special value *indefinite* is used to specify that an element is to be repeated continually until the parent time container ends. Although it is tempting to define this as "forever," this is not correct: the parent time container defines the context of *indefinite*. The *repeatDur* attribute defines a duration for all of the repeated iterations.

Synchronization behavior

In a perfect world, all of the defined timing in a specification would be implemented perfectly by a SMIL 2.0 player. Unfortunately, the world is not only imperfect — it is also unpredictable. In order to provide some measure of control in the face of unpredictably, SMIL 2.0 provides three high-level synchronization

control attributes: *syncBehavior* allows a presentation to define whether there can be slippage in implementing the composite timeline of the presentation; *syncTolerance* defines how much slip is allowed; *syncMaster* allows a particular element to become the "master" timebase against which all others are measured.

XML integration

When used in a native SMIL 2.0 document (one in which the outer XML tag is <smil>), the nature and meaning of various timing elements is clear. When integrating SMIL timing into other XML languages, a mechanism is required to identify timing containers. The SMIL 2.0 specification does this using the *timeContainer* and *timeAction* attributes.

Events and Hyperlinking

In the normal course of processing, the activation hierarchy of a SMIL 2.0 document determines the rendering of document elements. The user can influence the elements selected by using SMIL 2.0 *events*. The event architecture allows document components that are waiting to be activated or terminated to actually start or stop. There are several uses of events allowed in SMIL 2.0, but perhaps the most important new semantic in the language is the combination of events and the *begin/end* attributes. In further combination with the *excl* element, events provide a very powerful mechanism for conditional content activation.

SMIL 2.0 also supports a rich hyperlinking architecture. Unlike links in (X)HTML, the fundamental concept of

the SMIL link is that it models a temporal seek in a presentation. Rather than simply activating a target element, the target play state that is activated is identical to the state that the presentation would have been in if the target point had been arrived at 'naturally'. (One exception is that all event-based activation is ignored.) This means that all nodes temporally between the source and destination of the link need to be evaluated to see if they would have contributed to the final target play state. The temporal seeking and activation facility allows very polished presentation construction — but its implementation in the player is not for the faint-hearted!

Content Control Elements and Attributes

One of the major innovations of SMIL was support for conditional content via the switch element.

```
<switch>
 <video src="..." systemBitrate="115200" />
 <seq systemBitrate="57344">
    <img src="img12.png" dur="9s" />
 </seq>
<text src="desc.html" dur="30s"/>
</switch>
```

In this fragment, a video object is rendered if the system bitrate (actual or configured) is set to 112K or above. If the bitrate is 56K or above — but below 112K — a sequence of images is shown instead. If no other element had been selected in the switch, the text object is shown.

One of the limitations of the SMIL 1.0 switch element was that it only allowed selection based on pre-defined list of "system" attributes. SMIL 2.0 extends this notion with a user-defined set of test attributes: custom test

attributes. The custom test attributes can be defined by the author and selected by the user directly or indirectly via the player. SMIL 2.0 also allows test attributes to be used "in line": that is, outside the switch element. Any media object reference containing a system or custom test attribute will be evaluated as if it were wrapped into a single-element switch.

To a first approximation, both the event mechanism and the content control facilities provide a means for dynamic selection of objects in a presentation. The basic difference between these facilities is that the event mechanism works on objects that have been recognized by the SMIL 2.0 scheduler, while the content control facility determines which object the scheduler gets to evaluate. The actual selection process associated with the conditional control primitives may be static or dynamic. That is, the selection may be done at parse time (when the document is loaded) or at each iteration through the document. The specific selection policy is a property of the SMIL player.

Transitions and Animation

SMIL 2.0 significantly extends the facilities available for performing local operations on media objects in a document. Two of the most visible of these facilities are support for transitions and animation.

SMIL's transition support allows a set of basic transitions to be defined as part of the SMIL head element, and then to instance one of the available transition types as an input or output transition on a media object. For example, consider the SMIL 2.0 fragment in Figure 6. Transitions can be applied to all visual media, or collections of media. Each transition can have certain timing properties (duration) and other transition-specific properties (direction).

Animation in SMIL 2.0 comes in two flavors. First, there are animations that apply to attributes and elements in the SMIL presentation. This includes animating the position of a rendering region or a background color. A second type of animation support is the SMIL 2.0 Animation Specification, which gives generalized temporal animation support for integration into XML .

Layout

Unlike HTML, which uses an indirect layout model via CSS, SMIL also supports a direct layout model for managing the visual and audio rendering space

Figure 6: Transitions architecture in SMIL 2.0.

The transitions are defined in the head section and referenced in the body section as either input or output transitions.

associated with a presentation. In SMIL 2.0, the SMIL basic layout mechanism is supported with elements and attributes that allow layout to be specified as a hierarchy of rendering regions, and to be able to support multiple top-level presentation windows. The support for hierarchical layout is especially important when integrating animation into a presentation: content that is logically grouped together can be moved in concert by animating the position of the common parent region. Multiple top-level windows allow a single presentation to segment control and rendering operations in different parts of the screen in a coordinated manner.

Another enhancement to SMIL 2.0 layout is the support for sub-region positioning. This facility allows an object

to be placed at a particular X,Y offset within a region or aligned to a *registration point*. (In SMIL 1.0, all objects were placed at the top left corner of a region.) The placement occurs in-line, as part of the media object reference. SMIL 2.0 also supports an alignment mechanism for content in regions; this allows a set of images of varying size to be centered at a specific point in a region. SMIL 2.0 also allows multiple objects to be active in a region simultaneously, relaxing a restriction from SMIL 1.0.

(This chapter was adapted from the book SMIL: Interactive Multimedia on the Web, by Lloyd Rutledge and Dick Bulterman. A version of this chapter also appeared in an article in IEEE Multimedia Magazine, by Dick Bulterman, founder of Oratrix.)

GRiNS Quick Reference Information

SMIL Compliance Information

The GRiNS supports the entire SMIL 2.0 specification, although not all features are previewed during editing. Documents that make use of these constructs are parsed correctly, but the features are ignored during rendering.

Supported Media Table

The following chart gives a listing of the media types supported by various versions of GRiNS Editor for RealOne:

MIME type	Extensions	Windows 98/2K/XP
audio/basic	au	yes
audio/x-aiff	aiff, aifc, aif	yes
audio/x-wav	wav	yes
image/jpeg	jpeg, jpg	yes (2)
image/png	png	yes (1)
image/tiff	tiff, tif	yes
image/x-portable-anymap	pnm	no
image/x-portable-bitmap	pbm	no
image/x-portable-graymap	pgm	no
image/x-portable-pixmap	ppm	no
image/x-rgb	rgb	yes
image/x-xbitmap	xbm	no
	bmp	yes

MIME type	Extensions	Windows 98/2K/XP
	ras	yes
	tga	yes
video/mpeg	mpeg, mpg	yes
video/quicktime	qt	yes
video/x-msvideo	avi	yes
video/x-sgi-movie	mov	no
text/html (5)	html, htm	no
text/plain	txt	yes

Notes

- 1. Preview support seems to be somewhat buggy.
- 2. Not all encodings supported.
- 3. HTML data is rendered by the GRiNS Preview Player, but not converted to RealText.

Each of these formats is converted to the appropriate RealSystem datatype. For highest quality rending of a final presentation, we recommend converting some datatypes to RealMedia before inserting them in a presentation, if possible.

RealOne Media Conversion

The following chart describes the levels of support provided in the GR*i*NS/RealOne version for the listed RealMedia data types used in the RealNetworks RealOne Player:

RealMedia	Extension	Importable	Generated
RealAudio	ra, rm	yes	yes
RealVideo	rm	yes	yes
RealText	rt	yes	no(1)
RealPix	rp	yes	no

Notes

- 1. GR*i*NS/RealOne provides support for the automatic generation of simple RealText documents from immediate strings in the Editor, but it does not at present provide full RealText editing facilities. This is expected in a future release.
- 2. GR*i*NS/RealOne can import and convert most existing RealPix files.

References and Links

Please see the Links section of the GRiNS/RealOne Web site (<u>www.oratrix.com/</u>GRiNS).