SWG God Client — User Guide

2026-11-05

The God Client is the developer build of the Star Wars Galaxies client. It lets you fly a free camera through a live world and select, move, rotate and create objects on the server. It also lets you edit object scripts and variables, browse templates, and send system messages. The rebuilt client adds an in-game Terrain Editor.

This guide covers the rebuilt client in `E:\SWG_GodClient\swg\exe\win32_new`. Everything here comes from that client's source code and its configuration.

1. Starting up

Which client to run

What	Path
Rebuilt God Client (with Terrain Editor)	`E:\SWG_GodClient\swg\exe\win32_new\SwgGodClient_r.exe`
Launcher for it	`J:\SWG_Claude\God Client Terrain Editor (E).cmd`
Original 2016 client (no Terrain Editor)	`J:\SWG_Claude\God Client (E).cmd`
Source code	`E:\client-tools\src\game\client\application\SwgGodClient` (branch `godclient-terrain-tool`)

Start the client from its own folder, as the launcher does, so it finds its `.cfg` files and data.

Logging in

1. The client skips the intro (`skipIntro=true`) and shows the login screen.
2. It connects to the login server set in its config: `loginServerAddress0=192.168.1.200`, port `44453`.
3. Log in with an account that has god (admin) rights on your server. Without them, the server ignores move, create and edit requests.
4. Pick a character. The main window opens with the game view and the dockable tool windows.

Configuration files

The client reads `client.cfg`, which includes `common.cfg`, `SwgGodClient.cfg` and `user.cfg`. All four are in the `win32_new` folder.

Section and key	Meaning
`[ClientGame] loginServerAddress0`, `loginServerPort0`	Login server to connect to
`[ClientGame] skipIntro`	Skip the intro movies
`[GodClient] connectToPerforce`	Use Perforce for scripts and templates (SOE's original setup)
`[GodClient] loadServerObjects`	Show server-side objects in the Tree Browser

Section and key	Meaning
`[GodClient] scriptEditor`, `templateEditor`	Program used to view and edit scripts and templates (default `Textpad.exe`)
`[GodClient] local…Path`, `script…Path`, `template…Path`	Where source and compiled data live
`[GodClient] frameRateLimit`	Frame rate cap (0 = none)
`[ClientTerrain] terrainMultiThreaded`	Must be `true` for the Terrain Editor
`[SharedFoundation] demoMode=true` (in `user.cfg`)	Hides the "warnings logged" box at exit

2. The main window

The main window has a menu bar, toolbars, a game window and dockable tool windows. Toolbars: **File**, **Edit**, **Game**, **View**, **Script**, **ServerObjectTemplate** and **ClientObjectTemplate**. Each button matches a menu item below.

The **Game Window** shows the 3D view. Its status bar shows the camera pivot position, the pivot distance and the buildout region under the camera. Its **Game Focus** button hands the keyboard and mouse to the game, as in the normal client.

Two ideas run through all the editing:

- **Selection:** the objects you have picked, shown highlighted.
- **Ghosts:** see-through copies of the selection that you move, rotate and scale freely. **Apply Transform** (Ctrl+T) sends the ghosts' positions to the server, which moves the real objects. Until then the server copies don't change.

3. Camera controls

The camera uses Maya-style controls: hold **Alt** and drag. The camera turns around a pivot point in front of it.

Input	Action
Alt + left drag	Tumble: orbit around the pivot
Alt + right drag	Dolly: slide the camera parallel to the view
Alt + Ctrl + right drag	Slide the pivot along the ground, keeping the camera's height above it
Alt + middle drag (or left + right)	Zoom: move the pivot nearer or further
Alt + Ctrl + left or middle drag	Fly: free-look turning in place
Mouse wheel	Zoom in and out
C	Move the camera to the point under the cursor
=	Go to: type an exact pivot position (x, y, z) and distance
Ctrl+E / Ctrl+Alt+E	Center the camera on the selection / on the ghosts

Input	Action
Ctrl+F / Ctrl+Alt+F	Fit the selection / the ghosts to the screen
View → Reset Camera	Back to the default camera
Ctrl+F11	Interior camera (for inside buildings)
Enter (or Ctrl+F8)	Toggle game focus: play as the avatar instead of the free camera
A (single-player only)	Move the avatar to the camera

4. Selecting objects

Input	Action
Left click an object	Select only that object
Shift + left click	Add to the selection
Ctrl + left click	Toggle the object in or out of the selection
Left drag on empty ground	Rubber-band select everything in the box
Shift / Ctrl + rubber band	Add / toggle everything in the box
Left drag a selected object	Drag it over the ground and other objects
Tree Browser (Objects tab)	Pick objects from a list; double-click to jump to one
Window → Filters	Limit what the lists show: by distance from the avatar, network id range, or template

Locked objects: structures and other important objects start locked so they aren't moved by accident. Use **Edit → Unlock Selected** (Ctrl+U), **Unlock All**, **Unlock Non-Structures** or **Unlock Server Only Objects** to unlock them.

Selection groups: Ctrl+F1 … Ctrl+F4 stores the current selection as group 1–4. **F1 … F4** restores that group.

5. Moving, rotating and scaling

Hold a key and drag with the mouse. You are moving the ghosts; press **Ctrl+T** (Apply Transform) to send the result to the server.

Hold	Left drag	Right drag	Middle drag
T (translate)	Move in the view plane	Move up and down	Pull toward or push away from the camera
G (ground translate)	Move along the ground	Move up and down	Pull or push along the ground
R (rotate)	Yaw	Roll	Pitch
S (scale)	Scale height	Scale width and depth	—

Hold **Ctrl** while dragging with **G** to align the ghosts to the terrain as they move.

Keyboard nudges (selection, one step each):

Key	Action
Arrow keys	Nudge north, south, west, east
; and '	Up and down
> and <	Yaw +45° and −45°

Edit menu transform commands

Command	Shortcut	What it does
Apply Transform	Ctrl+T	Send the ghosts' positions and rotations to the server
Drop to Terrain	Ctrl+D	Put the selection on the ground
Align to Terrain	Ctrl+Alt+D	Tilt the selection to match the slope
Toggle Drop to Terrain / Toggle Align to Terrain	—	Do this automatically while moving
Reset Rotation	—	Back to upright, facing north
Rotate +45 / Rotate −45	—	Yaw by 45°
Random Rotate	—	A random yaw for each selected object (good for scattered props)
Set Transform	—	Type exact position (metres) and yaw, pitch and roll
Rotation mode (Yaw, Pitch, Roll)	—	Which axis the rotate buttons turn
Pivot mode (Self, Selection Center, Last Selection)	—	What the selection turns around
Tools → Snap To Grid…	—	Snap moves to a grid: block size, horizontal and vertical segments, sensitivity

6. Creating, copying and deleting

Command	Shortcut	What it does
Create New Object [template]	Ctrl+N	Create an object from the template selected in the Tree Browser (its name shows in the brackets)
Copy / Cut / Paste	Ctrl+C / Ctrl+X / Ctrl+V	Copy, cut and paste selected objects (paste creates new server objects)
Delete	Delete	Destroy the selected objects on the server
Undo / Redo	Ctrl+Z / Ctrl+Y	Undo or redo object edits (moves, creates, deletes)
Replace selection with Server/Client template	—	Swap the selected objects for another template (ObjectTemplate menu)
Copy For POI	—	Copy the selection's layout for use in a point of interest (POI)

Command	Shortcut	What it does
Create Theater	—	Write the selection as a theater: server and shared templates plus a data table, in the POI folders set in the config
Create ClientDataFile	—	Write the selection as a client data file
Edit Triggers...	—	Set a trigger volume's name and radius
Edit Form Data...	—	Edit the form fields of the selected object
Show Object Axes / Toggle Particle Systems Pause	—	Display aids

7. Brushes and palettes

A **brush** is a saved group of objects with their relative positions, so you can stamp the same arrangement again and again. A **palette** is a named collection of templates and brushes.

1. Select the objects and choose **Tools** → **Save As Brush**.
2. Open **Window** → **Group Object Editor**. It has **Brushes** and **Palettes** tabs.
3. Pick a brush and use **Paste Brush Here**, or **Edit** → **Paste Brush**, to create it at the cursor.
4. **Create Brush**, **Delete Brush**, **Create Palette** and **Delete Palette** manage the lists.

Brushes are saved on your PC and loaded when the client starts.

8. Tool windows

All of these are under the **Window** menu and can be docked or floated.

Window	What it's for
Tree Browser	Tabs: **Objects** (objects near you, filtered), **ServerTemplates**, **ClientTemplates**, **Scripts**, **Buildout Areas**. Each has a Refresh button
Object Editor	The selected object's **Attributes**, **ObjVars** (object variables), **Scripts** and **Skills**. Right-click a script or objvar to **Detach**, **Remove Objvar** or **Set Objvar**
Bookmarks	Camera and object bookmarks; jump to one, or delete it
Favorites	Templates you starred with **Add to favorites** in the template lists
Group Object Editor	Brushes and palettes (section 7)
Filters	What the object lists show: distance from the avatar, network id range, client or server template
Console	The God Client's message and command console (the game's own console is **~**, Game → Toggle Console)
Game Window	The 3D view
Region Viewer	Draws server regions on the map. Filter by type (Geographical, Mission, Municipal, PvP, Buildable, Spawnable, Difficulty), or show only regions whose value isn't 0
Terrain Editor	Sculpt, paint and plant the terrain (section 11)

9. Game and View menus

Game menu

Item	Shortcut	What it does
Game Focus	Enter	Play as the avatar instead of the free camera
HUD	Ctrl+H	Show or hide the game's on-screen interface
Toggle Console	~	Open the game console
Render Wireframe / Render Textured	—	Wireframe or normal rendering
Show Object Names / Show Object NetworkIds	—	Labels over objects
Show Debug Menu	—	Debug builds only
Terrain → Purge Terrain / Reload Terrain	—	Throw away and rebuild the terrain, or reload it from disk
Terrain → Terrain Editor	—	Open the Terrain Editor
Show Target Path, Ignore Target Path, Show Path Map	—	AI pathfinding display
Show Region Browser	—	Open the Region Viewer

View menu

Item	Shortcut	What it does
Add Camera Bookmark	Ctrl+B	Save the camera position
Add Object Bookmark	Ctrl+O	Bookmark the selected object
Remove Object Bookmark	Ctrl+Alt+O	Remove its bookmark
Bookmarks ▸	—	Jump to a camera or object bookmark
Center Selection / Center Ghosts	Ctrl+E / Ctrl+Alt+E	Aim the camera at them
Fit Selection / Fit Ghosts to Screen	Ctrl+F / Ctrl+Alt+F	Frame them
Show Trigger Volumes	—	Show trigger areas
Get SphereTree Snapshot / Turn Off Debug Spheres	—	Collision debug display
Reset Camera	—	Default camera

10. Scripts, templates and server tools

The **Script** and **ObjectTemplate** menus were built for SOE's Perforce depot. They can create, view, edit, revert, submit and compile scripts and object templates, and reload them on the server. They need `connectToPerforce=true`, a Perforce server and the depot paths in `[GodClient]`. Without Perforce, use **View** to open files in the configured editor, and **Refresh** to rebuild the lists.

Menu	Items
Script	Refresh, New, Edit, View, Revert, Submit, Compile, Server Reload
ObjectTemplate → Server	Refresh, New, Edit, View, Revert, Submit, Compile, Server Reload, Server Replace, Add to favorites
ObjectTemplate → Client	Refresh, New, Edit, View, Revert, Submit, Compile, Replace, Add to favorites
Buildout Areas (Tree Browser tab)	Refresh, Edit (mark for editing), Save

Other tools

- **Tools → Send a System Message:** a message to one player, a chat room, the current planet, the current galaxy, or all of SWG.
- **Tools → Save Interior Layout:** write the objects inside the current building's cells to a layout file.
- **Tools → Grab Relative Coordinates:** the cursor's position relative to the selection, for building layouts.

11. Terrain Editor

Open it with **Window → Terrain Editor** (also **Tools** and **Game → Terrain**), then tick **Terrain brush on**. With the brush on:

- left drag uses the tool
- right drag uses its alternate (Raise ↔ Lower), or picks a height for Flatten, Level and Water level
- Alt + mouse still moves the camera

Tools: Raise, Lower, Flatten, Level, Paint texture, Clear flora, Roughen, Terrace, Plant flora, Road, River, Water level, Smooth, Ramp, Copy ground, Stamp, Object scatter and Waterfall.

- **Copy ground** and **Stamp:** copy the shape of a piece of ground and stamp it elsewhere, turned, mirrored or scaled, or stamp a greyscale heightmap image as a mountain or crater.
- Outlines on the ground show the brush, the shape being dragged, and where a stamp will go.
- **Object scatter:** paints real server objects (the template selected in the Tree Browser) at any density, with Undo and Redo. They live on the server, not in the `.trn`.
- **Water:** lakes and rivers join water that's already there at the same level, and **Waterfall** builds a falling sheet of water from a cliff top into a pool.
- **Ramp:** drag from one end to the other for a straight slope between the two ground heights.
- **Flatten under selected objects:** a button that levels the ground under the selected buildings to their base height.
- Plant flora also plants bushes, grass and trees.
- Every tool except Road and River can fill a rectangle, circle or polygon instead of a brush stroke.
- The **Limits** box keeps Paint, Plant flora and Clear flora to a slope range, a height band or one existing texture.
- **Flora scatter, whole planet (%)** stops bushes, rocks and grass from standing in rows.
- Water level keeps lakes just below the shoreline, in a dug basin.

Edits have Undo and Redo. **Save (this client)** writes the planet's `.trn` into this client's data (backed up first), and **Revert to saved** reloads it. The **Save destinations** box also saves it to your own storage folder

(default `J:\SWG_Assets_storage`) or sends it to the server's data folder; both keep a backup of any file they replace. The server only uses terrain edits after a restart.

The full Terrain Editor manual is a separate file: `J:\SWG_Claude\GodClient_Terrain_Editor_Manual.pdf` (or `.md`).

12. Troubleshooting

Problem	Cause and fix
Moves don't stick	You moved the ghosts; press **Ctrl+T** (Apply Transform). Locked objects need **Unlock Selected** (Ctrl+U) first
Server ignores edits	The account has no god rights on the server
Can't log in	Check `loginServerAddress0` and `loginServerPort0` in the cfg files, and that the server is running
Script or template commands fail	They need Perforce (`connectToPerforce`) and the depot paths; use View and the configured editor instead
Keys move the avatar, not the camera	Game focus is on; press **Enter** to toggle it
Left click doesn't select	The Terrain Editor brush is on; untick **Terrain brush on**
"Warnings logged" box at exit	Harmless data warnings; `demoMode=true` in `user.cfg` hides it
Client slow to close (about 16–25 s)	Normal shutdown; not a hang
Terrain edits or fixes don't show	A different copy of the client was started; use the one in `exe\win32_new`