CS 111: Operating System Principles Lecture 15

Locking

1.0.0

Jon Eyolfson May 11, 2021



Locks Ensure Mutual Exclusion

Only one thread at a time can be between the lock and unlock calls

It does not help you ensure ordering between threads

Assume you had a circular buffer you want to use in a producer/consumer scenario e.g. 1s | wc

1

Semaphores are Used for Signaling

Semaphores have a value that's shared between threads/processes

```
#include <semaphore.h>
int sem_init(sem_t *sem, int pshared, unsigned int value)
```

There may up to value number of things with the semaphore simultaneously

It has two fundamental operations wait and post wait decrements the value atomically post increments the value atomically

If wait will not return until the value is greater than 0

Semaphore API is Similar to pthread Locks

```
#include <semaphore.h>
int sem_init(sem_t *sem, int pshared, unsigned int value)
int sem_destroy(sem_t *sem);
int sem_post(sem_t *sem);
int sem_wait(sem_t *sem);
int sem_trywait(sem_t *sem);
```

All functions return 0 on success

The pshared argument is a boolean, you can set it to 1 for IPC For IPC the semaphore needs to be in shared memory

How Could We Make This Print "Thread 1" then "Thread 2"?

```
#include <pthread.h>
#include <stdio.h>
#include <semaphore.h>
#include <stdlib.h>
void* p1 (void* arg) { printf("Thread 1\n"): return NULL: }
void* p2 (void* arg) { printf("Thread 2\n"): return NULL: }
int main(int argc, char *argv[])
    pthread t thread[2];
    pthread create(&thread[0], NULL, p1, NULL);
    pthread create(&thread[1], NULL, p2, NULL);
    pthread join(thread[0], NULL);
    pthread_join(thread[1], NULL);
    return EXIT SUCCESS:
```

This Code Prints "Thread 1" then "Thread 2"

```
static sem t sem;
void* p1 (void* arg) {
  printf("Thread 1\n");
  sem post(&sem);
void* p2 (void* arg) {
  sem_wait(&sem);
  printf("Thread 2\n");
int main(int argc, char *argv[])
  sem_init(&sem, 0, 0);
 /* rest as before */
```

No Matter Which Thread Executes First, We Get the Same Order

The value is initially 0

Assume "Thread 2" executes first It executes sem_wait, which is 0, and doesn't continue

"Thread 1" doesn't have to wait, it prints first before it increments the value

"Thread 2" can then execute its print statement

What happens if we initialized the value to 1?

We Can Use a Semaphore as a Mutex


How?

Using a Semaphore as a Mutex, Note the value

```
static sem t sem;
static int counter = 0;
void* run(void* arg) {
    for (int i = 0; i < 100; ++i) {
        sem wait(&sem);
        ++counter;
        sem post(&sem):
int main(int argc, char *argv[])
  // Create 8 threads
  // Join 8 threads
  sem_init(&sem, 0, 1);
  printf("counter = %i\n", counter);
```

Can We Come Up with a Solution for a Producer/Consumer Problem?

Assume you have a circular buffer:



The producer should write to the buffer As long as the buffer is not full

The consumer should read to the buffer As long as the buffer is not empty

We Would Create Two Semaphores, What values Should We Use?

```
sem t full;
sem t empty;
sem init(&full, 0, /* ??? */);
sem init(&empty, 0, /* ??? */);
void producer() {
 // produce data
 sem wait(empty);
 // fill a slot
 sem post(full);
void consumer() {
 sem wait(full);
 // empty a slot
 sem_post(empty);
 // consume data
```

The Previous values Depend on the Buffer Size

full should always be initialized to 0

empty should be initialized to the size of the buffer $-\ N$

Do we need any extra locking?

The Previous values Depend on the Buffer Size

full should always be initialized to 0

empty should be initialized to the size of the buffer $-\ N$

Do we need any extra locking? No, if there's a single producer and consumer Yes, otherwise

Monitors Are Built Into Some Languages

With object oriented programming, developers wanted something easier to use

Could mark a method as monitored, and let the compiler handle locking

An object can only have one thread active in its monitored methods

It's basically one mutex per object, created for you The compiler inserts calls to lock and unlock

Java's synchronized Keyword is an Example of a Monitor

```
public class Account {
 int balance:
 public synchronized void deposit(int amount) { balance += amount: }
 public synchronized void withdraw(int amount) { balance -= amount: }
the compiler transforms to:
 public void deposit(int amount) {
    lock(this.monitor);
    balance += amount;
    unlock(this.monitor);
 public void withdraw(int amount) {
    lock(this.monitor);
    balance -= amount;
    unlock(this.monitor);
```

Condition Variables Behave Like Semaphores

You can create your own custom queue of threads

The wait functions add this thread to the queue signal wakes up one thread, broadcast wakes up all threads

Condition Variables MUST Be Paired with a Mutex

Any calls to wait, signal, and broadcast must already hold the mutex

Why? wait needs to add itself to the queue safely (without data races)

It needs the mutex as an argument to unlock it before going to sleep

One mutex can also protect multiple condition variables

We'll only consider calls to wait and signal

We Can Use Condition Variables for Our Producer/Consumer

```
pthread mutex t mutex;
int nfilled;
pthread_cond_t has_filled;
pthread cond t has empty;
                                              void consumer() {
                                                pthread mutex lock(&mutex);
void producer() {
                                                // empty a slot
                                                if (nfilled == 0) {
 // produce data
  pthread mutex lock(&mutex):
                                                  pthread cond wait(&has filled.
 // fill a slot
                                                                    &mutex):
  if (nfilled == N) {
    pthread cond wait(&has empty,
                                                pthread cond signal(&has empty);
                      &mutex):
                                                pthread mutex unlock(&mutex);
                                                // consume data
  ++nfilled;
  pthread_cond_signal(&has_filled);
  pthread mutex unlock(&mutex);
```

Condition Variables Serve a Similar Purpose as Semaphores

You can think of semaphores as a special case of condition variables

They'll go to sleep when the value is 0, when it's greater than 0 they wake up

You can implement one using the other, however it can get messy

For complex conditions condition variables offer much better clarity

Locking Granularity is the Extent of Your Locks

You need locks to prevent data races

Lock large sections of your program, or divide the locks and use smaller sections? Lab 3

Things to consider about locks:

- Overhead
- Contention
- Deadlocks

Locking Overheads

- Memory allocated
- Initialization and destruction time
- Time to acquire and release locks

The more locks you have, the greater each cost is going to be

You Do NOT Want Deadlocks

The more locks you have, the more you have to worry about deadlocks

Conditions for deadlocking:

- 1. Mutual Exclusion (of coruse for simple locks)
- 2. Hold and Wait (you have a lock and try to acquire another)
- 3. No Preemption (we can't take simple locks away)
- 4. Circular Wait (waiting for a lock held by another process)

A Simple Deadlock Example

Consider two processors trying to get two locks:

| Thread 1 | Thread 2 |
|----------------|----------------|
| Get Lock 1 | Get Lock 2 |
| Get Lock 2 | Get Lock 1 |
| Release Lock 2 | Release Lock 1 |
| Release Lock 1 | Release Lock 2 |

Thread 1 gets Lock 1, then Thread 2 gets Lock 2, now they both wait for each other Deadlock

You Can Ensure Order to Prevent Deadlocks

```
void f1() {
    locktype_lock(&l1);
    locktype_lock(&l2);
    // protected code
    locktype_unlock(&l2);
    locktype_unlock(&l1);
}
```

This code will not deadlock, you can only get 12 if you have 11

You Could Also Prevent A Deadlock by Using trylock

Remember, for pthread there's trylock that returns 0 if it gets the lock

```
void f2() {
   locktype_lock(&l1);
   while (locktype_trylock(&l2) != 0) {
       locktype_unlock(&l1);
       // wait
      locktype_lock(&l1);
   }
   // protected code
   locktype_unlock(&l2);
   locktype_unlock(&l1);
}
```

This code will not deadlock, it will give up 11 if it can't get 12

We Explored More Advanced Locking

Before we did mutual exclusion, now we can ensure order

- Semaphores are an atomic value that can be used for signaling
- Condition variables are clearer for complex condition signaling
- Locking granularity matters, you'll find out in Lab 3
- You must prevent deadlocks