

Computer Networks - Xarxes de Computadors

Outline

- Course Syllabus
- Unit 1: Introduction
- Unit 2. IP Networks
- Unit 3. LANs
- Unit 4. TCP
- Unit 5. Network applications

Based on: https://studies.ac.upc.edu/FIB/grau/XC/#slides



Outline


- Introduction
- IEEE LAN Architecture
- Ethernet
- Ethernet Switches
- Wireless LANs




Unit 3. Local Area Networks, LANs Introduction – WAN and LAN differences

- WANs:
 - Main goal: scalability.
 - Switched network with mesh topology.
- LANs:
 - Multy-access network with shared media.
 - A Medium Access Control (MAC) protocol is needed.

To govern the access to the transmission medium



LANS



(PSTN – Public switched telephony network)




Outline

- Introduction
- IEEE LAN Architecture
- Ethernet
- Ethernet Switches
- Wireless LANs



Unit 3. Local Area Networks, LANs IEEE LAN Architecture


OSI Reference model:



- LLC sublayer (802.2):
 - Common to all 802.x MAC standards.
 - Define the interface with the upper layer and specifies several services (operational modes):
 - (i) unacknowledged connectionless, (ii) connection oriented, (iii) acknowledged connectionless.
- MAC sublayer:
 - Define the medium access protocol. It is different for each LAN technology.



IEEE LAN Architecture – LAN encapsulation





Unit 3. Local Area Networks, LANs Types of MACs

• Token Passing:

 Only the station having the token can transmit. After transmission the token is passed to another station.
 Examples: FDDI and Token-Ring (obsolete)

Random:

- There is no token. Instead, there is a non null collision probability. In case of collision, the frame is retransmitted after a random *backoff* time.
- Examples: Ethernet, WiFi



IEEE LAN Architecture – IEEE 802 standards (some)

802.1: LAN/MAN architecture.

802.2 Logical Link Control (LLC)

802.3 Ethernet

802.4 Token Bus

802.5 Token Ring

802.8 FDDI

802.11 WiFi: Wireless LANs.

802.15 Personal Area Networks or short distance wireless networks (WPAN)

802.15.1 Bluetooth

802.15.4 low data rate and low cost sensor devices

802.16 WiMAX: broadband Wireless Metropolitan Area Networks.

Name	Description	Status		
IEEE 802.1	Higher Layer LAN Protocols Working Group	Active		
IEEE 802.2	LLC	Disbanded		
IEEE 802.3	Ethernet	Active		
IEEE 802.4	Token bus	Disbanded		
IEEE 802.5	Token Ring MAC layer	Disbanded		
IEEE 802.6	MANS (DQDB)	Disbanded		
IEEE 802.7	Broadband LAN using Coaxial Cable	Disbanded		
IEEE 802.8	Fiber Optic TAG	Disbanded		
IEEE 802.9	Integrated Services LAN (ISLAN or isoEthernet)	Disbanded		
IEEE 802.10	Interoperable LAN Security	Disbanded		
IEEE 802.11	Wireless LAN (WLAN) & Mesh (Wi-Fi certification)	Active		
IEEE 802.12	100BaseVG	Disbanded		
IEEE 802.13	Unused ^[2]	reserved for Fast Ethernet development ^[3]		
IEEE 802.14	Cable modems	Disbanded		
IEEE 802.15	Wireless PAN	Active		
IEEE 802.15.1	Bluetooth certification	Disbanded		
IEEE 802.15.2	IEEE 802.15 and IEEE 802.11 coexistence	Hibernating ^[4]		
IEEE 802.15.3	High-Rate wireless PAN (e.g., UWB, etc.)	?		
IEEE 802.15.4	Low-Rate wireless PAN (e.g., ZigBee, WirelessHART, MiWi, etc.)	Active		
IEEE 802.15.5	Mesh networking for WPAN	?		
IEEE 802.15.6	Body area network	Active		
IEEE 802.15.7	Visible light communications	?		
IEEE 802.16	Broadband Wireless Access (WiMAX certification)	hibernating		
IEEE 802.16.1	Local Multipoint Distribution Service	hibernating		
IEEE 802.16.2	Coexistence wireless access	hibernating		

Source: https://en.wikipedia.org/wiki/IEEE_802

See: http://grouper.ieee.org/groups/802/1, 2, ...



Outline

- Introduction
- IEEE LAN Architecture
- Ethernet
- Ethernet Switches
- Wireless LANs



Unit 3. Local Area Networks, LANs Ethernet – Introduction

- Designed by Bob Metcalfe at Xerox in mid-70s.
- Initially was commercialized by Digital, Intel and Xerox consortium (DIX).
- Ethernet was standardized by IEEE (802.3) in 1983.
- Nowadays Ethernet is the leading LAN technology. There are numerous Ethernet standards with different transmission mediums, and line bitrates. There are several active Ethernet working groups inside IEEE 802.3.



Unit 3. Local Area Networks, LANs Carrier Sense Multiple Access/Collision Detection (CSMA/CD)


- Is a random MAC where the stations "listen" the medium (*carrier sense*) before transmission.
- When the medium is becomes free the frame is transmitted immediately, and the medium is listened to detect collisions.
- In case of collision, the frame is retransmitted after a random *backoff* time.



Unit 3. Local Area Networks, LANs Ethernet – CSMA/CD Ethernet protocol (simplified)

Legend:


- InterPacket Gap (IPG): 96 bits.
- JAM: 32 bits that produce an erroneus CRC.
- $backoff = n T_{512}$
- T_{512} : *SlotTime* (51,2 µs at 10 Mbps)
- $n = \text{random}\{0, 2^{\min\{N, 10\}}-1\},\$
 - N: number of retransmission of the same frame (1, 2...)
- The transmitting station must detect the collision (no ack is sent).





Unit 3. Local Area Networks, LANs Ethernet – Collision example

Stations A y B have frames ready to Tx:



NOTE: The preamble is not interrupted in case of collision, and the JAM is Tx immediately after.



Unit 3. Local Area Networks, LANs Ethernet – Half Duplex and full-duplex

- Half Duplex: Using CSMA/CD only one NIC can be simultaneously transmitting into the medium.
- Full Duplex: When 2 Ethernet NICs are connected point-to-point, some Ethernet standards allow a full-duplex Tx, .
- Ethernet NICs have an auto-negotiation mechanism to detect the full-duplex availability.
- In full-duplex mode Ethernet NICs deactivate CSMA/CD (no collisions can occur).



Ethernet – Frames

• Ethernet II (DIX) Frame:

- Min. length: 64B => Padding with 0 if needed (e.g. ARP). Wireshark keep in mind:
 - FCS also known as CRC (cyclic redundancy check) are stripped by NICs => -4B
 - Padding done by NICs => Not show in outgoing frames
- Preamble: Give time to detect, synchronize and start reception.
- Frame type: Identifies the upper layer protocol (IP, ARP, etc. RFC 1700, Assigned numbers)
 - 0x0800 for IPv4
 - 0x0806 for ARP
 - 0x86DD for IPv6
 - (0x8808 for Ethernet flow control (Control opcode: 0x0001))
 - 0x8100 for VLAN tagging (see subsection Virtual LANS)

xBasey



Unit 3. Local Area Networks, LANs Ethernet – Different Ethernet Standards

Denomination:

Line bitrate:

- 10: 10 Mbps
- 100: 100 Mbps
- 1000: 1000 Mbps (1 Gbps)
- 10G: 10 Gbps

Base band signal.

Broad: translated band signal.

Various meanings:

- Number: Maximum segment distant in hundreds of m.
- Reference to the medium type:
 - T: UTP
 - F: Optical Fiber
 - Other:
 - T4: Uses 4 UTP pairs.
 - TX: Full Duplex
 - ...



Unit 3. Local Area Networks, LANs Ethernet – Different Ethernet Standards (some)

Commercial					Cabling	UTP/OF Pairs			segment distance*	
name	bps	Standard	year	Name			Connector	Codification	Half duplex	Full duplex
Ethernet	10Mbps	802.3	1983	10Base5	Coax-thick	-	AUI	Manchester	500m	n/a
		802.3a	1985	10Base2	Coax-thin	-	BNC	Manchester	185m	n/a
		802.3i	1990	10BaseT	UTP-cat.3	2	RJ45	Manchester	100m	100m
		802.3j	1993	10BASE-FL	FO	2	SC	on/off Manchester	2000m	>2000m
Foot	100Mbps	802.3u	1995	100BaseTX	UTP-cat.5	2	RJ45	4B/5B	100m	100m
Fast Ethernet		802.3u	1995	100BaseFX	FO	2	SC	4B/5B	412m	2000m
		TIA/EIA-785	1999	100BaseSX	FO/led	2	SC	4B/5B	300m	300m
Gigabit-Eth.	1Gbps	802.3z	1998	1000BaseSX	FO	2	SC	8B/10B	275-316m	275-550m
		802.3z	1998	1000BaseLX	FO	2	SC	8B/10B	316m	550-10000m
		802.3z	1998	1000BaseLH	FO	2	SC	8B/10B	n/a	100km
		802.3ab	1999	1000BaseT	UTP-cat. 5e	4	RJ45	PAM5	100m	100m
10Gigabit- Eth.	10Gbps	802.3ae	2002	10GBASE-CX4	InfiniBand	4	CX4	8B/10B	n/a	15m
		802.3ae	2002	10GBASE-SR	FO	2	SC	64B/66B	n/a	26-300m
		802.3ae	2002	10GBASE-LR	FO	2	SC	64B/66B	n/a	10km
		802.3ae	2002	•••	FO	2	SC	•••	n/a	***

^{*}With OF the distance depends on the OF type.




Unit 3. Local Area Networks, LANs Ethernet – Different Ethernet Standards: 10BaseT

1990. Cable UTP-cat 3.


- Hub: Is a multi-port repeater (layer 1).
- The signal received in 1 port is retransmitted by all the others.
- Always half duplex

Otherwise it could receive data from more than one port simultaneously, which is incompatible with "The signal received in 1 port is retransmitted by all the others"

10BaseT segments







NIC "combo": Supports 10Base5, 10Base2, 10BaseT



Unit 3. Local Area Networks, LANs Ethernet – Different Ethernet Standards: after 10BaseT

All standards use UTP o OF (except 10GBaseCX4):

- Fast Ethernet (1995). 100BaseTX: UTP-cat. 5
- Gigabit Ethernet (1998). 1000BaseT: UTP-cat 5e
- 10Gigabit Ethernet (2002). Uses optical fiber. The only copper standard is Infiniband with segment size ≤ 15 m.



NIC 10/100 – RJ45 10BaseT-100BaseTX \$11.99



NIC 10/100/1000 - SC 10BaseFL-100BaseFX-1000Base-SX \$151



NIC 10Gbps – CX4 10GBaseCX4 \$795



Infiniband cable with CX4 connectors



Outline


- Introduction
- IEEE LAN Architecture
- Ethernet
- Ethernet Switches
- Wireless LANs



Ethernet Switches - Introduction

- Hub problem: If many stations are connected, may be inefficient due to collisions.
- Solution: bridges and switches.
- Ethernet bridge:
 - "plug and play" layer 2 device.
 - In each port there is a NIC in "promiscuous" mode: Capturing all frames.
 - The source address is used to "learn" which MAC is present in each port (MAC table). Each entry has the MAC and the port numbers.
 - The destination MAC is used to decide whether the frame needs to be retransmitted by another port.
 - Segments the "collision domain".





How the bridge works:


- If a frame is received with a source address not in the MAC table, it is added (*learning bridge*).
- If a frame from D1 is received with a destination address that: (i) is in D2, (ii) it is not in the table, (iii) it is broadcast: It is sent into D2 (*flooding*).
- If it is received a frame from D1 addressed to another station from D1, it is discarded (*filtering*).
- The entries have an *aging timer*. Each time an entry is used, it is refreshed. If the aging timer expires, the entry is removed.

Advantages:

- Segments the collision domain (less collisions).
- Clients in D1 and D2 can simultaneously send frames to their servers.



Ethernet Switches - Switch Architecture



Switch#show mac-a	ddress-table
Address	Dest Interface
00D0.5868.F583	FastEthernet 2
00E0.1E74.6ADA	FastEthernet 1
00E0.1E74.6AC0	FastEthernet 1
0060.47D5.2770	FastEthernet 3
00D0.5868.F580	FastEthernet 5





MAC Table in a CISCO Switch


Edge and backbone CISCO switches.


How the switch works:


- It is equivalent to a "multiport bridge".
- When a frame is received with a source address not in the table, it is added.
- If a frame is received with a destination address: (i) not in the table, (ii) broadcast or multicast: copy the frame in all transmission buffer of the other ports (flooding).
- If a frame is received with the address from another port: It is switched as fast as possible the transmission buffer of that port.
- If receives a frame addressed to another station from the same port, it is discarded (filtering).



Unit 3. Local Area Networks, LANs Ethernet Switches - Switch Capabilities







Simultaneous Transmissions

Ports with Different bitrates

Full Duplex Ports


- Each port is different a collision domain (less collisions).
- Different ports can be simultaneously Tx/Rx.
- Ports can have different bitrates.
- Ports may be full-duplex (usable if only one host is connected).
- There can be ports simultaneouly in half or full duplex mode.
- Link aggregation: Bitrate can be increased by aggegating several links, which behave as a slingle one (*etherchannel* in CISCO).
- Security: Stations can only capture the traffic of their collision domain.

...



Unit 3. Local Area Networks, LANs Ethernet Switches - Broadcast and Collision Domains

- Broadcast Domain: Set of stations that will received a broadcast frame sent by any of them.
- Unless Virtual LANs are used, a switch does not segment the broadcast domain.
- A router segment the broadcast domain.
- The broadcast reachability is important because allows reaching stations having one hop connectivity (with ARP).




leave the broadcast domain a router is required.



Ethernet Switches – Flow Control

- Switch Flow Control: Consists of adapting the rate at which the switch receives the frames, and the rate at which the switch can send them.
- Examples:






If no flow control is used, frames could be lost by buffer overflow.

- Flow control techniques (back pressure):
 - Jabber signal (half duplex): The switch sends a signal into the port which need to be throttled down, such that CSMA see the medium busy.
 - Pause frames (full duplex): The switch send special *pause frames*. These frames have an integer (2 bytes) indicating the number of slot-times (512 bits) that the NICs receiving the frame must be silent.



Unit 3. Local Area Networks, LANs Ethernet Switches – Problems of Flow Control

• Flow Control can introduce inefficiencies (*head of line blocking*):




The slow link may trigger the flow control and send pause frames towards the server, causing under-utilization of the switch-server link.

- We would expect a download of approximately 90 Mbps for PC1 and 10 Mbps for PC2. However, the flow control can make the PC1 throughput to be significantly lower. Switches allow disabling the flow control in a link (In CISCO: Switch(config-if)# flowcontrol send off). If flow control is disabled, traffic is assumed to be controlled by TCP.
- If not otherwise stated, we shall assume an *ideal* flow control in the problems, which allow achieving the maximum throughput.



Ethernet Switches – Line bitrate sharing

- Hub: If the hub is the bottleneck for all the active ports, the capacity is equally shared between all ports where frames are transmitted.
- Switch: If one congested port is the bottleneck for all ports sending traffic to it, the port bit rate is equally shared between all ports sending traffic to it.
- Example:




• If A, B and C simultaneously transmit to S: throughput $C \approx 100$ Mbps / 2 = 50 Mbps throughput A = throughput B $\approx (100 \text{ Mbps / } 2) / 2 = 25 \text{ Mbps}$



Unit 3. Local Area Networks, LANs Ethernet Switches – Spanning Tree Protocol (STP)

- The basic principle of the "layer 2 routing" done by Ethernet switches is based on having a unique port to forward the frame towards the destination. Therefore, loops are not allowed.
- In practice loops can appear because:
 - They are introduced by accident.
 - The are desirable to have redundant path (fault tolerance).
- If loops are introduced without protection a *broadcast storm* is No TTL at this layer produced, and the network blocks:

 Frames multiply and remain turning indefinitely in the loop!



Other problems:

- Reception of duplicated frames
- MAC Tables instability


 \parallel

Solution: IEEE 802.1D Spanning Tree Protocol (STP)



Unit 3. Local Area Networks, LANs Ethernet Switches – Spanning Tree Protocol (STP)

- STP goal: Build a loop free topology (STP-tree) with optimal paths. The ports that do not belong to the STP tree are blocked.
- The switches send 802.1D messages to their neighbors to build up the STP-tree. If the topology changes (e.g. due to a link failure), a new STP-tree is setup.






Unit 3. Local Area Networks, LANs Ethernet Switches – Virtual LANs, VLANs


- Motivation:
- Grouping related servers and hosts in different broadcast domains.
- How VLANs work:
- Each switch port belongs to a VLAN.
- The switch isolates different VLANs: The switch flooding is done only towards the ports of the same VLAN. Each VLAN is equivalent to a different physical switch.
- A router is needed to send traffic to a different VLAN.

Logic Topology



Physical Topology

Port configured in VLAN 1






Unit 3. Local Area Networks, LANs Ethernet Switches – Virtual LANs, VLANs

- Advantages:
- Flexibility of the physical placement of the devices.
- Facilitates the network grow.
- Facilitates the network management: Changing the topology, adding new subnetworks, moving ports from one network to another.
- NOTE: Since each VLAN is a different broadcast domain, usually a different STP instantiation is used for each VLAN. Thus, a different STP-tree is build in each VLAN.



Unit 3. Local Area Networks, LANs Ethernet Switches – VLAN Trunking

- Problem:
- Why connecting several ports between the same devices?
- Trunking:
- The port configured as trunk belongs to several VLANs (maybe all).
- The traffic sent in one VLAN is also sent to the trunk the VLAN belongs to.
- A tagging mechanism is used in the trunk to discriminate the traffic from different VLANs.





Ethernet Switches – VLAN Trunking

- Trunking Protocols:
- Inter-Switch Link (ISL). CISCO propietary protocol.
- IEEE-802.1Q.

"Frame type" of a standard Ethernet II header. The value 0x0811 adds 4 extra bytes to the header: the first 2 for the "TCI" and the last 2 for the the "Frame type" of the next header (IPv4, IPv6, ARP, etc.). The max. frame size is extended 1,518 bytes - 1,522 bytes. The min. frame size remains 64 bytes

IEEE-802.3 frame with the 802.1Q tag.

Legend:

- *Tag Protocol Identifier* (TPID): Field with the hex. value 0x8100 for an Ethernet frame.
- *Tag Control Information* (TCI): Contains several fields. The most important is the VLAN ID (12 bits), which identify the VLAN.



Outline

- Introduction
- IEEE LAN Architecture
- Ethernet
- Ethernet Switches
- Wireless LANs



Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – Brief WLAN History

- 1971: Prof. Norman Abramson develops ALOHANET for the University of Hawaii
- 1990: many companies develop proprietary WLANs products.
- 1996: ETSI approves HIPERLAN/1 and 1997 IEEE approves 802.11
- Late 90 and 2000: Wi-Fi Alliance, tremendous growth of 802.11 products.
- 1999: 802.11a, 802.11b. 2003: 802.11g. 2009: 802.11n...



802.11 indoor APs




802.11 NICs



802.11 outdoor



Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802.11




• ISM: Industrial Scientific and Medical. No licence required for non commercial usage.



Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802.11 Components


- Distribution System (DS):
 - Used by APs to exchange frames with one another and with wired networks. (e.g. an ethernet switch).
- Access Point (AP)
 - Simplify communication between stations.
 - All transmissions go through the AP.
 - APs are bridges and may have a collocated router.







Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802.11 Components (I/II)

- Service Set: a group of wireless network devices which share a service set identifier (SSID) typically the natural language label that users see as a network name (e.g. "My WiFi")
 - A service set is either a Basic Service Set (BSS) or an Extended Service Set (ESS)
- BSS: a subgroup of devices that share physical-layer medium access (i.e. that they are wirelessly networked)
 - Identified by a BSS Identifier (BSSID): 48 bits number
- ESS: a wireless network, created by multiple access points, which appears to users as a single, seamless network
 - Identified by a Extended Service Set Identifier (ESSID): the SSID BSS1










Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802. Components (II/II)



Source: https://en.wikipedia.org/wiki/Service_set_(802.11_network)



Wireless LANs (WLANs) – 802.11 MAC

- Carrier Sense Multiple Access with Collision Avoidance (CSMA/CA): In contrast to CSMA/CD, always wait a random backoff before Tx. Acks are needed to detect whether a transmitted frame collided.
- CSMA/CD is not used because collisions can hardly be detected in wireless (because in the antenna the Tx power is orders of magnitude higher than Rx power).

Wireless LANs (WLANs) – 802.11 Addresses

- Designed to be compatible with ethernet.
- Use non overlapping ranges with ethernet.
- The frame may have up to 4 addresses. The meaning of the addresses is specified by the bits to-DS and from-DS of the control.
- The **BSSID** is always present to identify frames belonging to the BSS



Generic frame format




Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802.11 Addresses


Scenario	Usage	to-DS	from-DS	Address1	Address2	Address3	Address4
STA→STA	Ad-hoc	0	0	DA	SA	BSSID	-
STA→AP	Infrastructure	1	0	BSSID	SA	DA	-
AP→STA	Infrastructure	0	1	DA	BSSID	SA	-
AP→AP	WDS	1	1	RA	TA	DA	SA

Legend: Destination Address (DA), Source Address (SA), Receiver Address (RA), Transmitter Address (TA)

Example:

M# ping S





Legend, frames 802.11:

MESSAGE-TYPE(to-DS, from-DS, Address1, Address2, Address3)

Legend, frames ethernet:

MESSAGE-TYPE(destination address, source address)


FF is the broadcast address




Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802.11 Addresses

Scenario	Usage	to-DS	from-DS	Address1	Address2	Address3	Address4
STA→STA	Ad-hoc	0	0	DA	SA	BSSID	-
STA→AP	Infrastructure	1	0	BSSID	SA	DA	-
AP→STA	Infrastructure	0	1	DA	BSSID	SA	-
AP→AP	WDS	1	1	RA	TA	DA	SA

Legend: Destination Address (DA), Source Address (SA), Receiver Address (FA), Transmitter Address (TA)





Legend, frames 802.11:

frame(to-DS, from-DS, Address1, Address2, Address3, Address4)

Legend, frames ethernet:


frame(destination address, source address)

The Wireless Distribution System (WDS) allows to expand a wireless network over multiple APs without the need of a DS



Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – Hidden Node Problem


- Node A is in coverage with AP and C
- A and B cannot hear each other
- When A transmits to AP, B cannot detect the transmission using the carrier sense mechanism
- If B transmits, a collision will occur at AP





Unit 3. Local Area Networks, LANs Wireless LANs (WLANs) – 802.11 RTS/CTS

Optional mechanism to solve the hidden node problem.



- RTS is sent using the basic access mechanism.
- Upon receiving a RTS/CTS, the station set the Network Allocation Vector (NAV) to the indicated duration. While the NAV is non zero, the virtual carrier sensing indicates that the medium is busy.
- RTS/CTS is only used for unicast Tx.
- There is a threshold indicating the minimum frame size for using RTS/CTS.



Exercicis proposats

- Exàmens:
 - 2020p-ef: problemes des de 1 a 10
- Col·lecció problemes:
 - Problema 9
 - Problema 10
 - Problema 11
 - Problema 13
 - Problema 14 (Versió 19: hi ha un error a les solucions d'escenari 1 i escenari 2: el control de flux el fan les NICs per CSMA/CD)