

Topics on Fundamental Science

D. T. McGuinness, Ph.D



M.Sc Electrodynamics Lecture Book

2026.WS





2026.WS

Electrodynamics

Lecture Book

D. T. McGuinness, Ph.D

MCI

(2026, D. T. McGuinness, Ph.D)

Current version is 2026.WS.

This document includes the contents of Electrodynamics, official name being *Elektrodynamik*, taught at MCI in the Mechatronik Smart Technologies. This document is the part of the module MECH-M-1-EDY-EDY-VO taught in the M.Sc degree.

All relevant code of the document is done using *SageMath* where stated and Python v3.14.3.

This document was compiled with Lua $\text{\TeX}$ v1.24.0, and all editing were done using GNU Emacs v30.2 using AUCT $\text{\TeX}$ and org-mode package.

This document is based on the following books and resources shown in no particular order:

A modern introduction to classical electrodynamics by Maggiore Michele , Oxford University Press (2023) *Introduction to Electrodynamics (4th Edition)* by Griffiths David J. , Cambridge University Press (2023) *Field and Wave Electromagnetics* by Cheng David Keun. , Pearson Education India (1989). by *Electromagnetic Waves and Radiation* , by *Schaums Electromagnetics* ,

The document is designed with no intention of publication and has only been designed for education purposes.

The current maintainer of this work along with the primary lecturer

is D. T. McGuinness, Ph.D. (dtm@mci4me.at).

Table of Contents

Part I Prologue

Chapter 1	The Purpose of Electromagnetism	3
1.1	Mechanics in Four Different Views	3
	Electromagnetism and Relativity · Four Kinds of Forces · Unifying Physical Theories · The Fields of Electrodynamics · Electric Charge · Interpreting Conservation of Charge	
Chapter 2	Vector Calculus	9
2.1	Vector Algebra	9
	Vector Operations · Vector Component Forms · Triple Products · Position, Displacement, and Separation Vectors	
2.2	Differential Calculus	16
	Ordinary Derivatives · Gradient · The Del Operator · Product Rules · Second Derivatives	
2.3	Integral Calculus	23
	Line, Surface, and Volume Integrals · The Fundamental Theorems of Vector Calculus · The Fundamental Theorem for Curls	
2.4	Curvilinear Coordinates	28
	Spherical Coordinate System · Cylindrical Coordinates	
2.5	Dirac Delta Function	31
	A Mathematical Anomaly · The 1D Dirac Delta Function · The 3D Dirac Delta Function	
2.6	Vector Field Theory	35
	Helmholtz Theorem · Potentials	

Part II Electric Fields

Chapter 3	Electrostatics	41
3.1	The Electric Field	41
	Coulomb's Law · The Electric Field · Continuous Charge Distributions	
3.2	Divergence and Curl of Electrostatic Fields	46
	Quantification · Divergence of E · Applications of Gauss's Law · Curl of E	
3.3	Electric Potential	53
	Defining the Potential · Some Digressions on Potential · Poisson's Equation and Laplace's Equation · The Potential of a Localised Charge Distribution · Boundary Conditions	
3.4	Work and Energy	61
	To Move a Charge · The Energy of a Point Charge Distribution · The Energy of a Continuous Charge Distribution · Comments on Electrostatic Energy	
3.5	Conductors	66
	Properties · Induced Charges · Surface Charge and the Force on a Conductor · Capacitors	

Part III Magnetic Fields

Part IV Electromagnetic Fields

Part V Appendix

Acronyms	79
-----------------	-----------

Supplemental List of Items

List of Figures

1.1	The Standard Model of particle physics is the theory describing three of the four known fundamental forces (electromagnetic, weak and strong interactions - excluding gravity) in the universe and classifying all known elementary particles. It was developed in stages throughout the latter half of the 20th century, through the work of many scientists worldwide, with the current formulation being finalized in the mid-1970s upon experimental confirmation of the existence of quarks.	6
2.1	A mnemonic, used to define the orientation of axes in three-dimensional space and to determine the direction of the cross product of two vectors, as well as to establish the direction of the force on a current-carrying conductor in a magnetic field. . .	11
2.2	The decomposition of the vector $\mathbf{A}$ into its components.	12
2.3	An example of a gradient field. Here the field itself is plotted by using arrows to designate the direction of the gradient. To explain the magnitude of the gradient it is either shown by the length of the arrow or by imposing colour on to the plot, which the latter has been used here. Extending this plot to our example, we can see that most of the high temperature resides on the edges of the room whereas the centre remains cool.	16
2.4	Visual description of the divergence operation and their possible outcomes. . . .	18
2.5	Different behaviours of the curl operation.	19
2.6	The method in which line integral is calculated. At each point the dot product of the vector ($\mathbf{v}$) is taken with the length vector ($d\mathbf{l}$) which is always tangential to the point in which the integration is taken.	23
2.7	An visual description of the surface integral.	24
2.8	To measure the height of a mountain, it doesn't matter what way we take, as long as we know the base and the top, we will know the height	25
2.9	The two types of coordinate systems in question. (a) Spherical coordinate system (b) Spherical coordinate system.	28
2.10	The vector plot of the "divergence problem".	31
2.11	A visual representation of a 1D Dirac Delta Function. Think of it as a distribution function being squeezed to an infinitely small width.	32
3.1	An example of a singular charge in space. As can be seen a charge with a plus value will generate a repulsive force.	42

3.2	The diagram for the question “Electric Field at a Distance” (a) The geometrical description (b) Additional annotations added.	44
3.3	An example of imagining electric field as a collection of lines passing through. Here we can see the flux lines (i.e., the arrows) passing through an object.	46
3.4	An example interaction of tow charges interacting with one another with their field lines visible. Please observe that the field line spread away from the plus charge and are collected by the minus charge.	47
3.5	A visual representation of the gauss’ law.	48
3.6	An imaginary Gaussian sphere.	50
3.7		51
3.8	The relation between three (3) major variables used in the study of electrostatics.	59
3.9	A thought experiment on how to figure out the discrepancy when a boundary is changed.	59
3.10	Some may say that superconductors can be considered as “perfect conductors”, however, they exhibit quantum effects such as the Meissner effect and quantization of magnetic flux. In perfect conductors, the interior magnetic field must remain fixed but can have a zero or nonzero value [1]. In real superconductors, all magnetic flux is expelled during the phase transition to superconductivity (the Meissner effect), and the magnetic field is always zero within the bulk of the superconductor [2].	66
3.11	A visual representation of treating a non-standard body and the generated electric field. Please observe that all lines flowing from the body is perpendicular.	67
3.12	A visual representation of the electric field inside a conductor.	67
3.13	Charges induced by a point charge in a conductor (a) When a charge approaches a conductor the charges will start to move where opposite charges will move towards the point charge and same charges will move away. While there is an imbalance now, the overall charge of the conductor remains the same (b) When a charge is given inside the cavity, again similar behaviour is to be expected inside the conductor.	68
3.14	Visual description of an electric field inside a cavity. As can be seen all the lines generated by the positive side of the edge is cancelled by the negative side with it absorbs making the inside of the cavity have 0 field.	68
3.15	A parallel-plate capacitor, as shown in part A, consists of two flat conducting plates. Here one plate is positively charged and the other one is charged negatively. At a distance of d apart, an electric field ($\vec{E}$) is generated between the two (2) plates.	70

List of Tables

1.1	The four fundamental forces and their respective properties.	5
-----	--	---

List of Examples

List of Exercises

3.1	Electric Field at a Distance	43
3.2	A Gaussian Sphere	49

List of Theorems

2.1	Calculus Theorem	25
2.2	Gradient Theorem	25
2.3	Line Independence of Gradient	26
2.4	Divergence Theorem	26
2.5	Stokes' Theorem	27
2.6	Zero Curl Fields	36
2.7	Zero Divergence Fields	36



Part I

Prologue

Part Contents

Chapter 1	The Purpose of Electromagnetism	3
Chapter 2	Vector Calculus	9

But still try, for who knows what is possible . . .

(Michael Faraday, in The Life and Letters of Faraday (1870) Vol. II, edited by Henry Bence Jones, p. 483)

Chapter 1

The Purpose of Electromagnetism

Table of Contents

1.1 Mechanics in Four Different Views	3
---	---

1.1 Mechanics in Four Different Views

Newtonian mechanics is generally sufficient enough for most **everyday** applications ranging from calculating the motion an object falling from a building to predicting the motion of planets. When objects start to move at high speeds,¹ however, the *Newtonian model* fails to predict accurately and was replaced by special relativity, which was introduced by *Einstein* in 1905 [1]. For objects which are **extremely small**, sizes comparable to that of atoms, then the theory of relativity fails for different reasons, and is superseded by quantum mechanics.²

Finally, for objects which are both very fast and very small,³ a mechanics which combines both relativity and quantum principles is needed:

This relativistic quantum mechanics is known as **quantum field theory**. Even today this new model cannot claim to be a completely satisfactory system.

Luckily for us, in **M.Sc Electrodynamics**, we will **NOT** look at these models in detail but look at a specific subset of it called **electrodynamics** which is generally in the domain of classical mechanics.⁴

¹as in speeds comparable to the speed of light.

²Developed by Bohr, Schrodinger, Heisenberg, and many others, in the 1920's, mostly.

³As is common in modern particle physics.

⁴which can be extended to other domains if needed.

1.1.1 Electromagnetism and Relativity

Interestingly, electromagnetism was one of the primary catalyst for developing **general relativity**.



Historically, the *Maxwell equations* were discovered before the theory of special relativity. It was thought light waves we derived above must be oscillations of some substance which fills all of space. This was dubbed the aether.⁵ The idea was that Maxwell's equations only hold in the frame in which the aether is at rest; light should then travel at speed c relative to the aether.

We now know that the **concept of the aether is unnecessary**. Instead, *Maxwell's equations* hold in all inertial frames and are the first equations of physics which are consistent with the laws of special relativity. Ultimately, it was by studying the Maxwell equations that Lorentz was able to determine the form of the Lorentz transformations which subsequently laid the foundation for Einstein's vision of space and time [3].

⁵the postulated medium for the propagation of light [2]. It was originally used to explain the ability of the apparently wave-based light to propagate through empty space, something waves should **NOT** be able to do. The assumption of a spatial plenum of luminiferous aether, rather than a spatial vacuum, provided the theoretical medium that was required by wave theories of light.

1.1.2 Four Kinds of Forces

Classical Mechanics tells us how behavior is when subjected to a given force. There are four (4) basic forces known to physics. Listing them in the order of decreasing strength:

Strong

Holds protons and neutrons together in the atomic nucleus, have extremely short range, so we do not "feel" them, in spite of the fact that they are a hundred times more powerful than electrical forces.

Weak

Accounts for certain kinds of radioactive decay, are also of short range, and they are far weaker than electromagnetic forces.

Gravitational

it is very weak⁶ that it is only in scale of huge mass concentrations, for example the earth and the sun, that we ever notice it at all.

⁶compared to all of the others

Electromagnetic

It is the interaction which occurs between particles with electric charge through electromagnetic fields.

For reference, the electrical repulsion between two (2) electrons is 1×10^{42} times as large as their gravitational attraction.

Not only are electromagnetic forces overwhelmingly dominant in everyday life, they are also, the only ones which are completely understood.

There is, of course, a classical theory of gravity and a relativistic one, but no entirely satisfactory quantum mechanical theory of gravity has been constructed. At the present time there is a very successful theory for the weak interactions, and a strikingly attractive candidate, called chromodynamics, for the strong interactions.

Traits	Strong Force	Electromagnetism	Weak Force	Gravity
Affected Particles	quarks ¹ and gluons ²	electrically charged	quarks and leptons ³	all particles with mass
Force Carrying Particle	gluon (g)	photon ⁴ (γ)	W and Z bosons (W^+ , W^- , Z^0)	graviton (unobserved)
Acting Range	short ($\sim 1\text{ fm}$) ⁵	∞	short	∞
Strength	1	$1/137$ ⁶	1×10^{-6}	6×10^{-39}

¹ Elementary particle responsible for making **protons** and **neutron**.

² Elementary particle acting as exchange particle for the **strong force** between **quarks**.

³ Elementary particle affected by the **weak force** but not by the **strong force**.


⁴ Elementary particle that is a **quantum** of the **electromagnetic** field, such as light and radio waves.

⁵ 1 femtometre ($1\text{ fm} = 1 \times 10^{-15}\text{ m}$). i.e., the gold nucleus radius is approx. 8,45 fm.

⁶ Known as the **fine structure constant**.

Table 1.1

The four fundamental forces and their respective properties.



⁷ James Clerk Maxwell
FRS FRSE
(1831 - 1879)

A Scottish physicist and mathematician who was responsible for the classical theory of electromagnetic radiation, which was the first theory to describe electricity, magnetism and light as different manifestations of the same phenomenon. Maxwell's equations for electromagnetism achieved the second great unification in physics, where the first one had been realised by Isaac Newton. Maxwell was also key in the creation of statistical mechanics.

With the publication of *A Dynamical Theory of the Electromagnetic Field* in 1865, Maxwell demonstrated electric and magnetic fields travel through space as waves moving at the speed of light. He proposed light is an undulation in the same medium that is the cause of electric and magnetic phenomena. The unification of light and electrical phenomena led to his prediction of radio waves. As a result of his equations, and other contributions such as introducing an effective method to deal with network problems and linear conductors, he is regarded as a founder of the modern field of electrical engineering.

All these theories draw their inspiration from electrodynamics. None can claim conclusive experimental verification at this stage. So electrodynamics, a complete and successful theory, has become a pedestal for physicists:

An ideal model that other theories emulate.

The laws of classical electrodynamics were discovered in bits and pieces by Franklin, Coulomb, Ampere, Faraday, and others, but the person who completed the job, and packaged it all in the compact and consistent form it has today, was James Clerk Maxwell.⁷ The theory is now about 150 years old.

1.1.3 Unifying Physical Theories

In the beginning, electricity and magnetism were entirely separate subjects. The one dealt with glass rods and cat's fur, batteries, currents, electrolysis, and lightning, whereas the other with bar magnets, iron filings, compass needles, and the North Pole. However, in 1820 Ørsted noticed that an electric current could deflect a magnetic compass needle [4]. Soon afterwards, Ampère correctly postulated all magnetic phenomena are due to electric charges in motion. Then, in 1831, Faraday discovered that a moving magnet generates an electric current [5]. By the time Maxwell and Lorentz put the finishing touches on the theory, electricity and magnetism were inextricably intertwined.

They could no longer be regarded as separate subjects, but rather as two aspects of a single subject: electromagnetism.

Faraday speculated that light, too, is electrical in nature [6]. Maxwell's theory provided justification for this hypothesis, and soon optics, which is the study of lenses, mirrors, prisms, interference, and diffraction, was incorporated into electromagnetism. Hertz, who presented the decisive experimental confirmation for Maxwell's theory in 1888, said [7]:




Figure 1.1

The Standard Model of particle physics is the theory describing three of the four known fundamental forces (electromagnetic, weak and strong interactions – excluding gravity) in the universe and classifying all known elementary particles. It was developed in stages throughout the latter half of the 20th century, through the work of many scientists worldwide, with the current formulation being finalized in the mid-1970s upon experimental confirmation of the existence of quarks.

The connection between light and electricity is now established ... In every flame, in every luminous particle, we see an electrical process ... Thus, the domain of electricity extends over the whole of nature. It even affects ourselves intimately: we perceive that we possess ... an electrical organ-the eye.

By 1900, three (3) great branches of physics: **electricity**, **magnetism**, and **optics** had merged into a single unified theory.

It became apparent that visible light represents only a tiny “window” in the vast spectrum of electromagnetic radiation, from radio through microwaves, infrared and ultraviolet ...

Einstein worked on a further unification, which would combine gravity and electrodynamics, in much the same way as electricity and magnetism had been combined a century earlier. His unified field theory was not particularly successful, but in recent years the same impulse has spawned a hierarchy of increasingly ambitious unification schemes, beginning in the 1960s with the electroweak theory of Glashow, Weinberg, and Salam, which joins the weak and electromagnetic forces [8], and culminating in the 1980s with the superstring theory.⁸

At each step in this hierarchy, the mathematical difficulties mount, and the gap between inspired conjecture and experimental test widens; nevertheless, it is clear the unification of forces initiated by electrodynamics has become a major theme in the progress of physics.

⁸an attempt to explain all of the particles and fundamental forces of nature in one theory by modeling them as vibrations of tiny supersymmetric strings.

1.1.4 The Fields of Electrodynamics

The essential problem the theory of electromagnetism hopes to solve is:

If there exists a bunch of electric charges here, what happens to some other charge, over another place?

The classical solution takes the form of a **field theory**:

We say that the space around an electric charge is permeated by **electric** and **magnetic** fields. A second charge, in the presence of these fields, experiences a force. The fields, then, transmit the influence from one charge to the other—they “mediate” the interaction.

When a charge undergoes acceleration, a portion of the field **detaches** itself, in sense, and travels off at the speed of light, carrying with it energy, momentum, and angular momentum. We call this **electromagnetic radiation**. Its existence invites⁹ us to regard the fields as independent dynamical entities in their own right, every bit as **real** as atoms or baseballs.

⁹if not compels

Our interest accordingly shifts from the study of forces between charges to the theory of the fields themselves. But it takes a charge to produce an electromagnetic field, and it takes another charge to detect one, so we had best begin by reviewing the essential properties of electric charge.

1.1.5 Electric Charge

Charge comes in two varieties

We call **plus** and **minus**, as their effects tend to cancel.¹⁰ The interesting point here is that plus and minus charges occur in exactly equal amounts, to high precision, in bulk matter, so that their effects are almost completely neutralised.

¹⁰If we have +q and q at the same point, electrically it is the same as having no charge there at all.

Charge is conserved

Charge cannot be created or destroyed [9]. What there is now has always been. A plus charge can **annihilate** an equal minus charge, but a plus charge cannot simply disappear by itself, something must pick up that electric charge. So the total charge of the universe is fixed for all time.

This is called **global conservation of charge**. Charges also cannot disappear and then reappear in some other place, the charge, if moved must follow a continuous path. This is called **local conservation of charge**.

Charge is quantised

While there is no restrictions in classical electrodynamics which require it to be, electric charge comes only in **integer multiples** of the basic unit of charge. If we call the charge on the proton +e, then the electron carries charge e.¹¹

¹¹It is never 7.392e, or 1/2e.

1.1.6 Interpreting Conservation of Charge

Charge conservation does **NOT** mean that individual positive and negative charges cannot be created or destroyed. Electric charge is carried by subatomic particles such as **electrons** and **protons**. Charged particles can be created and destroyed in elementary particle reactions.

In particle physics, charge conservation means, in reactions that create charged particles, equal numbers of positive and negative particles are always created, keeping the net amount of charge unchanged. Similarly, when particles are destroyed, equal numbers of positive and negative charges are destroyed.

This property is supported without exception by all empirical observations so far [9].

Even though the conservation of charge requires that the total quantity of charge in the universe is constant, it leaves open the question of what that quantity is. Most evidence indicates that the net charge in the universe is zero [10]. That is, there are equal quantities of positive and negative charge.

References

1. Einstein, A. On the electrodynamics of moving bodies (1905).
2. Brewer, E. C. *A guide to the scientific knowledge of things familiar* (CS Francis & Company, 1852).
3. Tong, D. *Ch 5. Electromagnetism and Relativity* 2024.
4. Snelders, H. A. M. Oersted's discovery of electromagnetism. *Romanticism and the Sciences*, 228–40 (1990).
5. Al-Khalili, J. The birth of the electric machines: a commentary on Faraday (1832)'Experimental researches in electricity'. *Philosophical transactions. Series A, Mathematical, physical, and engineering sciences* **373**, 20140208 (2015).
6. Schatz, P. & McCaffery, A. The faraday effect. *Quarterly Reviews, Chemical Society* **23**, 552–584 (1969).
7. Hertz, H. *On the relations between light and electricity in Heinrich Rudolf Hertz (1857-1894)* 273–288 (Routledge, 2019).
8. Bilenky, S. M. & Hosek, J. Glashow-Weinberg-Salam theory of electroweak interactions and the neutral currents. *Physics Reports* **90**, 73–157 (1982).
9. Purcell, E. M. *Electricity and magnetism* (Cambridge university press, 2013).
10. Orito, S & Yoshimura, M. Can the universe be charged? *Physical review letters* **54**, 2457 (1985).

Chapter 2

Vector Calculus

Table of Contents

2.1	Vector Algebra	9
2.2	Differential Calculus	16
2.3	Integral Calculus	23
2.4	Curvilinear Coordinates	28
2.5	Dirac Delta Function	31
2.6	Vector Field Theory	35

To understand how electromagnetism works we need to have a look at how **direction** is defined using mathematical notation. In this chapter we will have a good tour of the field of **vector calculus** and learn all then necessary concepts to tackle problems.

This chapter is treated as a more condensed, and specialized chapter of **M.Sc Higher Mathematics I** chapter of Differential and Integral Calculus and therefore, the student is suggested to look into those chapters to get a more in depth understanding of concepts if it is required.

2.1 Vector Algebra

Walking 5 km north and then 12 km east, we will have gone a total of 17 km, but if we carefully observe our current position, we will realize that we're not 17 km from where we set out, but only 13 km. To describe these quantities, we need a set of mathematics principles, which evidently do **NOT** add in the ordinary way.

2.1.1 Vector Operations

The reason they don't, is **displacements** have *direction* as well as *magnitude*, and it is essential to take both into account when we combine them. Such objects are called **vectors**.

For example: velocity, acceleration, force, momentum ...

By contrast, quantities which have magnitude but possess no direction are called **scalars**.

For example: mass, charge, density, temperature, ...

We will use **boldface** (**A**, **B**, and so on) for vectors and **normal-font** for scalars. The magnitude of a vector **A** is written $|\mathbf{A}|$ or, more simply, A . In diagrams, vectors are denoted by arrows:

the length of the arrow is proportional to the magnitude of the vector, and the arrow indicates its direction.

Minus A ($-\mathbf{A}$) is a vector with the same magnitude as **A** but of opposite direction.

Vectors have magnitude and direction but **not location**.

Here we will define four (4) vector operations: addition and three kinds of multiplication.

Addition of Two Vectors Place the tail of **B** at the head of **A**. Their sum, $\mathbf{A} + \mathbf{B}$, is the vector from the tail of **A** to the head of **B**. Addition is commutative¹:

$$\mathbf{A} + \mathbf{B} = \mathbf{B} + \mathbf{A},$$

5 kilometers east followed by 12 kilometers north gets us to the same place as 12 kilometers north followed by 5 kilometers east. Addition is also associative²:

$$(\mathbf{A} + \mathbf{B}) + \mathbf{C} = \mathbf{A} + (\mathbf{B} + \mathbf{C}).$$

To subtract a vector, add its opposite

$$\mathbf{A} - \mathbf{B} = \mathbf{A} + (-\mathbf{B}).$$

Multiplication by a Scalar Value Multiplication of a vector by a positive scalar a multiplies the *magnitude* but leaves the direction **unchanged**. This means if a is negative, the direction is reversed. Scalar multiplication is distributive³:

$$a(\mathbf{A} + \mathbf{B}) = a\mathbf{A} + a\mathbf{B}.$$

¹Meaning that the order in which elements are combined, swapped, or operated upon does **NOT** change the final result.

²Meaning that when we are adding or multiplying three or more numbers, the way we group them with parentheses does not change the result.

³Meaning that, multiplying the sum (or difference) of numbers by a factor gives the same result as multiplying each number individually by that factor and then adding (or subtracting) the products.

Dot Product of Two Vectors The dot product of two vectors is defined by:

$$\mathbf{A} \cdot \mathbf{B} \equiv AB \cos \theta$$

where θ is the angle they form when placed tail-to-tail.

$\mathbf{A} \cdot \mathbf{B}$ is itself a scalar.⁴

⁴which is why its alternative name is **scalar product**.

The dot product is both *commutative* and *distributive*,

$$\text{(Commutative)} \quad \mathbf{A} \cdot \mathbf{B} = \mathbf{B} \cdot \mathbf{A},$$

$$\text{(Distributive)} \quad \mathbf{A} \cdot (\mathbf{B} + \mathbf{C}) = \mathbf{A} \cdot \mathbf{B} + \mathbf{A} \cdot \mathbf{C},$$

Geometrically, $\mathbf{A} \cdot \mathbf{B}$ is the product of A times the projection of $\mathbf{B}$ along $\mathbf{A}$.⁵ If the two (2) vectors are parallel, then $\mathbf{A} \cdot \mathbf{B} = AB$. In particular, for any vector $\mathbf{A}$,

⁵Or the product of B times the projection of $\mathbf{A}$ along $\mathbf{B}$.

$$\mathbf{A} \cdot \mathbf{A} = A^2$$

If $\mathbf{A}$ and $\mathbf{B}$ are perpendicular, then $\mathbf{A} \cdot \mathbf{B} = 0$.

Cross Product of Two Vectors The cross product of two (2) vectors is defined by:

$$\mathbf{A} \times \mathbf{B} \equiv AB \sin \theta \hat{n}$$

where $\hat{n}$ is a **unit vector**⁶ pointing **perpendicular** to the plane of $\mathbf{A}$ and $\mathbf{B}$. Of course, there are two directions perpendicular to any plane: **in** and **out**.

⁶Meaning it is a vector with a magnitude of 1.

The ambiguity is resolved by the **right-hand rule**, shown in Fig. 2.1: let our fingers point in the direction of the first vector and curl around (via the smaller angle) toward the second; then our thumb indicates the direction of $\hat{n}$.

$\mathbf{A} \times \mathbf{B}$ is itself a *vector* and it is also known as **vector product**.




Figure 2.1

A mnemonic, used to define the orientation of axes in three-dimensional space and to determine the direction of the cross product of two vectors, as well as to establish the direction of the force on a current-carrying conductor in a magnetic field.

The cross product is *distributive*,

$$\mathbf{A} \times (\mathbf{B} + \mathbf{C}) = (\mathbf{A} \times \mathbf{B}) + (\mathbf{A} \times \mathbf{C})$$

but **NOT** commutative:

$$(\mathbf{B} \times \mathbf{A}) = -(\mathbf{A} \times \mathbf{B})$$

If two (2) vectors are parallel, their cross product is zero. In particular,

$$\mathbf{A} \times \mathbf{A} = 0,$$

for any vector $\mathbf{A}$.

2.1.2 Vector Component Forms

Previously, we've defined the four (4) vector operations in abstract form, without reference to any particular coordinate system. In practice, it is often easier to set up **Cartesian coordinates** (x, y, z) and work with vector **components**.

Let $\hat{x}$, $\hat{y}$, $\hat{z}$ be unit vectors parallel to the x , y , and z axes, respectively. An arbitrary vector $\mathbf{A}$ can be expanded in terms of these **basis vectors**:⁷

$$\mathbf{A} = A_x \hat{x} + A_y \hat{y} + A_z \hat{z}$$

The symbols A_x , A_y , A_z , are **the components** of $\mathbf{A}$. In geometrical terms they are the **projections** of $\mathbf{A}$ along the three (3) coordinate axes (i.e., $A_x = \mathbf{A} \cdot \hat{x}$, $A_y = \mathbf{A} \cdot \hat{y}$, $A_z = \mathbf{A} \cdot \hat{z}$).

We can now reformulate each of the four (4) vector operations as a rule for manipulating components:

$$\begin{aligned} \mathbf{A} + \mathbf{B} &= (A_x \hat{x} + A_y \hat{y} + A_z \hat{z}) + (B_x \hat{x} + B_y \hat{y} + B_z \hat{z}) \\ &= (A_x + B_x) \hat{x} + (A_y + B_y) \hat{y} + (A_z + B_z) \hat{z} \end{aligned}$$

The operation rules are as follows:

- i. To add vectors, add like components.

$$a\mathbf{A} = (aA_x) \hat{x} + (aA_y) \hat{y} + (aA_z) \hat{z}$$

- ii. To multiply by a scalar, multiply each component. As $\hat{x}$, $\hat{y}$, $\hat{z}$ are mutually perpendicular unit vectors, the following properties are valid:

$$\hat{x} \cdot \hat{x} = \hat{y} \cdot \hat{y} = \hat{z} \cdot \hat{z} = 1 \quad \hat{x} \cdot \hat{y} = \hat{x} \cdot \hat{z} = \hat{y} \cdot \hat{z} = 0$$

Accordingly,

$$\mathbf{A} \cdot \mathbf{B} = (A_x \hat{x} + A_y \hat{y} + A_z \hat{z}) \cdot (B_x \hat{x} + B_y \hat{y} + B_z \hat{z})$$

- iii. To calculate the dot product, multiply like components, and add. In particular,

$$\mathbf{A} \cdot \mathbf{A} = A_x[2] + A_y[2] + A_z[2], \quad \text{so} \quad A = \sqrt{A_x[2] + A_y[2] + A_z[2]}$$

Similarly the following relations can be derived:

$$\begin{aligned} \hat{x} \times \hat{x} &= \hat{y} \times \hat{y} = \hat{z} \times \hat{z} = 0, \\ \hat{x} \times \hat{y} &= -\hat{y} \times \hat{x} = \hat{z}, \\ \hat{y} \times \hat{z} &= -\hat{z} \times \hat{y} = \hat{x}, \\ \hat{z} \times \hat{x} &= -\hat{x} \times \hat{z} = \hat{y}. \end{aligned}$$




Figure 2.2

The decomposition of the vector $\mathbf{A}$ into its components.

⁷One of a specific set of building block vectors that serve as the fundamental coordinate system for a vector space. By scaling and combining these vectors, you can create or describe every other vector in that space.

Therefore,

$$\begin{aligned}\mathbf{A} \times \mathbf{B} &= (A_x \hat{x} + A_y \hat{y} + A_z \hat{z}) \times (B_x \hat{x} + B_y \hat{y} + B_z \hat{z}) \\ &= (A_y B_z - A_z B_y) \hat{x} + (A_z B_x - A_x B_z) \hat{y} + (A_x B_y - A_y B_x) \hat{z}.\end{aligned}$$

This expression look unruly but we can tidy it up and write it more neatly as a **determinant**:

$$\mathbf{A} \times \mathbf{B} = \begin{vmatrix} \hat{x} & \hat{y} & \hat{z} \\ A_x & A_y & A_z \\ B_x & B_y & B_z \end{vmatrix}$$

- iv. To calculate the cross product, form the determinant whose first row is $\hat{x}, \hat{y}, \hat{z}$, whose second row is $\mathbf{A}$ (in component form), and whose third row is $\mathbf{B}$.

2.1.3 Triple Products

As the cross product of two (2) vectors is itself a vector, it can be dotted or crossed with a 3rd vector to form a **triple** product.

Scalar Triple Product Evidently,

$$\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = \mathbf{B} \cdot (\mathbf{C} \times \mathbf{A}) = \mathbf{C} \cdot (\mathbf{A} \times \mathbf{B}),$$

for they all correspond to the same value.

The **alphabetical** order is preserved.

Alternatively, the **non-alphabetical** triple products,

$$\mathbf{A} \cdot (\mathbf{C} \times \mathbf{B}) = \mathbf{B} \cdot (\mathbf{A} \times \mathbf{C}) = \mathbf{C} \cdot (\mathbf{B} \times \mathbf{A}),$$

have the **opposite** sign. In component form,

$$\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = \begin{vmatrix} A_x & A_y & A_z \\ B_x & B_y & B_z \\ C_x & C_y & C_z \end{vmatrix}.$$

A final point worth mentioning is the dot and cross can be **interchanged**:

$$\mathbf{A} \cdot (\mathbf{B} \times \mathbf{C}) = (\mathbf{A} \times \mathbf{B}) \cdot \mathbf{C},$$

however, it is important to stress it out, the placement of the parentheses is **critical**:

Cross Product of Two Scalars

2.1 Information

$(\mathbf{A} \cdot \mathbf{B}) \times \mathbf{C}$ is a meaningless expression. We can't make a cross product from a scalar and a vector.

Vector Triple Product The vector triple product can be simplified by the **BAC-CAB** rule:

$$\mathbf{A} \times (\mathbf{B} \times \mathbf{C}) = \mathbf{B}(\mathbf{A} \cdot \mathbf{C}) - \mathbf{C}(\mathbf{A} \cdot \mathbf{B}).$$

Please observe that the following triple product

$$(\mathbf{A} \times \mathbf{B}) \times \mathbf{C} = -\mathbf{C} \times (\mathbf{A} \times \mathbf{B}) = -\mathbf{A}(\mathbf{B} \cdot \mathbf{C}) + \mathbf{B}(\mathbf{A} \cdot \mathbf{C})$$

is an entirely different vector.⁸ All *higher* vector products can be similarly reduced, often by repeated application, so it is never necessary for an expression to contain more than one cross product in any term. For instance,

$$\begin{aligned} (\mathbf{A} \times \mathbf{B}) \cdot (\mathbf{C} \times \mathbf{D}) &= (\mathbf{A} \cdot \mathbf{C})(\mathbf{B} \cdot \mathbf{D}) - (\mathbf{A} \cdot \mathbf{D})(\mathbf{B} \cdot \mathbf{C}), \\ \mathbf{A} \times [\mathbf{B} \times (\mathbf{C} \times \mathbf{D})] &= \mathbf{B}[\mathbf{A} \cdot (\mathbf{C} \times \mathbf{D})] - (\mathbf{A} \cdot \mathbf{B})(\mathbf{C} \times \mathbf{D}). \end{aligned}$$

⁸To reiterate cross-products are not associative.

2.1.4 Position, Displacement, and Separation Vectors

The location of a point in three dimensions can be described by listing its Cartesian coordinates (x, y, z) . The vector to that point from the origin ($\mathcal{O}$) is called the **position vector**:

$$\mathbf{r} \equiv x \hat{\mathbf{x}} + y \hat{\mathbf{y}} + z \hat{\mathbf{z}}$$

Throughout **M.Sc Electrodynamics**, $\mathbf{r}$ will be used to measure **distance**. Its magnitude:

$$r = \sqrt{x^2 + y^2 + z^2}$$

is the distance from the origin, and

$$\hat{\mathbf{r}} = \frac{\mathbf{r}}{r} = \frac{(x) \hat{\mathbf{x}} + (y) \hat{\mathbf{y}} + (z) \hat{\mathbf{z}}}{\sqrt{x^2 + y^2 + z^2}}$$

is a unit vector pointing **radially outward**. The **infinitesimal displacement vector**, from (x, y, z) to $(x + dx, y + dy, z + dz)$, is

$$d\mathbf{l} = (dx) \hat{\mathbf{x}} + (dy) \hat{\mathbf{y}} + (dz) \hat{\mathbf{z}}.$$

In electrodynamics, one frequently encounters problems involving two (2) points:

source point ($\mathbf{r}'$), where an electric charge is located, and

field point ($\mathbf{r}$), at which we are calculating the electric or magnetic field.

To make these redundant calculations easier to handle, let's use the following short-hand notation:

$$\{\eta \mathbf{r}\} \equiv \mathbf{r} - \mathbf{r}'$$

Its magnitude is:

$$\{\eta \mathbf{r}\} = |\mathbf{r} - \mathbf{r}'|$$

and a unit vector in the direction from $\mathbf{r}'$ to $\mathbf{r}$ is

$$\{\eta \hat{\mathbf{r}}\} = \frac{\{\eta \mathbf{r}\}}{\{\eta \mathbf{r}\}} = \frac{\mathbf{r} - \mathbf{r}'}{|\mathbf{r} - \mathbf{r}'|}$$

In Cartesian coordinates our new short-notations would be as following:




Figure 2.3

An example of a gradient field. Here the field itself is plotted by using arrows to designate the direction of the gradient. To explain the magnitude of the gradient it is either shown by the length of the arrow or by imposing colour on to the plot, which the latter has been used here.

Extending this plot to our example, we can see that most of the high temperature resides on the edges of the room whereas the centre remains cool.

2.2 Differential Calculus

In mathematics, differential calculus is a subfield of calculus that studies the rates at which quantities change and therefore plays a vital role in understanding electric and magnetic fields interacting and changing with time. This section will give a broad overview. If you require a detailed look, please consult **M.Sc Higher Mathematics I**.

2.2.1 Ordinary Derivatives

Assume a function of just one (1) variable: $f(x)$. Therefore, the question we need to answer is what does the derivative, df/dx , do and convey?

It tells us how rapidly the function $f(x)$ **varies** when we change the argument x by an infinitesimal amount, dx :

$$df = \left(\frac{d}{dx} [f] \right) dx$$

If we increment x by an infinitesimal amount dx , then f changes by an amount df ⁹.

Geometrically, the derivative df/dx is the **slope** of the graph of f versus x .

⁹Here we can think the derivative as the proportionality factor.

2.2.2 Gradient

Assume a function which accepts three (3) variables. As an example, let's take the temperature $T(x, y, z)$ in the lecture room. Start out in one corner, and set up a system of cardinal directions. Then for each point (x, y, z) in the room, T gives the temperature at that spot. We want to generalise the notion of **derivative** to functions like T , which depend **NOT** on one but on three variables.

A derivative tells us **how fast the function varies**, if we move a little distance. But this time the situation is more complicated, because it depends on what **direction** we move:

- Going straight up, the temperature will probably increase fairly rapidly,

■ Moving horizontally, it may not change much at all.

In fact, the question of “How fast does T vary?” can have an infinite number of answers, one for each direction we might choose to explore. Fortunately, the problem is not as bad as it looks. A theorem on partial derivatives states:

$$dT = \left(\frac{\partial T}{\partial x} \right) dx + \left(\frac{\partial T}{\partial y} \right) dy + \left(\frac{\partial T}{\partial z} \right) dz$$

This tells us how T changes when we alter all three (3) variables by the infinitesimal amounts of dx , dy , dz . We can write the aforementioned equation as a dot product:

$$dT = \left(\frac{d}{dT} \right)[x] \hat{x} + \frac{d}{dT}[y] \hat{y} + \frac{d}{dT}[z] \hat{z} \cdot ((dx) \hat{x} + (dy) \hat{y} + (dz) \hat{z}) = (\nabla T) \cdot (d\mathbf{l}),$$

where

$$\nabla T \equiv \frac{d}{dT}[x] \hat{x} + \frac{d}{dT}[y] \hat{y} + \frac{d}{dT}[z] \hat{z}$$

is the **gradient** of T . Note that ∇T is a **vector quantity**, with three (3) components.¹⁰

2.2.3 The Del Operator

The gradient has the formal appearance of a vector, (∇) ,¹¹ **multiplying** a scalar T :

$$\nabla T = \left(\hat{x} \frac{\partial}{\partial x} + \hat{y} \frac{\partial}{\partial y} + \hat{z} \frac{\partial}{\partial z} \right) T$$

The term in parentheses is called **del** operator:

$$\nabla = \hat{x} \frac{\partial}{\partial x} + \hat{y} \frac{\partial}{\partial y} + \hat{z} \frac{\partial}{\partial z}$$

Del is **NOT** a vector, in the usual sense. It doesn't mean much until we provide it with a function to act upon. Furthermore, it does **NOT** “multiply” T . Rather, it is an instruction to **differentiate** what follows. To be precise, then, we say that ∇ is a vector operator which **acts upon** T , not a vector that multiplies T .

With this qualification, though, ∇ mimics the behaviour of an ordinary vector in virtually every way. Almost anything that can be done with other vectors can also be done with ∇ . Now, an ordinary vector **A** can multiply in three (3) ways:

1. By a scalar a : **Aa**;
2. By a vector **B**, via the dot product: **A · B**;
3. By a vector **B** via the cross product: **A × B**.

Correspondingly, there are three ways the operator ∇ can act:

$$\nabla = i \frac{d}{dx} + j \frac{d}{dy} + k \frac{d}{dz},$$

¹¹The History of Nabla

The operator (∇) , was originally introduced by William Rowan Hamilton (1805-1865). Hamilton wrote the operator as a rotated nabla and it was P. G. Tait who established an upside-down delta as the conventional symbol in *An Elementary Treatise on Quaternions* (1867) [1]. Tait was also responsible for establishing the term *nabla*.

David Wilkins suggests Hamilton may have used the nabla as a general purpose symbol or abbreviation for whatever operator he wanted to introduce at any time. In 1837 Hamilton used the nabla, in its modern orientation, as a symbol for any arbitrary function in *Trans. R. Irish Acad. XVII. 236. (OED.)* [2] He used the nabla to signify a permutation operator in “On the Argument of Abel, respecting the Impossibility of expressing a Root of any General Equation above the Fourth Degree, by any finite Combination of Radicals and Rational Functions, (1839).

Hamilton used the rotated nabla (∇), for the vector differential operator in the *Proceedings of the Royal Irish Academy* (1846). Hamilton also used the rotated nabla as the vector differential operator in *On Quaternions; or on a new System of Imaginaries in Algebra*. For more information, please visit [here](#).

¹⁰This is the generalised derivative we have been looking for.




Figure 2.4

Visual description of the divergence operation and their possible outcomes.

1. On a scalar function T : ∇T (the gradient);
2. On a vector function $\mathbf{v}$, via the dot product: $\nabla \cdot \mathbf{v}$ (divergence)
3. On a vector function $\mathbf{v}$, via the cross product: $\nabla \times \mathbf{v}$ (curl).

It is time to examine the other two (2) vector derivatives: divergence and curl.

Divergence From the definition of ∇ we construct the divergence as follows:

$$\begin{aligned}\nabla \cdot \mathbf{v} &= \left(\left(\frac{\partial}{\partial x} \right) \hat{\mathbf{x}} + \left(\frac{\partial}{\partial y} \right) \hat{\mathbf{y}} + \left(\frac{\partial}{\partial z} \right) \hat{\mathbf{z}} \right) \cdot \left((v_x) \hat{\mathbf{x}} + (v_y) \hat{\mathbf{y}} + (v_z) \hat{\mathbf{z}} \right) \\ &= \frac{\partial v_x}{\partial x} + \frac{\partial v_y}{\partial y} + \frac{\partial v_z}{\partial z}.\end{aligned}$$

Observe that the divergence of a vector function $\mathbf{v}$ is itself a **scalar** $\nabla \cdot \mathbf{v}$.

Let's try to visualise this concept. The name divergence is well chosen, for $\nabla \cdot \mathbf{v}$ is a measure of how much $\mathbf{v}$ spreads out¹² from the initial point.

¹²i.e., diverges

For example, a vector function in **Fig. 2.4** has a large (positive) divergence,¹³ two functions in **Fig. 2.4** have zero divergence, and one function has a negative divergence.

¹³if the arrows pointed in, it would be a negative divergence

As an example, imagine standing at the edge of a pond. Sprinkle some dust on the surface.

1. If the material spreads out, then we dropped it at a point of **positive divergence**;
2. If it collects together, we dropped it at a point of **negative divergence**.

Curl From the definition of ∇ we construct the curl:

$$\begin{aligned}\mathbf{v} \times \mathbf{v} &= \begin{vmatrix} \hat{\mathbf{x}} & \hat{\mathbf{y}} & \hat{\mathbf{z}} \\ \frac{\partial}{\partial x} & \frac{\partial}{\partial y} & \frac{\partial}{\partial z} \\ v_x & v_y & v_z \end{vmatrix} \\ &= \hat{\mathbf{x}} \left(\frac{\partial v_z}{\partial y} - \frac{\partial v_y}{\partial z} \right) + \hat{\mathbf{y}} \left(\frac{\partial v_x}{\partial z} - \frac{\partial v_z}{\partial x} \right) + \hat{\mathbf{z}} \left(\frac{\partial v_y}{\partial x} - \frac{\partial v_x}{\partial y} \right).\end{aligned}$$




Figure 2.5
Different behaviours of the
curl operation.

Similar to divergence, the name curl is also well chosen, for $\nabla \times \mathbf{v}$ is a measure of how much $\mathbf{v}$ swirls around the point in question. Therefore all function except the rightmost in **Fig. 2.5** all have zero curl, whereas the functions in **Fig. 2.5** all have a substantial curl sans one, pointing in the $\hat{z}$ direction, as the natural right-hand rule would suggest.

To finish these two (2) important operations, let's again imagine we are standing at the edge of a pond. Float a small flower, if it starts to rotate, then we placed it at a point of nonzero curl. A whirlpool would be a region of large curl.

2.2.4 Product Rules

The calculation of ordinary derivatives is facilitated by a number of rules which are as follows:

$$\begin{aligned}
 \text{Sum Rule} \quad \frac{d}{dx}(f + g) &= \frac{df}{dx} + \frac{dg}{dx} \\
 \text{Constant Multiplication} \quad \frac{d}{dx}(kf) &= k \frac{df}{dx} \\
 \text{Product Rule} \quad \frac{d}{dx}(fg) &= f \frac{dg}{dx} + g \frac{df}{dx} \\
 \text{Quotient Rule} \quad \frac{d}{dx}\left(\frac{f}{g}\right) &= \frac{g \frac{df}{dx} - f \frac{dg}{dx}}{g^2}
 \end{aligned}$$

Similar relations hold for the vector derivatives. Thus,

$$\begin{aligned}
 \nabla(f + g) &= \nabla f + \nabla g, & \nabla(kf) &= k \nabla f, \\
 \nabla \cdot (\mathbf{A} + \mathbf{B}) &= (\nabla \cdot \mathbf{A}) + (\nabla \cdot \mathbf{B}), & \nabla \cdot (k\mathbf{A}) &= k(\nabla \cdot \mathbf{A}), \\
 \nabla \times (\mathbf{A} + \mathbf{B}) &= (\nabla \times \mathbf{A}) + (\nabla \times \mathbf{B}), & \nabla \times (k\mathbf{A}) &= k(\nabla \times \mathbf{A}),
 \end{aligned}$$

The product rules, on the other hand, are not quite so simple. There are two (2) ways to construct a scalar as the product of two functions:

$$\begin{aligned}
 fg &\quad (\text{product of two scalar functions}), \\
 \mathbf{A} \cdot \mathbf{B} &\quad (\text{dot product of two vector functions}),
 \end{aligned}$$

and two ways to make a vector:

$$\begin{aligned}
 f\mathbf{A} &\quad (\text{scalar times vector}), \\
 \mathbf{A} \times \mathbf{B} &\quad (\text{cross product of two vectors}).
 \end{aligned}$$



Accordingly, there are six (6) product rules, which are as follows:

$$\begin{aligned}
 \text{Gradient I} \quad & \nabla(fg) = f\nabla g + g\nabla f \\
 \text{Gradient II} \quad & \nabla(\mathbf{A} \cdot \mathbf{B}) = \mathbf{A} \times (\nabla \times \mathbf{B}) + \mathbf{B} \times (\nabla \times \mathbf{A}) + (\mathbf{A} \cdot \nabla)\mathbf{B} + (\mathbf{B} \cdot \nabla)\mathbf{A} \\
 \text{Divergence I} \quad & \nabla \cdot (f\mathbf{A}) = f(\nabla \cdot \mathbf{A}) + \mathbf{A} \cdot (\nabla f) \\
 \text{Divergence II} \quad & \nabla \cdot (\mathbf{A} \times \mathbf{B}) = \mathbf{B} \cdot (\nabla \times \mathbf{A}) - \mathbf{A} \cdot (\nabla \times \mathbf{B}) \\
 \text{Curl I} \quad & \nabla \times (f\mathbf{A}) = f(\nabla \times \mathbf{A}) - \mathbf{A} \times (\nabla f), \\
 \text{Curl II} \quad & \nabla \times (\mathbf{A} \times \mathbf{B}) = (\mathbf{B} \cdot \nabla)\mathbf{A} - (\mathbf{A} \cdot \nabla)\mathbf{B} + \mathbf{A}(\nabla \cdot \mathbf{B}) - \mathbf{B}(\nabla \cdot \mathbf{A})
 \end{aligned}$$

The proofs for rules come straight from the product rule for ordinary derivatives. As an example:

$$\begin{aligned}
 \nabla \cdot (f\mathbf{A}) &= \frac{\partial}{\partial x}(fA_x) + \frac{\partial}{\partial y}(fA_y) + \frac{\partial}{\partial z}(fA_z) \\
 &= \left(\frac{\partial f}{\partial x}A_x + f\frac{\partial A_x}{\partial x} \right) + \left(\frac{\partial f}{\partial y}A_y + f\frac{\partial A_y}{\partial y} \right) + \left(\frac{\partial f}{\partial z}A_z + f\frac{\partial A_z}{\partial z} \right) \\
 &= (\nabla f) \cdot \mathbf{A} + f(\nabla \cdot \mathbf{A}).
 \end{aligned}$$

It is also possible to formulate three quotient rules:

$$\begin{aligned}
 \nabla \left(\frac{f}{g} \right) &= \frac{g\nabla f - f\nabla g}{g^2}, \\
 \nabla \cdot \left(\frac{\mathbf{A}}{g} \right) &= \frac{g(\nabla \cdot \mathbf{A}) - \mathbf{A} \cdot (\nabla g)}{g^2}, \\
 \nabla \times \left(\frac{\mathbf{A}}{g} \right) &= \frac{g(\nabla \times \mathbf{A}) + \mathbf{A} \times (\nabla g)}{g^2}.
 \end{aligned}$$

However, given these can be obtained quickly from the previously mentioned product rules, there is no point in listing them separately and is left for the reader as exercise.

2.2.5 Second Derivatives

The gradient, the divergence, and the curl are the only first derivatives we can make with $\nabla \cdot \mathbf{v}$ by applying ∇ twice, we can construct five (5) types of 2nd derivatives.

The gradient ∇T is a vector, so we can take the divergence and curl of it:

1. Divergence of gradient: $\nabla \cdot (\nabla T)$.
2. Curl of gradient: $\nabla \times (\nabla T)$.

The divergence $\nabla \cdot \mathbf{v}$ is a scalar, therefore all we can do is take its gradient:

3. Gradient of divergence: $\nabla(\nabla \cdot \mathbf{v})$.

The curl $\nabla \times \mathbf{v}$ is a vector, so we can take its divergence and curl:

4. Divergence of curl: $\nabla \cdot (\nabla \times \mathbf{v})$.

5. Curl of curl: $\nabla \times (\nabla \times \mathbf{v})$.

This exhausts the possible combinations, and in fact **NOT** all of them give anything new. Let's consider them one at a time:

Divergence of a Gradient

$$\begin{aligned}\nabla \cdot (\nabla T) &= \left(\hat{x} \frac{\partial}{\partial x} + \hat{y} \frac{\partial}{\partial y} + \hat{z} \frac{\partial}{\partial z} \right) \cdot \left(\frac{\partial T}{\partial x} \hat{x} + \frac{\partial T}{\partial y} \hat{y} + \frac{\partial T}{\partial z} \hat{z} \right) \\ &= \frac{\partial^2 T}{\partial x^2} + \frac{\partial^2 T}{\partial y^2} + \frac{\partial^2 T}{\partial z^2}.\end{aligned}$$

This object, which we write as $\nabla^2 T$ for short, is called the Laplacian¹⁴ of T , which will be our focus later.

The Laplacian of a scalar T is a scalar value.

Occasionally, we will use the Laplacian of a vector, $\nabla^2 \mathbf{v}$. By this we mean a **vector** quantity whose x-component is the Laplacian of v_x , and so on.

$$\nabla^2 \mathbf{v} \equiv \left(\nabla^2 v_x \right) \hat{x} + \left(\nabla^2 v_y \right) \hat{y} + \left(\nabla^2 v_z \right) \hat{z}$$

This is nothing more than a convenient extension of the meaning of ∇^2 .

Curl of a Gradient

The curl of a gradient is **always** zero:

$$\nabla \times (\nabla T)$$

This is an **important fact**, which will be used repeatedly. Without going into too much detail into the proof, it relies on the following relation:

$$\frac{\partial}{\partial x} \left(\frac{\partial T}{\partial y} \right) = \frac{\partial}{\partial y} \left(\frac{\partial T}{\partial x} \right)$$

Gradient of Divergence

This operation rarely occurs in physical applications, and it has not been given any special name of its own. Notice that $\nabla (\nabla \cdot \mathbf{v})$ is **NOT** the same as the Laplacian of a vector:

$$\nabla^2 = (\nabla \cdot \nabla) \neq \nabla (\nabla \cdot \mathbf{v})$$

Divergence of a Curl

Similar to the curl of a gradient, it is always zero:

$$\nabla \cdot (\nabla \times \mathbf{v}) = 0.$$

¹⁴A differential operator given by the divergence of the gradient of a scalar function on Euclidean space. It is usually denoted by the symbols $\nabla \cdot \nabla$, ∇^2 or Δ . In a Cartesian coordinate system, the Laplacian is given by the sum of second partial derivatives of the function with respect to each independent variable.

The Laplace operator is named after the French mathematician *Pierre-Simon de Laplace* (1749-1827), who first applied the operator to the study of celestial mechanics: the Laplacian of the gravitational potential due to a given mass density distribution is a constant multiple of that density distribution. Solutions of Laplace's equation $\Delta f = 0$ are called harmonic functions and represent the possible gravitational potentials in regions of vacuum.

The Laplacian occurs in many differential equations describing physical phenomena. Poisson's equation describes electric and gravitational potentials; the diffusion equation describes heat and fluid flow; the wave equation describes wave propagation; and the Schrödinger equation describes the wave function in quantum mechanics. In image processing and computer vision, the Laplacian operator has been used for various tasks, such as blob and edge detection.

Curl of a Curl

As we can check from the definition of ∇ :

$$\nabla \times (\nabla \times \mathbf{v}) = \nabla(\nabla \cdot \mathbf{v}) - \nabla^2 \mathbf{v}.$$

So curl-of-curl gives nothing new as the first term is just the divergence of a curl, and the second is the Laplacian. To put it short, then, there are just two kinds of second derivatives:¹⁵

1. Laplacian,
2. Gradient of divergence.

¹⁵It is possible to work out 3rd derivatives, but fortunately second derivatives suffice for practically all physical applications.

2.3 Integral Calculus

Integral calculus is a branch of mathematics focused on integration. It is the inverse of differentiation and is primarily used to calculate the accumulation of quantities, find the area under curves, determine volumes of 3D objects, and solve real-world problems in physics and engineering. As with previous section, this is just an overview. For a detailed look, please consult **M.Sc Higher Mathematics** chapter of the same name.

2.3.1 Line, Surface, and Volume Integrals

In electrodynamics, we encounter several different kinds of integrals, among which the most important are **line** (or **path**) **integrals**, **surface integrals** (or **flux**), and **volume integrals**, which will be the focus of this section.

Line Integrals Has an expression of the form:

$$\int_a^b \mathbf{v} \cdot d\mathbf{l}$$

where $\mathbf{v}$ is a vector function, $d\mathbf{l}$ is the infinitesimal displacement vector, and the integral is to be carried out along a prescribed path $\mathcal{P}$ from point a to point b . If the path forms a closed loop,¹⁶

¹⁶i.e., if $b = a$.

We put a circle on the integral sign:

$$\oint \mathbf{v} \cdot d\mathbf{l}$$

At each point on the path, we take the dot product of $\mathbf{v}$ (evaluated at that point) with the displacement $d\mathbf{l}$ to the next point on the path.

A good example of a line integral is the work done by a force $\mathbf{F}$:

$$W = \int \mathbf{F} \cdot d\mathbf{l}$$




Figure 2.6

The method in which line integral is calculated. At each point the dot product of the vector ($\mathbf{v}$) is taken with the length vector ($d\mathbf{l}$) which is always tangential to the point in which the integration is taken.

Ordinarily, the value of a line integral depends critically on the path taken from $\mathbf{a}$ to $\mathbf{b}$, but there is an important special class of vector functions for which the line integral is independent of path and is determined entirely by the end points.

It will be our business in due course to characterise this special class of vectors.

A force which has this property is called **conservative**.¹⁷

¹⁷A conservative vector field is a vector field that is the gradient of some function [3] and has the property that its line integral is **path independent**.

Surface Integrals A surface integral is an expression of the form:

$$\int_S \mathbf{v} \cdot d\mathbf{a}$$

where $\mathbf{v}$ is a vector function, and the integral is over a specified surface S . Here $d\mathbf{a}$ is an infinitesimal patch of area, with direction **perpendicular to the surface**. There are, two (2) directions perpendicular to any surface, so the **sign** of a surface integral is intrinsically ambiguous.




Figure 2.7: An visual description of the surface integral.

If the surface is closed,¹⁸ we put a circle on the integral sign:

$$\oint \mathbf{v} \cdot d\mathbf{a}$$

¹⁸ imagine it forming a balloon.

Tradition dictates that **outward** is positive, but for open surfaces it's arbitrary.

As an example, if $\mathbf{v}$ describes the flow of a fluid,¹⁹ then $\int \mathbf{v} \cdot d\mathbf{a}$ represents the total mass per unit time passing through the surface.

¹⁹ Measured in mass per unit area per unit time.

Ordinarily, the value of a surface integral depends on the particular surface chosen, but there is a special class of vector functions for which it is **independent** of the surface and is determined entirely by the boundary line. An important task will be to characterise this special class of functions.

Volume Integrals A volume integral is an expression of the form:

$$\int_V T d\tau$$

where T is a scalar function and $d\tau$ is an infinitesimal volume element. In Cartesian coordinates,

$$d\tau = dx dy dz$$

As an example, if T is the density of a substance,²⁰ then the volume integral would give the total mass.

²⁰ This might vary from point to point.

Occasionally we shall encounter volume integrals of vector functions:

$$\int \mathbf{v} d\tau = \int (v_x \hat{x} + v_y \hat{y} + v_z \hat{z}) d\tau = \hat{x} \int v_x d\tau + \hat{y} \int v_y d\tau + \hat{z} \int v_z d\tau.$$

As the unit vectors ($\hat{x}$, $\hat{y}$, $\hat{z}$) are constants, they can be taken outside the integral.

2.3.2 The Fundamental Theorems of Vector Calculus

Assume $f(x)$ is a function of one (1) variable. Based on this, the fundamental theorem of calculus says:




Figure 2.8

To measure the height of a mountain, it doesn't matter what way we take, as long as we know the base and the top, we will know the height.

Calculus Theorem

2.1 Theorem

The **integral** of a **derivative** over some **region** is given by the **value of the function** at the end points (**boundaries**)

$$\int_a^b \left(\frac{d}{dx} f(x) \right) dx = f(x) - f(a) \quad \text{or} \quad \int_a^b F(x) dx = f(x) - f(a)$$

In vector calculus there are three (3) species of derivative²¹ and each has its own “fundamental theorem” with essentially the same format. Our purpose here is to not prove these theorems here, but rather, understand what they **mean**.

²¹These are gradient, divergence, and curl

The Fundamental Theorem for Gradients Suppose we have a scalar function of three (3) variables $T(x, y, z)$. Starting at point **a**, move a small distance $d\mathbf{l}_1$. The function T will change by an amount:

$$dT = (\nabla T) \cdot d\mathbf{l}_1$$

Now let's move an additional small displacement $d\mathbf{l}_2$. The incremental change in T will be now:

$$dT = (\nabla T) \cdot d\mathbf{l}_2$$

In this manner, proceeding by infinitesimal steps, we make the journey to point **b**. At each step we compute the gradient of T , at that point, and dot it into the displacement $d\mathbf{l}$. . . this gives us the change in T .

Gradient Theorem

2.2 Theorem

The total change in T in going from **a** to **b** (along the path selected) is:

$$\int_a^b (\nabla T) \cdot d\mathbf{l} = T(\mathbf{b}) - T(\mathbf{a})$$

Similar to “ordinary” fundamental theorem, this theorem says the integral²² of a derivative, which here the gradient, is given by the value of the function at the boundaries which are **a** and **b** respectively.

²²In this case it is a line integral

As an example, assume we want to measure the height of GrossGlockner. We could climb the mountain from base, or take the high alpine road, or take a helicopter ride all the way up to top. Regardless of the options we take, we should get the same answer either way.²³

²³This is the essence of the fundamental theorem

Line Independence of Gradient

2.3 Theorem

Gradients have the special property that their line integrals are path independent:

- $\int_a^b (\nabla T) \cdot d\mathbf{l}$ is independent of the path taken from **a** to **b**.
- $\oint (\nabla T) \cdot d\mathbf{l} = 0$, since the beginning and end points are identical, and hence $T(\mathbf{b}) - T(\mathbf{a}) = 0$.

The Fundamental Theorem for Divergences

This theorem has at least three (3) special names depending on the literature source:

1. Gauss's theorem,
2. Green's theorem,
3. Divergence theorem.

The fundamental theorem for divergences states:

Divergence Theorem

2.4 Theorem

The **integral** of a **derivative** (the **divergence**) over a **region** (in this case the **volume**, $\mathcal{V}$) is equal to the value of the function at the **boundary** (in this case the **surface** $\mathcal{S}$ bounding the volume).

$$\int_{\mathcal{V}} (\nabla \cdot \mathbf{v}) \, d\tau = \oint_{\mathcal{S}} \mathbf{v} \cdot d\mathbf{a}.$$

The boundary term is itself an integral, more specifically, a surface integral. This is reasonable: the “boundary” of a line is just two end points, but the boundary of a volume is a closed surface. To create an analogy, if $\mathbf{v}$ represents the flow of an incompressible fluid, then the flux $\mathbf{v}$ is the total amount of fluid passing out through the surface, per unit time. Now, the divergence measures the *spreading out* of the vectors from a point, a place of high divergence is like a tap, pouring out liquid. If we have a bunch of tap in a region filled with incompressible fluid, an equal amount of liquid will be forced out through the boundaries of the region. In fact, there are two (2) ways we could determine how much is being produced:

- i. we could count up all the faucets, recording how much each puts out
- ii. we could go around the boundary, measuring the flow at each point, and add it all up

We get the same answer either way:

$$\int (\text{faucets within the volume}) = \oint (\text{flow out through the surface})$$

2.3.3 The Fundamental Theorem for Curls

The fundamental theorem for curls, also known as **Stokes' theorem**, states:²⁴

Stokes' Theorem

2.5 Theorem

Integral of a **derivative** over a **region** ($\mathcal{S}$) is equal to the value of the function at **boundary** ($\mathcal{P}$).

$$\int_{\mathcal{S}} (\nabla \times \mathbf{v}) \cdot d\mathbf{a} = \oint_{\mathcal{P}} \mathbf{v} \cdot d\mathbf{l}.$$

Similar to the divergence theorem, the boundary term is itself an integral. Specifically, a *closed line integral*.

Remember the curl measures the *twist* of the vectors $\mathbf{v}$. Think of a region of high curl as a whirlpool, where if we put a wheel there, it will rotate. Now, the integral of the curl over some surface (or, more precisely, the *flux* of the curl through the surface) represents the *total amount of swirl*, and we can determine that just as well by going around the edge and finding how much the flow is following the boundary.

$\oint \mathbf{v} \cdot d\mathbf{l}$ is sometimes called the **circulation** of $\mathbf{v}$ [4].

There seems to be an ambiguity in *Stokes' theorem* concerning the boundary line integral:

Which way are we supposed to go around?²⁵

The answer is that it doesn't matter which way we go **as long as we are consistent**, for there is an additional sign ambiguity in the surface integral:


Which way does $d\mathbf{a}$ point?

For a closed surface,²⁶ $d\mathbf{a}$ points in the direction of the outward normal. But for an open surface, which way would be defined as out? Consistency in Stokes' theorem is given by the right-hand rule. If our rings point in the direction of the line integral, then our thumb fixes the direction of $d\mathbf{a}$.

Ordinary, a flux integral depends critically on what surface we integrate over, but this is **NOT** the case with curls. For Stokes' theorem says that $\oint (\nabla \times \mathbf{v}) \cdot d\mathbf{a}$ is equal to the line integral of $\mathbf{v}$ around the boundary, and the latter makes no reference to the specific surface we choose.

Proposition I $\oint (\nabla \times \mathbf{v}) \cdot d\mathbf{a}$ depends only on the boundary line, not on the particular surface used.

Proposition II $\oint (\nabla \times \mathbf{v}) \cdot d\mathbf{a} = 0$ for any closed surface.



²⁴ Sir George Gabriel Stokes, 1st Baronet, (1819 - 1903)

was an Irish mathematician and physicist. Born in County Sligo, Ireland, Stokes spent his entire career at the University of Cambridge, where he served as the Lucasian Professor of Mathematics for 54 years, from 1849 until his death in 1903, the longest tenure held by the Lucasian Professor. As a physicist, Stokes made seminal contributions to fluid mechanics, including the Navier-Stokes equations; and to physical optics, with notable works

²⁵ On *televis*ion and *flu*id mechanics. As a mathematician, he popularised "Stokes' theorem" in vector calculus and contributed to the theory of asymptotic expansions. Stokes, along with Felix Hoppe-Seyler, first demonstrated the *oxy*gen transport function of haemoglobin, and showed colour changes produced by the aeration of haemoglobin solutions.




Figure 2.9

The two types of coordinate systems in question. (a) Spherical coordinate system (b) Spherical coordinate system.

2.4 Curvilinear Coordinates

Curvilinear coordinates are a generalized coordinate system in which coordinate lines can be curved. Unlike Cartesian systems that use straight, fixed axes, curvilinear coordinates feature basis vectors that change in direction or magnitude from point to point. Here we will have a look at the two most important ones which have numerous applications in engineering and physics problems.

2.4.1 Spherical Coordinate System

It is possible to label a point P in Cartesian coordinates (x, y, z) , but sometimes it is more convenient to use **spherical** coordinates (r, θ, ϕ) ; r is the distance from the origin, θ is called the **polar angle**, and ϕ is the **azimuthal angle**. Their relation to Cartesian coordinates can be read from **Fig. 2.9a**.

$$x = r \sin \theta \cos \phi, \quad y = r \sin \theta \sin \phi, \quad z = r \cos \theta.$$

Fig. 2.9a also shows three unit vectors, $\hat{r}$, $\hat{\theta}$, $\hat{\phi}$, pointing in the direction of increase of the corresponding coordinates.

They constitute an **orthogonal** basis set;²⁷ similar to $\hat{x}$, $\hat{y}$, $\hat{z}$, and any vector $\mathbf{A}$ can be expressed in terms of them, in the usual way:

$$\mathbf{A} = (A_r) \hat{r} + (A_\theta) \hat{\theta} + (A_\phi) \hat{\phi}$$

Here, A_r , A_θ , A_ϕ are the radial, polar, and azimuthal components of vector $\mathbf{A}$. In terms of the Cartesian unit vectors:

$$\begin{aligned} \hat{r} &= (\sin \theta \cos \phi) \hat{x} + (\sin \theta \sin \phi) \hat{y} + (\cos \theta) \hat{z}, \\ \hat{\theta} &= (\cos \theta \cos \phi) \hat{x} + (\cos \theta \sin \phi) \hat{y} + (-\sin \theta) \hat{z}, \\ \hat{\phi} &= (-\sin \phi) \hat{x} + (\cos \phi) \hat{y} + (0) \hat{z}. \end{aligned}$$

²⁷meaning mutually perpendicular.



An infinitesimal displacement in the $\hat{r}$ direction is simply dr , just as an infinitesimal element of length in the $\hat{x}$ direction is dx :

$$dl_r = dr$$

On the other hand, an infinitesimal element of length in the $\hat{\theta}$ direction is **NOT** just $d\theta$ but rather,

$$dl_\theta = r d\theta$$

Similarly, an infinitesimal element of length in the $\hat{\phi}$ direction is

$$dl_\phi = r \sin \theta d\phi$$

Thus the general infinitesimal displacement $d\mathbf{l}$ is:

$$d\mathbf{l} = (dr) \hat{r} + (r d\theta) \hat{\theta} + (r \sin \theta) \hat{\phi}$$

This plays the role $d\mathbf{l} = (dx) \hat{x} + (dy) \hat{y} + (dz) \hat{z}$ plays in Cartesian coordinates. The infinitesimal volume element $d\tau$, in spherical coordinates, is the product of the three (3) infinitesimal displacements:

$$d\tau = dl_r dl_\theta dl_\phi = r^2 \sin \theta dr d\theta d\phi.$$

It is not possible to give a general expression for **surface** elements $d\mathbf{a}$, since these depend on the orientation of the surface. We simply have to analyse the geometry for any given case, which goes for **Cartesian** and **curvilinear** coordinates.

Integrating over the surface of a sphere, for instance, makes r constant, whereas θ and ϕ change:

$$d\mathbf{a}_1 = dl_\theta dl_\phi \hat{r} = r^2 \sin \theta d\theta d\phi \hat{r}$$

On the other hand, if the surface lies in the xy plane, making θ is constant, while r and ϕ vary:

$$d\mathbf{a}_2 = dl_r dl_\phi \hat{\theta} = r dr d\phi \hat{\theta}$$

Finally: r ranges from 0 to ∞ , ϕ from 0 to 2π , and θ from 0 to π .

2.4.2 Cylindrical Coordinates

The cylindrical coordinates (s, ϕ, z) of a point P are defined in **Fig. 2.9b**. Observe that ϕ has the same meaning as in spherical coordinates, and z is the same as Cartesian; s is the distance to P from the z axis, whereas the spherical coordinate r is the distance from the origin. The relation to Cartesian coordinates is:

$$x = s \cos \phi \quad y = s \sin \phi \quad z = z.$$

The unit vectors are:

$$\begin{aligned} \hat{s} &= \cos \phi \hat{x} + \sin \phi \hat{y} \\ \hat{\phi} &= -\sin \phi \hat{x} + \cos \phi \hat{y} \\ \hat{z} &= \hat{z} \end{aligned}$$

The infinitesimal displacements are

$$dl_s = ds \quad dl_\phi = s d\phi, \quad dl_z = dz$$

which makes:

$$d\mathbf{l} = ds \hat{s} + s d\phi \hat{\phi} + dz \hat{z}.$$

and the volume element is

$$d\tau = s ds d\phi dz$$

The range of s is $(0, \infty)$, ϕ is from 0 to 2π and z is from $-\infty$ to $+\infty$



2.5 Dirac Delta Function

2.5.1 A Mathematical Anomaly

Consider the following vector function:

$$\mathbf{v} = \frac{1}{r^2} \hat{\mathbf{r}}$$

At every location, $\mathbf{v}$ is directed **radially outward** which we can see in **Fig. 2.10**. Let's calculate its divergence:

$$\nabla \cdot \mathbf{v} = \frac{1}{r^2} \frac{\partial}{\partial r} \left(r^2 \frac{1}{r^2} \right) = \frac{1}{r^2} \frac{\partial}{\partial r} (1) = 0$$

This is interesting as this calculation gives us an unforeseen solution. Let's look at it closer. Suppose we integrate over a sphere of radius R , centred at the origin. The surface integral therefore is

$$\oint \mathbf{v} \cdot d\mathbf{a} = \int \left(\frac{1}{R^2} \hat{\mathbf{r}} \right) \cdot (R^2 \sin \theta d\theta d\phi \hat{\mathbf{r}}) = \left(\int_0^\pi \sin \theta d\theta \right) \left(\int_0^{2\pi} d\phi \right) = 4\pi$$

But the volume integral ($\int \nabla \cdot \mathbf{v} d\tau$), should be zero (**0**) if we assume the aforementioned calculation to be true.

Does this mean that the divergence theorem is false?

The source of the problem lies at the point $r = 0$, where **$\mathbf{v}$ blows up**. It is true that $\nabla \cdot \mathbf{v} = 0$ everywhere **except** the origin, but right at the origin is the situation gets a little bit complicated.

Observe, the surface integral is **independent** of R . If the divergence theorem is to be true, we should expect

$$\int \nabla \cdot \mathbf{v} d\tau = 4\pi,$$

for any non-zero vector and the origin.

This means the value of 4π must be coming from the point $r = 0$. Therefore, $\nabla \cdot \mathbf{v}$ has the unique property that it vanishes everywhere except at one point, and yet its **integral** is 4π .




Figure 2.10
The vector plot of the "divergence problem".

No normal function behaves like that.

An Analogy with Density

2.2 Information

To wrap our heads around this property think of **density**.

The density of a point particle is zero except at the exact location of the particle, and yet its **integral** is finite. Namely, the mass of the particle.




Figure 2.11

A visual representation of a 1D Dirac Delta Function. Think of it as a distribution function being squeezed to an infinitely small width.

What we have stumbled upon is called the **Dirac delta function**. It arises in numerous branches of theoretical physics and plays a central role in the theory of electrodynamics.

2.5.2 The 1D Dirac Delta Function

The one-dimensional Dirac delta function ($\delta(x)$), can be pictured as an infinitely high, infinitesimally narrow “spike”, with area 1.

That is to say:

$$\delta(x) = \begin{cases} 0, & \text{if } x \neq 0 \\ \infty, & \text{if } x = 0 \end{cases}$$

and,

$$\int_{-\infty}^{\infty} \delta(x) dx = 1$$

In a strict sense of definition, $\delta(x)$ is **NOT** a function at all, as its value is not finite at $x = 0$. In literature it is known as a generalised function.²⁸

If $f(x)$ is some “ordinary” function, then the product ($f(x)\delta(x)$) is zero everywhere except at $x = 0$. It follows that:

$$f(x)\delta(x) = f(0)\delta(x). \quad (2.1)$$

The product is zero anyway except at $x = 0$. Based on this property, we may as well replace $f(x)$ by the value it assumes at the origin.

Particularly

$$\int_{-\infty}^{\infty} f(x)\delta(x) dx = f(0) \int_{-\infty}^{\infty} \delta(x) dx = f(0). \quad (2.2)$$

²⁸Objects extending the notion of functions on real or complex numbers. There is more than one recognised theory, for example the theory of distributions. Generalised functions are especially useful for treating discontinuous functions more like smooth functions, and describing discrete physical phenomena such as point charges.

Under an integral, then, the delta function “picks out” the value of $f(x)$ at $x = 0$.²⁹ Of course, we can shift the spike from $x = 0$ to some other point, $x = a$:

$$\delta(x - a) = \begin{cases} 0, & \text{if } x \neq a \\ \infty, & \text{if } x = a \end{cases} \quad \text{with} \quad \int_{-\infty}^{\infty} \delta(x - a) dx = 1.$$

which turns Eq. (2.1) into:

$$f(x)\delta(x - a) = f(a)\delta(x - a),$$

and Eq. (2.2) generalises to:

$$\int_{-\infty}^{\infty} f(x)\delta(x - a) dx = f(a).$$

While δ itself is not a proper function, integrals over δ are perfectly acceptable. In fact, it's best to think of the delta function as something that is always intended for use under an integral sign. In particular, two expressions involving delta functions, say $D_1(x)$ and $D_2(x)$, are considered equal if:

$$\int_{-\infty}^{\infty} f(x)D_1(x) dx = \int_{-\infty}^{\infty} f(x)D_2(x) dx,$$

for all **ordinary** functions $f(x)$.

²⁹Here and below, the integral need not run from $-\infty$ to $+\infty$; it is sufficient that the domain extend across the delta function, and $-\epsilon$ to $+\epsilon$ would do as well.

2.5.3 The 3D Dirac Delta Function

Once we have defined the 1D Dirac, it is simple to generalise it to 3D with the following:

$$\delta^3(\mathbf{r}) = \delta(x)\delta(y)\delta(z),$$

As we can see, it is similar to 1D, where 3D Dirac is zero everywhere except at $(0, 0, 0)$, where it blows up. Its volume integral is 1:

$$\int_{\text{all space}} \delta^3(\mathbf{r}) d\tau = \iiint_{-\infty}^{\infty} \delta(x)\delta(y)\delta(z) dx dy dz = 1$$

And, the general form is:

$$\int_{\text{all space}} f(\mathbf{r})\delta^3(\mathbf{r} - \mathbf{a}) d\tau = f(\mathbf{a}).$$

As in the 1D case, integration with δ picks out the value of the function f at the location of the spike.

We can fix the paradox introduced in Section 2.5. Remember, the divergence of $\hat{\mathbf{r}}/r^2$ is zero everywhere except at the origin, however, its integral over any volume containing the origin is a constant.

These are precisely the defining conditions for the Dirac delta function; evidently

$$\nabla \cdot \left(\frac{\hat{\mathbf{r}}}{r^2} \right) = 4\pi\delta^3(\mathbf{r})$$

Or in a more general fashion:

$$\nabla \cdot \left(\frac{\{\eta \hat{\mathbf{r}}\}}{\{\eta \mathbf{r}\}^2} \right) = 4\pi \delta^3(\{\eta \hat{\mathbf{r}}\})$$

Differentiation here is with respect to $\mathbf{r}$, while $\mathbf{r}^f$ is held constant.

2.6 Vector Field Theory

2.6.1 Helmholtz Theorem

Electricity and magnetism are generally expressed as **electric and magnetic fields**, $\mathbf{E}$ and $\mathbf{B}$ and like many physical laws, these are most compactly expressed as **differential equations**.

As $\mathbf{E}$ and $\mathbf{B}$ are **vectors**, the differential equations naturally involve vector derivatives: *divergence* and *curl*. Maxwell reduced the entire theory to four (4) fundamental equations, specifying respectively the divergence and the curl of $\mathbf{E}$ and $\mathbf{B}$.

This formulation raises an interesting question:

To what extent is a vector function determined by its divergence and curl?

To study this case let's assume a vector of $\mathbf{F}$. If the divergence of $\mathbf{F}$ is a specified scalar function D ,

$$\nabla \cdot \mathbf{F} = D,$$

and the curl of $\mathbf{F}$ is a specified vector function $\mathbf{C}$,

$$\nabla \times \mathbf{F} = \mathbf{C},$$

and for consistency, we assume $\mathbf{C}$ to have **NO** divergence,

$$\nabla \cdot \mathbf{C} = 0,$$

Remember, the divergence of a curl is **ALWAYS** zero.

Using this knowledge, is it possible to determine the function $\mathbf{F}$?

Without knowing more information, it is not really possible. There are many functions whose divergence and curl are both zero everywhere.

Some examples are:

$$\mathbf{F} = 0,$$

$$\mathbf{F} = (y) \hat{x} + (zx) \hat{y} + (xy) \hat{z},$$

$$\mathbf{F} = (\sin x \cosh y) \hat{x} + (-\cos x \sinh y) \hat{y} + (\cdot) \hat{z}$$

If we recall **Higher Mathematics I**, to solve a differential equation with a particular solution, we must also be supplied with appropriate **boundary conditions**.

In electrodynamics we typically require the fields go to zero at infinity. With that extra information, the **Helmholtz theorem**³⁰ guarantees the field is uniquely determined by its divergence and curl.



³⁰Hermann Ludwig Ferdinand von Helmholtz (1821 - 1894)

was a German physicist and physician who made significant contributions in several scientific fields, particularly hydrodynamic stability. The Helmholtz Association, the largest German association of research institutions, was named in his honour.

In physics, he is known for his theories on the conservation of energy and on the electrical double layer, work in electrodynamics, chemical thermodynamics, and on a mechanical foundation of thermodynamics. Although credit is shared with Julius von Mayer, James Joule, and Daniel Bernoulli-among others-for the energy conservation principles that eventually led to the first law of thermodynamics, he is credited with the first formulation of the energy conservation principle in its maximally general form.

2.6.2 Potentials

If the curl of a vector field ($\mathbf{F}$) vanishes everywhere, then $\mathbf{F}$ can be written as the **gradient of a scalar potential** (V):

$$\nabla \times \mathbf{F} = 0 \iff \mathbf{F} = -\nabla V$$

The minus sign is purely conventional.

That's the essential idea of the following theorem:

Zero Curl Fields

2.6 Theorem

The following conditions are **equivalent**.

- i. $\nabla \times \mathbf{F} = 0$ everywhere,
- ii. $\int_a^b \mathbf{F} \cdot d\mathbf{l}$ is independent of path, for any given end points,
- iii. $\oint \mathbf{F} \cdot d\mathbf{l} = 0$ for any closed loop,
- iv. $\mathbf{F}$ is the gradient of some scalar function: $\mathbf{F} = -\nabla V$.

The potential is **NOT** unique as any constant can be added to V , since this will not affect its gradient.

If the divergence of a vector field ($\mathbf{F}$) vanishes everywhere, then $\mathbf{F}$ can be expressed as the curl of a **vector potential** ($\mathbf{A}$):

$$\nabla \cdot \mathbf{F} = 0 \iff \mathbf{F} = \nabla \times \mathbf{A}$$

That's the main conclusion of the following theorem:

Zero Divergence Fields

2.7 Theorem

The following conditions are **equivalent**:

- i. $\nabla \cdot \mathbf{F} = 0$ everywhere.
- ii. $\oint \mathbf{F} \cdot d\mathbf{a}$ is independent of surface, for any given boundary line.
- iii. $\oint \mathbf{F} \cdot d\mathbf{a} = 0$ for any closed surface.
- iv. $\mathbf{F}$ is the curl of some vector function: $\mathbf{F} = \nabla \times \mathbf{A}$.

The vector potential is **NOT** unique as the gradient of any scalar function can be added to $\mathbf{A}$ without affecting the curl, given the curl of a gradient is zero.

Incidentally, in all cases, a vector field $\mathbf{F}$ can be written as the gradient of a scalar plus the curl of a vector.

$$\mathbf{F} = -\nabla V + \nabla \times \mathbf{A}$$

References

1. Tait, P. G. *An elementary treatise on quaternions* (CUP Archive, 2018).
2. Hamilton, W. R. On the Argument of Abel. *Transactions of the Royal Irish Academy* **18**, 171–259 (1839).
3. Marsden, J. E. & Tromba, A. *Vector calculus* (Macmillan, 2003).
4. Moffatt, H. K. *A brief introduction to vortex dynamics and turbulence* in *Environmental hazards: the fluid dynamics and geophysics of extreme events* 1–27 (World Scientific, 2011).



Part II

Electric Fields

Part Contents

Chapter 3	Electrostatics	41
-----------	--------------------------	----

Wahrlich es ist nicht das Wissen, sondern das Lernen, nicht das Besitzen sondern das Erwerben, nicht das Da-Seyn, sondern das Hinkommen, was den grössten Genuss gewährt.

It is not knowledge, but the act of learning, not possession but the act of getting there, which grants the greatest enjoyment.

(Carl Friedrich Gauss in Letter to Farkas Bolyai (2 September 1808))

Chapter 3

Electrostatics

Table of Contents

3.1 The Electric Field	41
3.2 Divergence and Curl of Electrostatic Fields	46
3.3 Electric Potential	53
3.4 Work and Energy	61
3.5 Conductors	66

3.1 The Electric Field

In essence, problem of electrodynamics is to solve:

We have some electric charges, $q_1, q_2, q_3, \dots$, let's call them **source charges**. What force do they exert on another charge (i.e., **test charge**), Q ?

The positions of the source charges are given¹ and the trajectory of the test particle is to be calculated. For most realistic cases, both the **source charges** and the **test charge** are in motion.

¹usually as functions of time

The solution to this problem is solved with the **principle of superposition**, which states:

The interaction between any two (**2**) charges is **unaffected** by the presence of others.

This means to determine the force on Q , we can first calculate the force $\vec{F}_1$, caused by q_1 alone, then we calculate the force $\vec{F}_2$, and then q_2 alone and so on.

Finally, we take the vector sum of all these individual forces:

$$\vec{F} = \vec{F}_1 + \vec{F}_2 + \vec{F}_3 + \dots$$

Therefore, if we can find the force on Q caused by a single source charge q , we are, in principle, done.²

It seems easy, right? Why don't we just write down the formula for the force on Q directed **towards** q , and calculate it?

We could, but some technicalities limit us, for not only does the force on Q depend on the separation distance $\{\eta\mathbf{r}\}$ between the charges, but also depends on *both* their velocities and on the *acceleration* of q .

Moreover, it is not the position, velocity, and acceleration of q **right now** that matter:

electromagnetic particles/waves travels at the speed of light, so what concerns Q is the position, velocity, and acceleration q *had* at some earlier time, when the message left.

Therefore, in spite of the fact that the basic question is easy to state³, therefore we shall not answer this with a **direct** answer now but go at it by stages.

To simplify this problem, we assume time to be **irrelevant**, making the special case of **electrostatics** in which all the *source charges are stationary* whereas the test charge may be in motion.

3.1.1 Coulomb's Law

What is the force on a test charge Q due to a single point charge q , that is at *rest* a distance $\{\eta\mathbf{r}\}$ away? The answer is given by Coulomb's law⁴:

$$\vec{F} = \frac{1}{4\pi\epsilon_0} \frac{qQ}{\{\eta\mathbf{r}\}^2} \{\eta\mathbf{r}\}^2 \quad (3.1)$$

The constant ϵ_0 is the **permittivity of free space**. In SI units, where force is in newtons (N) distance in meters (m), and charge in coulombs (C).

$$\epsilon_0 8.85 \times 10^{-12} \text{ C}^2 \cdot \text{N}^{-1} \cdot \text{m}^2$$


In other words,

the force is proportional to the product of the charges and inversely proportional to the square of the separation distance.

Remember, $\{\eta\mathbf{r}\}$ is the separation vector from $\vec{r}$, (the location of q) to $\vec{r}$ (the location of Q):

$$\{\eta\mathbf{r}\} = \vec{r} - \vec{r},$$

$\{\eta\mathbf{r}\}$ is its magnitude, and $\{\eta\hat{\mathbf{r}}\}$ is its direction. The force points **along the line** from q to Q ;



²The principle of superposition may seem "obvious" to us, but it did NOT have to be simple.

Figure 3.1 For the electromagnetic force were proportional to the square of the total source charge, seen a charge with a plus value will generate a repulsive force. the principle of superposition would not hold, as

$(q_1 + q_2)^2 \neq q_1^2 + q_2^2$, as there would be "cross terms" to consider. Superposition is NOT a logical necessity, but an experimental fact.

³Most complicated problem are funny enough relatively easy to state (see Collatz conjecture)



⁴Charles-Augustin de Coulomb (1736 - 1806) was a French officer, engineer, physicist and the discoverer of what is now called Coulomb's law, the description of the electrostatic force of attraction and repulsion. He also did important work on friction, and his work on earth pressure formed the basis for the later development of much of the science of soil mechanics. The SI unit of electric charge, the **coulomb**, was named in his honor in 1880.

- it is repulsive if q and Q have the same sign,
- it is attractive if their signs are opposite

Coulomb's law and the principle of superposition form the physical foundation for electrostatics with the rest, except for some special properties of matter, is **mathematical derivation** of these fundamental rules.

3.1.2 The Electric Field

If we have *several* point charges $q_1, q_2, \dots, q_n$, at distances $\{\eta_r\}_1, \{\eta_r\}_2, \dots, \{\eta_r\}_n$ from Q , the total force on Q is evidently

$$\begin{aligned}\vec{F} &= \vec{F}_1 + \vec{F}_2 + \dots = \frac{1}{4\pi\epsilon_0} \left(\frac{q_1 Q}{\{\eta_r\}_1^2} \{\eta_r\}_1 + \frac{q_2 Q}{\{\eta_r\}_1^2} \{\eta_r\}_2 + \dots \right) \\ &= Q \frac{1}{4\pi\epsilon_0} \left(\frac{q_1}{\{\eta_r\}_1^2} \{\eta_r\}_1 + \frac{q_2}{\{\eta_r\}_2^2} \{\eta_r\}_2 + \dots \right)\end{aligned}$$

or in a more cleaner way:

$$F = Q\vec{E}$$

where

$$\vec{E}(\vec{r}) \equiv \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \frac{q_i}{\{\eta_r\}_i^2} \{\eta_r\}_i \quad (3.2)$$

$\vec{E}$ is called the **electric field** of the source charges. It is important to mention, it is a function of the position $(\vec{r})$, as the separation vectors $\{\eta_r\}_i$ depend on the location of the **field point** P .

But it makes no reference to the test charge Q .

The electric field is a **vector quantity** that varies from point to point and is determined by the configuration of source charges. Physically, $\vec{E}(\vec{r})$ is the force per unit charge that would be exerted on a test charge, if you were to place one at P .

Electric Field at a Distance

3.1 Exercise

Find the $\vec{E}$ field a distance z above the midpoint between two (2) equal charges (q), a distance d apart:

Continues on next page →



← Continued from previous page




Figure 3.2: The diagram for the question “Electric Field at a Distance” (a) The geometrical description (b) Additional annotations added.

Let $\vec{E}_1$ be the field of the left charge, and $\vec{E}_2$ that of the right charge alone. Adding them, the horizontal components cancel and the vertical components add to:

$$E_z = 2 \frac{1}{4\pi\epsilon_0} \frac{q}{\{r\}^2} \cos\theta.$$

Here $\{r\} = \sqrt{z^2 + (d/2)^2}$ and $\cos\theta = z/\{r\}$, therefore:

$$\vec{E} = \frac{1}{4\pi\epsilon_0} \frac{2qz}{[z^2 + (d/2)^2]^{3/2}} \hat{z} \quad \blacksquare$$

3.1.3 Continuous Charge Distributions

Our definition of the electric field Eq. (3.2) assumes the field source is a **collection** of discrete point charges q_i . If, the charge is distributed continuously over some region, the sum becomes an integral:

$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{1}{\{r\}^2} \{r\} \hat{r} dq$$

1. If charge is spread out along a **line**, with charge-per-unit-length λ , then $dq = \lambda dl'$, where dl' is an element of length along the line.
2. If charge is smeared out over a **surface**, with charge-per-unit-area σ , then $dq = \sigma da'$, where da' is an element of area on the surface.
3. If charge fills a **volume** with charge-per-unit-volume ρ , then $dq = \rho d\tau'$, where $d\tau'$ is an element of volume.

These aforementioned volumetric definitions can be rewritten as:



$$dq \rightarrow \lambda dl' \sim \sigma da' \sim \rho d\tau'.$$

Therefore the electric field of a line charge is,

$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\lambda(\vec{r}')}{\{\eta_r\}^2} \{\eta_r\} d\ell',$$

for a surface charge,

$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\sigma(\vec{r}')}{\{\eta_r\}^2} \{\eta_r\} da',$$

and for a volume charge,

$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\vec{r}')}{\{\eta_r\}^2} \{\eta_r\} d\tau'. \quad (3.3)$$

Eq. (3.3) is often referred to as **Coulomb's law**, as it is such a short step from the original shown in Eq. (3.1), and because a volume charge is in a sense the most general and realistic case.



3.2 Divergence and Curl of Electrostatic Fields

As we have seen by now, the integrals involved in computing $\vec{E}$ can be complicated and often laborious, even for reasonably simple charge distributions.

Therefore, rest of electrostatics from this point onwards is devoted to assembling methods for **avoiding these integrals**.

It all begins with the **divergence** and **curl** of $\vec{E}$. We shall calculate the divergence of $\vec{E}$ directly from Eq. (3.3), but first we should develop an intuitive view of $\vec{E}$.

Let's begin with the simplest possible case:

A singular point charge (q), situated at the **origin**:

$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{r}$$

As the equation tells, the field falls off with a factor of $1/r^2$, the vectors get shorter as you go farther away from the origin and **they always point radially outward**. But there is a nicer way to represent this field, and that's to connect up the arrows, to form **field lines**. The magnitude of the field is indicated by the **density** of the field lines:

It's strong near the center where the field lines are close together, and weak farther out, where they are relatively far apart.

In truth, the field-line diagram can be deceptive, as when we draw it on a two-dimensional surface, for the density of lines passing through a circle of radius r is the total number divided by the circumference ($n/2\pi r$), which goes at a rate of $(1/r)$, and not $1/r^2$.

But if were to imagine the model in three dimensions then the density of lines is the total number divided by the area of the sphere ($n/4\pi r^2$), which **does** change with a factor of $1/r^2$.

Such diagrams are also convenient for representing more complicated fields. Field lines begin on positive charges and end on negative ones and they cannot simply terminate in midair, though they may extend out to infinity.

If they were to terminate, the divergence of $\vec{E}$ would not be zero, and that cannot happen in empty space. In addition, field lines can never cross at the intersection,

With all this in mind, it is easy to sketch the field of any simple configuration of point charges.




Figure 3.3

An example of imagining electric field as a collection of lines passing through. Here we can see the flux lines (i.e., the arrows) passing through an object.




Figure 3.4

An example interaction of two charges interacting with one another with their field lines visible. Please observe that the field line spread away from the plus charge and are collected by the minus charge.

In this model, the **flux** of $\vec{E}$ through a surface $\mathcal{S}$,

$$\Phi_E = \int_{\mathcal{S}} \vec{E} \cdot d\vec{a}.$$

is a measure of **the number of field lines** passing through $\mathcal{S}$. It is worth mentioning here that it is only a representation of the field lines,⁵ as the **total** number would be infinite. But **for a given sampling rate** the flux is *proportional* to the number of lines drawn, because the field strength, is proportional to the density of field lines, and therefore $\vec{E} \cdot d\vec{a}$, is proportional to the number of lines passing through the infinitesimal area $d\vec{a}$.

This means the flux through any **closed** surface is a measure of the total mass inside the surface. For the field lines that originate on a positive charge must either pass through the surface or else terminate on a negative charge inside. On the other hand, a charge *outside* the surface will contribute nothing to the total flux, since its field lines pass in one side and out the other.

This is the basic idea behind Gauss' law.

3.2.1 Quantification


In the case of a point charge q at the origin, the flux of $\vec{E}$ through a spherical surface of radius (r) is:

$$\oint \vec{E} \cdot d\vec{a} = \int \frac{1}{4\pi\epsilon_0} \left(\frac{q}{r^2} \hat{r} \right) \cdot (r^2 \sin\theta d\theta d\phi \hat{r}) = \frac{1}{\epsilon_0} q$$

Observe that the radius of the sphere **cancels out**, as the surface area goes **up** as r^2 , the field goes *down* as $1/r^2$, so the product is **constant**. In terms of the field-line picture, this makes sense, given the same number of field lines pass through any sphere centered at the origin, regardless of its size.

In fact, it doesn't have to be a sphere. **Any** closed surface, whatever its shape, would be pierced by the same number of field lines. Evidently the flux through any surface enclosing the charge is q/ϵ_0 .

Let's extend this idea a bit further and assume instead of a single charge at the origin, we have a bunch of charges scattered about.



⁵In the history of physics, a line of force in Michael Faraday's extended sense is synonymous with James Clerk Maxwell's line of induction. According to J.J. Thomson, Faraday usually discusses lines of force as chains of polarized particles in a dielectric, yet sometimes Faraday discusses them as having an existence all their own as in stretching across a vacuum. From the 20th century perspective, lines of force are energy linkages embedded in a 19th-century field theory that led to more mathematically and experimentally sophisticated concepts and theories, including Maxwell's equations and Albert Einstein's theory of relativity.



According to the principle of superposition, the total field is the vector sum of all the individual fields:

$$\vec{E} = \sum_{i=1}^n \vec{E}_i$$

The flux through a surface that encloses them all is:

$$\oint \vec{E} \cdot d\vec{a} = \sum_{i=1}^n \left(\oint \vec{E}_i \cdot d\vec{a} \right) = \sum_{i=1}^n \left(\frac{1}{\epsilon_0} q_i \right)$$

For any closed surface, then,

$$\oint \vec{E} \cdot d\vec{a} = \frac{1}{\epsilon_0} Q_{\text{enc}} \quad (3.4)$$

where Q_{enc} is the total charge enclosed within the surface. This is the quantitative statement of Gauss's law. As it stands, Gauss's law is an *integral* equation, but we can easily turn it into a *differential* one, by applying the divergence theorem:

$$\oint_S \vec{E} \cdot d\vec{a} = \int_V (\nabla \cdot \vec{E}) d\tau$$

Rewriting Q_{enc} in terms of the charge density ρ , we have

$$Q_{\text{enc}} = \int_V \rho d\tau$$

So Gauss's law becomes

$$\int_V (\nabla \cdot \vec{E}) d\tau = \int_V \left(\frac{\rho}{\epsilon_0} \right) d\tau$$

And since this holds for *any* volume, the integrands must be equal:

$$\nabla \cdot \vec{E} = \frac{1}{\epsilon_0} \rho \quad (3.5)$$

Eq. (3.5) carries the same message as Eq. (3.4) as it is **Gauss's law in differential form**. The differential version is idler, but the integral form has the advantage in that it accommodates point, line, and surface charges more naturally.




Figure 3.5: A visual representation of the gauss' law.

3.2.2 Divergence of E

Let's go back, now, and calculate the divergence of $\vec{E}$ directly from Eq. (3.3):



$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int_{\text{all space}} \frac{\{\eta_{\mathbf{r}}\}}{\{\eta_{\mathbf{r}}\}^2} \rho(\mathbf{r}') d\tau'$$

While the interaction is originally defined over the volume occupied by the charge, it is much easier to encompass all the space as $\rho = 0$ outside the volume regardless.

Noting that the $\vec{r}$ -dependence of the aforementioned equation is contained in the following:

$$\{\eta_{\mathbf{r}}\} = \vec{r} - \mathbf{r}', \quad \text{where we have} \quad \nabla \cdot \vec{E} = \frac{1}{4\pi\epsilon_0} \int \nabla \cdot \left(\frac{\{\eta_{\mathbf{r}}\}}{\{\eta_{\mathbf{r}}\}^2} \right) \rho(\mathbf{r}') d\tau'$$

This is precisely the divergence we calculated in the previous chapter regarding the divergence anomaly.

$$\left(\frac{\{\eta_{\mathbf{r}}\}}{\{\eta_{\mathbf{r}}\}^2} \right) = 4\pi\delta^2(\{\eta_{\mathbf{r}}\})$$

Using this relation we can arrive at the following:

$$\nabla \cdot \vec{E} = \frac{1}{4\pi\epsilon_0} \int 4\pi\delta^3(\vec{r} - \mathbf{r}') \rho(\mathbf{r}') d\tau' = \frac{1}{\epsilon_0} \rho(\vec{r})$$

which is Gauss's law in differential form given in Eq. (3.5). To recover the integral form in Eq. (3.4), we run the previous argument **in reverse**, integrate over a volume and apply the divergence theorem:

$$\int_V \nabla \cdot \vec{E} d\tau = \oint_S \vec{E} \cdot d\vec{a} = \frac{1}{\epsilon_0} \int_V \rho d\tau = \frac{1}{\epsilon_0} Q_{\text{enc.}}$$

3.2.3 Applications of Gauss's Law

Let us look at some of the use cases of Gauss's law, in integral form. When the problem allows symmetry, it allows us the **quickest** and **easiest** way of computing electric fields. Let's understand this statement with a series of examples.

A Gaussian Sphere

3.2 Exercise

Find the field outside a uniformly charged solid sphere of radius R and total charge q .

Imagine a spherical surface at radius $r > R$, shown below. This is called a Gaussian surface.

Continues on next page →

← Continued from previous page




Figure 3.6: An imaginary Gaussian sphere.

Gauss's law says that:

$$\oint_S \vec{E} \cdot d\vec{a} = \frac{1}{\epsilon_0} Q_{\text{enc}},$$

For this case it is $Q_{\text{enc}} = q$. At first glance this doesn't seem to get us very far, as the quantity we want (E) is buried inside the surface integral. Luckily, symmetry allows us to extract E from under the integral sign: E certainly points radially outward,⁵ as does da , so we can drop the dot product,

$$\int_S \vec{E} \cdot d\vec{a} = \int_S |\vec{E}| da$$

and the magnitude of E is constant over the Gaussian surface, so it comes outside the integral

$$\int_S |\vec{E}| da = |\vec{E}| \int_S da = |E| 4\pi r^2$$

Therefore:

$$|\vec{E}| 4\pi r^2 = \frac{1}{\epsilon_0} q \quad \text{or} \quad \vec{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{r} \quad \blacksquare$$

Gauss's law is always **true**, however it may **NOT** always be useful. If ρ had not been uniform,⁶ or if we had chosen some other shape for our Gaussian surface, it would still have been true that the flux of $\vec{E}$ is q/ϵ_0 , but $\vec{E}$ would not have pointed in the same direction as $d\vec{a}$, and its magnitude would not have been constant over the surface, and without that we cannot get $|\vec{E}|$ outside of the integral.

Symmetry is crucial to this application of Gauss's law.

There are three (3) kinds of symmetry that work:

Spherical it is a concentric sphere,

Cylindrical it is a coaxial cylinder,

Plane A pillbox which straddles the surface.

While cylindrical and plane symmetries technically require infinitely long cylinders, and planes are assumed to extend to infinity, we shall often use them to get approximate answers for “long” cylinders or “large” planes, at points far from the edges.

Although the direct use of Gauss's law to compute electric fields is limited to cases of spherical, cylindrical, and planar symmetry, we can put together **combinations** of objects possessing such symmetry, even though the arrangement as a whole is not symmetrical. For example, invoking the principle of superposition, we could find the field in the vicinity of two uniformly charged parallel cylinders, or a sphere near an infinite charged plane.




Figure 3.7

3.2.4 Curl of E

It is time to calculate the curl of $\vec{E}$, as we did the divergence. As usual, to derive this behaviour, we shall use the simplest case:

a point charge at the origin.

In this case we write down:

$$\vec{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{r}.$$

To get a feel of the curve of $\vec{E}$, let us calculate the line integral of this field from some point $\vec{a}$ to some other point $\vec{b}$:

$$\int_{\vec{a}}^{\vec{b}} \vec{E} \cdot d\vec{T}$$

As we are working in spherical coordinates, $(dr) \hat{r} + (r d\theta) \hat{\theta} + (r \sin \theta d\phi) \hat{\phi}$, so

$$\vec{E} \cdot d\vec{T} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} dr$$

Therefore

$$\int_{\vec{a}}^{\vec{b}} \vec{E} \cdot d\vec{T} = \frac{1}{4\pi\epsilon_0} \int_a^b \frac{q}{r^2} dr = -\frac{1}{4\pi\epsilon_0} \frac{q}{r} \Big|_{r_a}^{r_b} = \frac{1}{4\pi\epsilon_0} \left(\frac{q}{r_a} - \frac{q}{r_b} \right)$$

where r_a is the distance from the origin to the point $\vec{a}$ (i.e., $r_a = |\vec{a} - \mathcal{O}|$) and r_b is the distance to $\vec{b}$ (i.e., $r_b = |\vec{b} - \mathcal{O}|$). The integral around a closed path is evidently zero (for then $r_a = r_b$):

$$\oint \vec{E} \cdot d\vec{T} = 0 \quad (3.6)$$

And through the use of **Stokes' Theorem** one could arrive its differential form:

$$\nabla \times \vec{E} = 0 \quad (3.7)$$

Now, we proved Eq. (3.6) and Eq. (3.7) only for the field of a single point charge at the origin, but these results make no reference to what is, a perfectly arbitrary choice of coordinates.

They hold no matter where the charge is located. Moreover, if we have many charges, the principle of superposition states that the total field is a vector sum of their individual fields:

$$\vec{E} = \vec{E}_1 + \vec{E}_2 + \dots$$

which means

$$\nabla \times \vec{E} = \nabla \times (\vec{E}_1 + \vec{E}_2 + \dots)$$

Therefore, Eq. (3.6) and Eq. (3.7) hold for any static charge distribution.



3.3 Electric Potential

Now we look at another important concept in electric fields which is generally used as a mathematical concept but has significant use nonetheless.

3.3.1 Defining the Potential

The electric field $\vec{E}$ is a **special kind** of vector function, one whose curl is zero.

For example, $\vec{E} = y \hat{x}$, could **NOT** possibly be an electrostatic field as **NO** set of charges, regardless of their sizes and positions, could ever produce such a field.

We're going to exploit this special property of electric fields to reduce a **vector** problem (finding $\vec{E}$) to a **scalar** problem. We know from the previous chapter that any vector whose curl is zero is equal to the gradient of some scalar. What we are going to do now amounts to a proof in the context of electrostatics.

As $\nabla \times \vec{E} = 0$, the line integral of $\vec{E}$ around any closed loop is zero.⁷ As $\oint \vec{E} \cdot d\vec{l} = 0$, the line integral of $\vec{E}$ from point $\vec{a}$ to point $\vec{b}$ is the same for all paths.

⁷This is a consequence of the Stokes' Theorem.

Because the line integral is independent of path, we can define a function

$$V(\vec{r}) \equiv - \int_{\mathcal{O}}^{\vec{r}} \vec{E} \cdot d\vec{T} \quad (3.8)$$

Here $\mathcal{O}$ is some standard reference point on which we have agreed beforehand. V then depends only on the point $\vec{r}$. We will call this the **electric potential**.

The potential difference between two (2) points $\vec{a}$ and $\vec{b}$ is

$$\begin{aligned} V(\vec{b}) - V(\vec{a}) &= - \int_{\mathcal{O}}^{\vec{b}} \vec{E} \cdot d\vec{T} + \int_{\mathcal{O}}^{\vec{a}} \vec{E} \cdot d\vec{T} \\ &= - \int_{\mathcal{O}}^{\vec{b}} \vec{E} \cdot d\vec{T} - \int_{\vec{a}}^{\mathcal{O}} \vec{E} \cdot d\vec{T} = - \int_{\vec{a}}^{\vec{b}} \vec{E} \cdot d\vec{T}. \end{aligned} \quad (3.9)$$

Now, the fundamental theorem for gradients states the following:

$$V(\mathbf{b}) - V(\mathbf{a}) = \int_a^b (\nabla V) \cdot d\vec{T}, \quad \text{and} \quad \int_a^b (\nabla V) \cdot d\vec{T} = - \int_a^b \vec{E} \cdot d\vec{T}.$$

Since, finally, this is true for any points $\vec{a}$ and $\vec{b}$, the integrands must be equal:

$$\vec{E} = -\nabla V \quad (3.10)$$

Eq. (3.10) is the differential version of Eq. (3.8) which says that the electric field is the gradient of a scalar potential, which is what we set out to prove.

Notice the subtle but crucial role played by path independence⁸ in this argument. If the line integral of $\vec{E}$ depended on the path taken, then the “definition” of V , Eq. (3.8), would **NOT** be useful as it simply would **NOT** define a function, since changing the path would alter the value of $V(\vec{r})$.

⁸or, equivalently, the fact that $\nabla \times \vec{E} = 0$

The minus sign in $\vec{E} = -\nabla V$ is there due to historical conventions.

An Important Distinction

3.1 Information

It is easy to be confused about the term **electrical potential** and a **voltage source** we encounter when we analyse a normal circuit. However there is a significant difference between them.

Electrical potential is the energy per unit charge gained or lost when a charge is moved from some reference point at which the potential is defined to be zero. **Voltage**, on the other hand, is the difference in potential between two (2) arbitrary points at which the potential is **NOT** necessarily zero.

For example, the potential at point **A** relative to a defined reference point⁹ might be 100 V, and the potential at point **B** might be 10 V volts. Then the voltage between **B** and **A** is 90 V volts.

⁹sometimes an infinite distance away

3.3.2 Some Digressions on Potential

Naming

The naming of V as **potential** is unfortunate as it inevitably reminds us of potential *energy*. This is particularly problematic, as there is a connection between **potential** and **potential energy**. Incidentally, a surface over which the potential is constant is called an **equipotential**.

Advantages of the Potential

If we know V , we can easily get $\vec{E}$. It's simple, just take the gradient: $\vec{E} = -\nabla V$. This is due to the three (3) components of $\vec{E}$ not being independent. In fact, they are **explicitly** interrelated by the very condition we started with, $\nabla \times \vec{E} = 0$.

In terms of components,

$$\frac{\partial}{\partial E}[x][y] = \frac{\partial}{\partial E}[y][x], \quad \frac{\partial}{\partial E}[z][y] = \frac{\partial}{\partial E}[y][z], \quad \frac{\partial}{\partial E}[x][z] = \frac{\partial}{\partial E}[z][x].$$

The Reference Point

There is a **necessary** ambiguity in the definition of potential, as the choice of reference point $\mathcal{O}$ was arbitrary. Changing reference points amounts to adding a constant K to the potential:

$$V'(\vec{r}) = - \int_{\mathcal{O}}^{\vec{r}} \vec{E} \cdot d\vec{T} = - \int_{\mathcal{O}'}^{\mathcal{O}} \vec{E} \cdot d\vec{T} - \int_{\mathcal{O}}^{\vec{r}} \vec{E} \cdot d\vec{T} = K + V(\vec{r})$$

where K is the line integral of $\vec{E}$ from the old reference point $\mathcal{O}$ to the new one $\mathcal{O}'$. Of course, adding a constant to V will **NOT** affect the potential **difference** between two (2) points:

$$V'(\mathbf{b}) - V'(\mathbf{a}) = V(\mathbf{b}) - V(\mathbf{a}),$$

since the K 's cancel out.¹⁰ Nor does the ambiguity affect the gradient of V :

$$\nabla V' = \nabla V,$$

since the derivative of a constant is zero (0). That's why all such V 's, differing only in their choice of reference point, correspond to the same field $\vec{E}$.

Potential as such carries no real physical significance, for at any given point we can adjust its value at will by a suitable relocation of $\mathcal{O}$.

¹⁰Actually, it was already clear from Eq. (3.9) that the potential difference is independent of $\mathcal{O}$, as it can be written as the line integral of $\vec{E}$ from $\vec{a}$ to $\vec{b}$, with no reference to $\mathcal{O}$.

However, therefore V 's a "reference level to use for $\mathcal{O}$ in electrostatics—almost-one-like equations to sea level for altitude—and that is a point infinitely far from the charge. Ordinarily, then, we "set the zero of potential at infinity." (Since $V(\mathcal{O}) = 0$, choosing a reference point is equivalent to selecting a place where V is to be zero.) But I must warn you that there is one special circumstance in which this convention fails: when the charge distribution itself extends to infinity. The symptom of trouble, in such cases, is that the potential blows up. For instance, the field of a uniformly charged plane is $(\sigma/2\epsilon_0$

$$V(z) = - \int_{\infty}^z \frac{1}{2\epsilon_0} \sigma dz = - \frac{1}{2\epsilon_0} \sigma (z - \infty).$$

The remedy is simply to choose some other reference point (in this example you might use a point on the plane). Notice that the difficulty occurs only in textbook problems; in "real life" there is no such thing as a charge distribution that goes on forever, and we can always use infinity as our reference point.

Superposition Principle

The original superposition principle pertains to the force on a test charge (Q). It says that the total force on Q is the **vector sum** of the forces attributable to the source charges individually:

$$\vec{F} = \vec{F}_1 + \vec{F}_2 + \vec{F}_3 \dots$$

Dividing through by Q , we see that the electric field, too, obeys the superposition principle:

$$\vec{E} = \vec{E}_1 + \vec{E}_2 + \dots$$

Integrating from the common reference point to $\vec{r}$, it follows that the potential also satisfies such a principle:

$$V = V_1 + V_2 + \dots$$

That is, the potential at any given point is the sum of the potentials due to all the source charges separately. Only this time it is an ordinary sum, not a vector sum, which makes it a lot easier to work with.

Units of Potential

For our system of units, SI, force is measured in newtons (N) and charge in coulombs (C), so electric fields are in newtons per coulomb ($\text{N} \cdot \text{C}^{-1}$).

Accordingly, potential is known-meters per coulomb ($\text{m} \cdot \text{C}^{-1}$), or joules per coulomb ($\text{J} \cdot \text{C}^{-1}$).

A joule per coulomb is a volt.

3.3.3 Poisson's Equation and Laplace's Equation

We now know the electric field ($\vec{E}$) can be written as the **gradient of a scalar potential**:

$$\vec{E} = -\nabla V$$

The question arises:

How are divergence and curl of $\vec{E}$ related to our new definition of electric potential, V ?

$$\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0} \quad \text{and} \quad \nabla \times \vec{E} = 0$$

Well, we can write the aforementioned equations in the following form:

$$\nabla \cdot \vec{E} = \nabla \cdot (-\nabla V) = -\nabla^2 V$$

so, apart from that persistent minus sign, the divergence of $\vec{E}$ is the **Laplacian** of V . Gauss's law, then, says:

$$\nabla^2 V = -\frac{\rho}{\epsilon_0}$$

This is known as **Poisson's equation**. In regions where there is no charge, so $\rho = 0$, Poisson's equation reduces to **Laplace's equation**:

$$\nabla^2 V = 0$$

We'll explore this in Chapter 3 when we work with on **Advanced Mathematical Methods**.

What about the curl? Let's do the math and write the following form:

$$\nabla \times \vec{E} = \nabla \times (-\nabla V) = 0$$

But that's no condition on V as curl of gradient is always zero.

Of course, here, we used curl to show $\vec{E}$ could be expressed as the gradient of a scalar, so it's not really surprising that this works out. It takes only one (1) Partial Differential Equation (PDE) (Poisson's) to determine V , as V is a scalar; for $\vec{E}$ we needed two (2), the divergence and the curl.¹¹

¹¹This comes from Helmholtz theorem, which we discussed previously.

3.3.4 The Potential of a Localised Charge Distribution

Previously, we have defined V in terms of $\vec{E}$ as shown in Eq. (3.8).

Ordinarily, though, it's E that we're looking for.¹² The idea is that it might be easier to get V first, and then calculate $\vec{E}$ by taking the gradient. Typically, then, we know where the charge is,¹³ and we want to find V .

¹²if we already knew $\vec{E}$, there wouldn't be much point in calculating V

¹³that is, we know where the charge density (ρ) is.

Now, Poisson's equation relates V and ρ , but unfortunately it's "the wrong way around":

it would give us ρ , if we knew V , whereas we want V , knowing ρ .

What we need to do is **invert** Poisson's equation. That's the idea for this section, although we shall do it by roundabout means, beginning, as always, with a point charge at the origin.

The electric field is:

$$\vec{E} = \frac{1}{4\pi\epsilon_0} \left(\frac{1}{r^2} \right) \hat{r},$$

so

$$\vec{E} \cdot d\vec{T} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} dr \quad \text{where} \quad d\vec{T} = dr \hat{r} + r d\theta \hat{\theta} + r \sin \theta d\phi \hat{\phi}.$$

Setting the reference point at a place in infinity,¹⁴ the potential of a point charge q at the origin is

$$V(r) = - \int_{\infty}^{\vec{r}} \vec{E} \cdot d\vec{T} = \frac{1}{4\pi\epsilon_0} \int_{\infty}^{\vec{r}} \frac{q}{r'^2} dr' = \frac{1}{4\pi\epsilon_0} \frac{q}{r} \Big|_{\infty}^r = \frac{1}{4\pi\epsilon_0} \frac{q}{r}.$$

¹⁴We will see here the advantage of using infinity for the reference point as it kills the lower limit on the integral.

Please observe the sign of V ; presumably the conventional minus sign in the definition Eq. (3.8) was chosen to make the potential of a positive charge come out positive.

Think Topographically

3.2 Information

It is useful to remember that regions of positive charge are potential "hills", regions of negative charge are potential "valleys", and the electric field points "downhill", from plus toward minus.



In general, the potential of a point charge q is

$$V(\vec{r}) = \frac{1}{4\pi\epsilon_0} \frac{q}{\{r\}},$$

where $\{r\}$, as always, is the distance from q to $\vec{r}$. Invoking the superposition principle, then, the potential of a collection of charges is

$$V(\vec{r}) = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \frac{q_i}{\{r\}_i},$$

or, for a continuous distribution,

$$f_{nr}V[\vec{r}] = \frac{1}{4\pi\epsilon_0} \int \frac{1}{t} dq.$$

In particular, for a volume charge, it's

$$f_{nr}V[\vec{r}] = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\mathbf{r}')}{\{r\}} d\tau'. \quad (3.11)$$

This is the equation we were looking for, telling us how to compute V when we know ρ . It is useful to think of this equation as the “solution” to Poisson’s equation, for a localized charge distribution.

Let’s compare Eq. (3.11) with the corresponding formula for the electric field in terms of ρ Eq. (3.3):

$$\vec{E}(\vec{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\mathbf{r}')}{\{r\}^2} \{\hat{r}\} d\tau'$$

The main point to notice is that the unit vector ($\{\hat{r}\}$) is gone, so there is no need to fuss with components. The potentials of line and surface charges are

$$V = \frac{1}{4\pi\epsilon_0} \int \frac{\lambda(\vec{r}')}{\{r\}} dl' \quad \text{and} \quad V = \frac{1}{4\pi\epsilon_0} \int \frac{\sigma(\vec{r}')}{\{r\}} da' \quad \text{and}$$

It is worth stressing that everything in this section is predicated on the assumption that the reference point is at **infinity**. This is hardly apparent in Eq. (3.11), but remember that we got that equation from the potential of a point charge at the origin, $(1/4\pi\epsilon_0)(q/r)$, which is valid only when $\mathcal{O} = \infty$.

If we try to apply these formulas to one of those artificial problems in which the charge itself extends to infinity, the integral will diverge.

3.3.5 Boundary Conditions

In the typical electrostatic problem we are given a source charge distribution (ρ), and we want to find the electric field ($\vec{E}$) it produces.

Unless the symmetry of the problem allows a solution by Gauss's law, it is generally to our advantage to calculate the potential first, as an intermediate step.

These are the three fundamental quantities of electrostatics:

$$\rho, \vec{E}, \text{ and } V.$$

We have, in the course of our discussion, derived all six (6) formulas interrelating them. These equations are neatly summarized in **Fig. 3.8**. We began with just two (2) experimental observations:

1. The principle of superposition—a broad general rule applying to **all** electromagnetic forces, and
2. Coulomb's law—the fundamental law of electrostatics.

From these, all else are derived. You may have noticed that the electric field always undergoes a discontinuity when you cross a surface charge σ . In fact, it is a simple matter to find the **amount** by which $\vec{E}$ changes at such a boundary. Suppose we draw a wafer-thin Gaussian pillbox, extending just barely over the edge in each direction as seen in **Fig. 3.9**. Gauss's law says that

$$\oint \vec{E} \cdot d\vec{a} = \frac{1}{\epsilon_0} Q_{\text{enc}} = \frac{1}{\epsilon_0} \sigma A,$$

where A is the area of the pillbox lid (m^2).¹⁵ Now, the sides of the pillbox contribute **nothing** to the flux, in the limit as the thickness ϵ goes to zero, so we are left with:

$$E_{\text{above}}^{\perp} - E_{\text{below}}^{\perp} = \frac{1}{\epsilon_0} \sigma,$$

where $E_{\text{above}}^{\perp}$ denotes the component of $\vec{E}$ **perpendicular** to the surface immediately above, and $E_{\text{below}}^{\perp}$ is the same, only just below the surface. For consistency, we let “upward” be the positive direction for both.

Based on this model we can say normal component of $\vec{E}$ (for clarity it is, $\vec{E} \cdot \hat{n}$) is discontinuous by an amount σ/ϵ_0 at any boundary. In particular, where there is **no** surface charge, $E^{\perp}$ is continuous, as for instance at the surface of a uniformly charged solid sphere. The tangential component of $\vec{E}$, by contrast,





Figure 3.8

The relation between three (3) major variables used in the study of electrostatics.



¹⁵If σ varies from point to point or the surface is curved, we need to make sure A to be extremely small.

Figure 3.9

A thought experiment on how to figure out the discrepancy when a boundary is changed.



is always continuous.

For if we apply:

$$\oint \vec{E} \cdot d\vec{T} = 0$$

to the thin rectangular loop of Fig. 2.37, the ends give nothing,¹⁶ and the sides give $(E_{\text{above}}^{\parallel} - E_{\text{below}}^{\parallel})l$,¹⁶ as $\epsilon \rightarrow 0$.
so

$$\vec{E}_{\text{above}}^{\parallel} = \vec{E}_{\text{below}}^{\parallel}$$

where $\vec{E}^{\parallel}$ stands for the components of $\vec{E}$ parallel to the surface. The boundary conditions on E (Eqs. 2.31 and 2.32) can be combined into a single formula:

$$\vec{E}_{\text{above}} - \vec{E}_{\text{below}} = \frac{\sigma}{\epsilon_0} \hat{n}, \quad (3.12)$$

where $\hat{n}$ is a unit vector perpendicular to the surface, pointing from "below" to "above."⁸ The potential, meanwhile, is continuous across any boundary (Fig. 2.38), since $V_{\text{above}} - V_{\text{below}} = -\int_0^b \vec{E} \cdot d\vec{T}$; as the path length shrinks to zero, so too does the integral:

$$V_{\text{above}} = V_{\text{below}}.$$

However, the **gradient** of V inherits the discontinuity in $\vec{E}$ given and following this $\vec{E} = -\nabla V$, which Eq. (3.12) implies that:

$$\nabla V_{\text{above}} - \nabla V_{\text{below}} = -\frac{1}{\epsilon_0} \sigma \hat{n},$$

or, more conveniently,

$$\frac{\partial V_{\text{above}}}{\partial n} - \frac{\partial V_{\text{below}}}{\partial n} = -\frac{1}{\epsilon_0} \sigma, \quad (3.13)$$

where

$$\frac{\partial V}{\partial n} = \nabla V \cdot \hat{n}$$

denotes the **normal derivative** of V .¹⁷ Please note that these boundary conditions relate the fields and potentials just above and **just** below the surface. For example, the derivatives in Eq. (3.13) are the **limiting** values as we approach the surface from either side.¹⁸

¹⁷That is, the rate of change in the direction perpendicular to the surface

¹⁸Observe that it doesn't matter which side you call **above** and which **below**, given the reversal would switch the direction of $\hat{n}$.

Incidentally, if we're only interested in the field due to the essentially flat local patch of surface charge itself, the answer is $(\sigma/2\epsilon_0) \hat{n}$ immediately above the surface, and $-(\sigma/2\epsilon_0) \hat{n}$ immediately below. Evidently the entire discontinuity in $\vec{E}$ is attributable to this local patch of surface charge.



3.4 Work and Energy

3.4.1 To Move a Charge

To understand how to define work, Let us assume that we have a stationary configuration of source charges, and we want to move a test charge (Q) from point $\vec{a}$ to point $\vec{b}$. Here we need to ask the following question:

How much work will we have to do?

At any point along the path, the electric force on Q is $\vec{F} = Q\vec{E}$; the force we must exert, in opposition to this electrical force, is $-Q\vec{E}$. The work we do is therefore:

$$W = \int_0^b \vec{F} \cdot d\vec{T} = -Q \int_0^b \vec{E} \cdot d\vec{T} = Q \left[V(\vec{b}) - V(\vec{a}) \right].$$

Please observe the answer is **independent of the path** we take from $\vec{a}$ to $\vec{b}$;

In mechanics, we call the electrostatic force “conservative”.¹⁹

Dividing through by Q , we have:

$$V(\vec{b}) - V(\vec{a}) = \frac{W}{Q}. \quad (3.14)$$

In other words, the potential difference between points $\vec{a}$ and $\vec{b}$ is equal to the work per unit charge required to carry a particle from $\vec{a}$ to $\vec{b}$. In particular, if we want to bring Q in from far away and stick it at point $\vec{r}$, the work we must do is

$$W = Q \left[V(\vec{r}) - V(\infty) \right],$$

so, if we have set the reference point at infinity,

$$W = QV(r) \quad (3.15)$$

Here, **potential** is potential **energy**, the work it takes to create the system, per unit charge, just as the field is the force per unit charge.

3.4.2 The Energy of a Point Charge Distribution

How much work would it take to assemble an entire **collection** of point charges? Imagine bringing in the charges, one by one, from far away (Fig. 2.40). The first charge, q_1 , takes no work, since there is no field yet to fight against. Now bring in q_2 . According to Eq. (3.15), this will cost you $q_2 V_1(\mathbf{r}_2)$, where V_1 is the potential due to q_1 , and $\mathbf{r}_2$ is the place we're putting q_2 :

$$W = \frac{1}{4\pi\epsilon_0} q_2 \left(\frac{q_1}{q_1^2} \right)$$

¹⁹A force with the property which the total work done by the force in moving a particle between two (2) points is independent of the path taken. Equivalently, if a particle travels in a closed loop, the total work done by a conservative force is zero.



(λ_{12}) is the distance between q_1 and q_2 once they are in position). As you bring in each charge, nail it down in its final location, so it doesn't move when you bring in the next charge. Now bring in q_3 ; this requires work $q_3 V_{1,2}(\mathbf{r}_3)$, where $V_{1,2}$ is the potential due to charges q_1 and q_2 , namely, $(1/4\pi\epsilon_0)(q_1/\lambda_{13} + q_2/\lambda_{23})$. Thus

$$W_3 = \frac{1}{4\pi\epsilon_0} q_3 \left(\frac{q_1}{\lambda_{13}} + \frac{q_2}{\lambda_{23}} \right).$$

Similarly, the extra work to bring in q_4 will be

$$W_4 = \frac{1}{4\pi\epsilon_0} q_4 \left(\frac{q_1}{\lambda_{14}} + \frac{q_2}{\lambda_{24}} + \frac{q_3}{\lambda_{34}} \right).$$

The total work necessary to assemble the first four charges, then, is

$$W = \frac{1}{4\pi\epsilon_0} \left(\frac{q_1 q_2}{\lambda_{12}} + \frac{q_1 q_3}{\lambda_{13}} + \frac{q_1 q_4}{\lambda_{14}} + \frac{q_2 q_3}{\lambda_{23}} + \frac{q_2 q_4}{\lambda_{24}} + \frac{q_3 q_4}{\lambda_{34}} \right).$$

You see the general rule: Take the product of each pair of charges, divide by their separation distance, and add it all up:

$$W = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \sum_{j>i}^n \frac{q_i q_j}{\lambda_{ij}}.$$

The stipulation $j > i$ is to remind you not to count the same pair twice. A nicer way to accomplish this is **intentionally** to count each pair twice, and then divide by 2:

$$W = \frac{1}{8\pi\epsilon_0} \sum_{i=1}^n \sum_{j=i}^n \frac{q_i q_j}{\lambda_{ij}}$$

(we must still avoid $i = j$, of course). Notice that in this form the answer plainly does not depend on the **order** in which you assemble the charges, since every pair occurs in the sum. Finally, let's pull out the factor q_i :

$$W = \frac{1}{2} \sum_{i=1}^n q_i \left(\sum_{j \neq i}^n \frac{1}{4\pi\epsilon_0 \lambda_{ij}} q_j \right).$$

The term in parentheses is the potential at point $\mathbf{r}_i$ (the position of q_i) due to all the **other** charges—all of them, now, not just the ones that were present at some stage during the assembly. Thus,

$$W = \frac{1}{2} \sum_{i=1}^n q_i V(\mathbf{r}_i). \quad (3.16)$$

That's how much work it takes to assemble a configuration of point charges; it's also the amount of work you'd get back if you dismantled the system. In the meantime, it represents energy stored in the configuration ("potential" energy, if you insist, though for obvious reasons I prefer to avoid that word in this context).

3.4.3 The Energy of a Continuous Charge Distribution

For a volume charge density (ρ), Eq. (3.16) becomes:²⁰

$$W = \frac{1}{2} \int \rho V d\tau \quad (3.17)$$

²⁰The corresponding integrals for line and surface charges would be $\int \lambda V d\ell$ and $\int \sigma V da$.

There is a tidy way to rewrite this result, in which ρ and V are eliminated in favor of $\vec{E}$. First use Gauss's law to express ρ in terms of $\vec{E}$:

$$\rho = \epsilon_0 \nabla \cdot \vec{E} \quad \text{so} \quad W = \frac{\epsilon_0}{2} \int (\nabla \cdot \vec{E}) V d\tau$$

Now use integration by parts, to transfer the derivative from $\vec{E}$ to V :

$$W = \frac{\epsilon_0}{2} \left[- \int \vec{E} \cdot (\nabla V) d\tau + \oint V \vec{E} \cdot d\vec{a} \right].$$

But we know $\nabla V = -\vec{E}$, so

$$W = \frac{\epsilon_0}{2} \left(\int_V E^2 d\tau + \oint_S V \vec{E} \cdot d\vec{a} \right) \quad (3.18)$$

But what volume is this we're integrating over? Let's go back to the formula we started with, Eq. (3.17). From its derivation, it is clear that we should integrate over the region where the charge is located. But actually, any larger volume would do just as well:

The "extra" territory we throw in will contribute nothing to the integral, since $\rho = 0$ out there.

With this in mind, we return to Eq. (3.18). What happens here, as we enlarge the volume beyond the minimum necessary to trap all the charge? Well, the integral of E^2 can only increase;²¹ evidently the surface integral must decrease correspondingly to leave the sum intact.²²

²¹the integrand being positive.

It is now worth stressing out that Eq. (3.18) gives us the correct energy W , whatever volume we use;²³ but the contribution from the volume integral goes up, and that of the surface integral goes down, as you take larger and larger volumes.

²²In fact, at large distances from the charge, $\vec{E}$ goes $1/r^2$ and V $1/r$, while the surface area grows like r^2 ; roughly speaking, then, the surface integral goes down like $1/r$.

In particular, why not integrate over all space?

Then the surface integral goes to zero, and we are left with:

$$W = \frac{\epsilon_0}{2} \int E^2 d\tau \quad (3.19)$$

²³as long as it encloses all the charge

3.4.4 Comments on Electrostatic Energy

An Interesting Inconsistency

We can see Eq. (3.19) implies the energy of a stationary charge distribution is always **positive**. On the other hand, Eq. (3.16) which we derived Eq. (3.19), can be either **positive** or **negative**.

For instance, according to Eq. (3.16), the energy of two (2) equal but **opposite** charges a distance $\{r\}$ apart is $-(1/4\pi\epsilon_0)(q^2/\{r\})$.



What's gone wrong? Which equation is correct?

The answer is that **both** are correct, but they speak to slightly different questions. Eq. (3.16) does **NOT** take into account the work necessary to make the point charges in the first place; we **started** with point charges and simply found the work required to bring them together. This is wise strategy, given Eq. (3.19) indicates that the energy of a point charge is in fact **infinite**:

$$W = \frac{\epsilon_0}{2(4\pi\epsilon_0)^2} \int \left(\frac{q^2}{r^4} \right) (r^2 \sin \theta \, dr \, d\theta \, d\phi) = \frac{q^2}{8\pi\epsilon_0} \int_0^\infty \frac{1}{r^2} \, dr = \infty.$$

Eq. (3.19) is more **complete**, in the sense that it tells you the **total** energy stored in a charge configuration, but Eq. (3.16) is more appropriate when we're dealing with point charges, because we prefer to leave out that portion of the total energy that is attributable to the fabrication of the point charges themselves.

In practice, after all, the point charges are given to us ready-made; all we do is move them around. Since we did not put them together, and we cannot take them apart, it is immaterial how much work the process would involve.²⁴

Now, it is a valid question to ask when the inconsistency crept into an apparently watertight derivation. The "flaw" lies between Eq. (3.16) and Eq. (3.17):

In the former, $V(\vec{r}_i)$ represents the potential due to all the **other** charges **but not** q_i , whereas in the latter, $V(\vec{r})$ is the **full** potential. For a **continuous** distribution, there is no distinction, given the amount of charge **right at the point** $\vec{r}$ is vanishingly small, and its contribution to the potential is zero.

In the presence of point charges we should better stick with Eq. (3.16).

²⁴Still, the infinite energy of a point charge is a recurring source of embarrassment for electromagnetic theory, afflicting the quantum version as well as the classical.

The Place where Energy is Stored

Eq. (3.17) and Eq. (3.19) offer two (2) different ways of calculating the same thing.

1. The first is an integral over the charge distribution;
2. The second is an integral over the field.

These can involve completely different regions. For instance, in the case of the spherical shell, the charge is confined to the surface, whereas the electric field is everywhere **outside** this surface.

Where is the energy, then?

Is it stored in the field, as Eq. (3.19) seems to suggest, or is it stored in the charge, as Eq. (3.17) implies? At the present stage this is simply an unanswerable question: I can tell you what the total energy is, and I can provide you with several different ways to compute it, but it is impertinent to worry about where the energy is located. In the context of radiation theory it is useful to regard the

energy as stored in the field, with a density:

$$\frac{\epsilon_0}{2} E^2 = \text{energy per unit volume.}$$

But in electrostatics one could just as well say it is stored in the charge, with a density $\frac{1}{2}\rho V$.

The difference is purely a matter of bookkeeping.

Principle of Superposition

Because electrostatic energy is quadratic in the fields, it does **NOT** obey a superposition principle. The energy of a compound system is **NOT** the sum of the energies of its parts considered separately as there are also “cross terms” to take into account:

$$\begin{aligned} W_{\text{tot}} &= \frac{\epsilon_0}{2} \int E^2 d\tau' = \frac{\epsilon_0}{2} \int (\vec{E}_1 + \vec{E}_2)^2 d\tau' \\ &= \frac{\epsilon_0}{2} \int (E_1^2 + E_2^2 + 2\vec{E}_1 \cdot \vec{E}_2) d\tau \\ &= W_1 + W_2 + \epsilon_0 \int \vec{E}_1 \cdot \vec{E}_2 d\tau. \end{aligned}$$

For example, if you double the charge everywhere, you **quadruple** the total energy.




Figure 3.10

Some may say that superconductors can be considered as “perfect conductors”, however, they exhibit quantum effects such as the Meissner effect and quantization of magnetic flux. In perfect conductors, the interior magnetic field must remain fixed but can have a zero or nonzero value [1]. In real superconductors, all magnetic flux is expelled during the phase transition to superconductivity (the Meissner effect), and the magnetic field is always zero within the bulk of the superconductor [2].

3.5 Conductors

3.5.1 Properties

In an insulator, for example glass or rubber, each electron is on a short leash, as it is attached to a particular atom. In a metallic **conductor**, by contrast, one or more electrons per atom are free to roam.²⁵ A **perfect** conductor would contain an **unlimited** supply of free charges.

In real life there are no such things perfect conductors, but metals come pretty close, for most purposes and therefore we can assume them to be perfect.

²⁵In liquid conductors such as salt water, it is ions that do the moving. However, for now we shall only focus on solid materials.

From this aforementioned definition, the basic electrostatic properties of ideal conductors immediately follow:

i. No Electric Field Inside a Conductor

Let’s have a think about this statement. If there **were** any field, those free charges would **move**, and it wouldn’t be electrostatics any more. To give a more concrete explanation, we better examine what happens when we put a conductor into an external electric field $\vec{E}_0$, seen in **Fig. 3.12**.

Initially, the field will drive any free positive charges to the right, and negative ones to the left.²⁶ When they come to the edge of the material, the charges pile up: plus on the right side, minus on the left. Now, these induced charges produce a field of their own ($\vec{E}_1$), which, as we can see from the figure, is in the **opposite direction** to $\vec{E}_0$.

That’s the crucial point, for it means the field of the induced charges tends to cancel the original field. Charge will continue to flow until this cancellation is complete, and the resultant field inside the conductor is precisely zero.²⁷ The whole process is practically instantaneous.

²⁶In practice, it’s the electrons that do the moving, but when they depart, the right side is left with a net positive charge, so it doesn’t really matter which charges move; the effect is the same.

²⁷Outside the conductor the field is not zero, for here $\vec{E}_0$ and $\vec{E}_1$ do NOT tend to cancel.

ii. Charge Density is Zero inside a Conductor

This follows from Gauss's law:

$$\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0}$$

If $\vec{E}$ is zero, then by extension, so is ρ . There is still charge around, but exactly as much plus as minus, so the **net** charge density in the interior is zero.

iii. Any Net Charge is on the Surface

That's the only place left.

iv. A Conductor is an Equipotential

For if $\vec{a}$ and $\vec{b}$ are any two (2) points within (or at the surface of) a given conductor,

$$V(\vec{b}) - V(\vec{a}) = - \int_a^b \vec{E} \cdot d\vec{T} = 0, \quad \text{therefore} \quad V(\vec{b}) = V(\vec{a}).$$

v. E is Perpendicular to the Surface

Otherwise, charge will immediately flow around the surface until it kills off the tangential component which are shown in **Fig. 3.11**.²⁸

It is an astonishing fact the charge on a conductor flows to the surface. Given their mutual repulsion, the charges naturally **spread out** as much as possible, but for all of them to go to the surface seems like a waste of the interior space. Surely we could do better, from the point of view of making each charge as far as possible from its neighbors, to sprinkle **some** of them throughout the volume. Well, it simply is not so. You do best to put all the charge on the surface, and this is true regardless of the size or shape of the conductor.

The problem can also be phrased in terms of **energy**.

Like any other free dynamical system, the charge on a conductor will seek the configuration that minimizes its potential energy. What property (iii) asserts is that the electrostatic energy of a solid object²⁹ is a minimum when charge is spread over the surface.

For instance, the energy of a sphere is

$$(1/8\pi\epsilon_0)(q^2/R)$$

if the charge is uniformly distributed over the surface, but it is,

$$(3/20\pi\epsilon_0)(q^2/R)$$

if the charge is uniformly distributed throughout the volume

²⁸Perpendicular to the surface, charge cannot flow, of course, since it is confined to the conducting object.




Figure 3.11

A visual representation of treating a non-standard body and the generated electric field. Please observe that all lines flowing from the body is perpendicular.




Figure 3.12

A visual representation of the electric field inside a conductor.

²⁹with specified shape and total charge




Figure 3.13

Charges induced by a point charge in a conductor (a) When a charge approaches a conductor the charges will start to move where opposite charges will move towards the point charge and same charges will move away. While there is an imbalance now, the overall charge of the conductor remains the same (b) When a charge is given inside the cavity, again similar behaviour is to be expected inside the conductor.

3.5.2 Induced Charges

If we were to hold a charge ($+q$) near an **uncharged** conductor seen in **Fig. 3.13a**, the two (2) will attract one another. The reason for this is that $+q$ will pull minus charges ($-q$) over to the near side and repel plus charges to the far side.³⁰ Since the negative induced charge is closer to q , there is a net force of attraction.

When we speak of the field, charge, or potential "inside" a conductor, we should think of the "meat" of the conductor; if there is some hollow **cavity** in the conductor, and within that cavity we put some charge, then the field in the cavity will **NOT** be zero. But in a remarkable way the cavity and its contents are electrically isolated from the outside world by the surrounding conductor, shown in **Fig. 3.13b**.

No external fields penetrate the conductor; they are cancelled at the outer surface by the induced charge there. Similarly, the field due to charges within the cavity is cancelled, for all exterior points, by the induced charge on the inner surface. However, the compensating charge left over on the outer surface of the conductor effectively "communicates" the presence of q to the outside world.

The total charge induced on the cavity wall is equal and opposite to the charge inside, for if we surround the cavity with a Gaussian surface, all points of which are in the conductor (**Fig. 3.13b**), $\oint \vec{E} \cdot d\vec{a} = 0$, and therefore with Gauss's law, the net enclosed charge must be zero (0). But $Q_{\text{enc}} = q + q_{\text{induced}}$, so $q_{\text{induced}} = -q$. Then if the conductor as a whole is electrically neutral, there must be a charge $+q$ on its outer surface.

If a cavity surrounded by conducting material is itself empty of charge, then the field within the cavity is zero. For any field line would have to begin and end on the cavity wall, going from a plus charge to a minus charge, shown in **Fig. 3.14**.




Figure 3.14

Visual description of an electric field inside a cavity. As can be seen all the lines generated by the positive side of the edge is cancelled by the negative side with it absorbs making the inside of the cavity have 0 field.

³⁰Another way to think of it is that the charge moves around in such a way as to kill off the field of q for points inside the conductor, where the total field must be zero.

Letting that field line be part of a closed loop, the rest of which is entirely inside the conductor (where $\vec{E} = 0$), the integral $\oint \vec{E} \cdot d\vec{T}$ is distinctly **positive**, in violation of $\oint \vec{E} \cdot d\vec{T} = 0$. It follows that $\vec{E} = 0$ within an **empty** cavity, and there is in fact **no** charge on the surface of the cavity.³¹

3.5.3 Surface Charge and the Force on a Conductor

Because the field inside a conductor is zero (**0**), boundary condition 2.33 requires the field immediately **outside** is:

$$E = \frac{\sigma}{\epsilon_0} \hat{n}, \quad (3.20)$$

consistent with our earlier conclusion that the field is **normal to the surface**. In terms of potential, Eq. (3.13) gives us:

$$\sigma = -\epsilon_0 \frac{\partial V}{\partial n}$$

These equations enable us to calculate the surface charge on a conductor, if we can determine $\vec{E}$ or V .³² In the presence of an electric field, a surface charge will experience a force; the force per unit area ($\vec{f}$), is $\sigma \vec{E}$.

But there's a problem here:

The electric field is **discontinuous** at a surface charge.

So what are we supposed to use: E_{above} , E_{below} , or something in between? The answer is that we should use the average of the two:

$$\vec{f} = \sigma \vec{E}_{\text{average}} = \frac{1}{2} \sigma (\vec{E}_{\text{above}} + \vec{E}_{\text{below}}).$$

You may ask:, why the average?

The reason is very simple, though the telling makes it sound complicated: Let's focus our attention on a tiny patch of surface surrounding the point in question (Fig. 2.50).³³ The total field consists of two parts—that attributable to the patch itself, and that due to everything else (other regions of the surface, as well as any external sources that may be present): $\vec{E} = \vec{E}_{\text{patch}} + \vec{E}_{\text{other}}$. Now, the patch cannot exert a force on itself, any more than you can lift yourself by standing in a basket and pulling up on the handles. The force on the patch, then, is due exclusively to E_{other} , and this suffers no discontinuity (if we removed the patch, the field in the "hole" would be perfectly smooth). The discontinuity is due entirely to the charge on the patch, which puts out a field ($\sigma/2\epsilon_0$) on either side, pointing away from the surface. Thus,

$$\begin{aligned} \vec{E}_{\text{above}} &= \vec{E}_{\text{other}} + \frac{\sigma}{2\epsilon_0} \hat{n}, \\ \vec{E}_{\text{below}} &= \vec{E}_{\text{other}} - \frac{\sigma}{2\epsilon_0} \hat{n}. \end{aligned} \quad \text{therefore,} \quad \vec{E}_{\text{other}} = \frac{1}{2} (\vec{E}_{\text{above}} + \vec{E}_{\text{below}}) = \vec{E}_{\text{average}}.$$

Averaging is really just a device for removing the contribution of the patch itself. That argument applies to **any** surface charge; in the particular case of a conductor, the field is zero inside and



³¹This is why we are **relatively safe** inside a metal car during a thunderstorm—you may get cooked, if lightning strikes, but we will **NOT** be **electrocuted**. The same principle applies to the placement of sensitive apparatus inside a grounded Faraday cage, to shield out stray electric fields. In practice, the enclosure doesn't even have to be solid conductor—chicken wire will often suffice [3].

³²we shall use them frequently in the next chapter.

³³Make it small enough so it is essentially flat and the surface charge on it is essentially constant.

(σ/ϵ_0) m outside as shown in Eq. (3.20), so the average is $(\sigma/2\epsilon_0) \hat{n}$, and the force per unit area is

$$\vec{f} = \frac{1}{2\epsilon_0} \sigma^2 \hat{n}.$$

This amounts to an outward **electrostatic pressure** on the surface, tending to draw the conductor into the field, regardless of the sign of σ . Expressing the pressure in terms of the field just outside the surface,

$$P = \frac{\epsilon_0}{2} E^2.$$

3.5.4 Capacitors

Suppose we have two (2) conductors, and we put charge $+Q$ on one and $-Q$ on the other as shown in Fig. 3.15. Since V is **constant** over a conductor, we can speak unambiguously of the potential difference between them:

$$V = V_+ - V_- = - \int_-^+ \vec{E} \cdot d\vec{l}.$$

We don't know how the charge distributes itself over the two conductors, and calculating the field would be a nightmare, if their shapes are complicated, but this much we do know:

E is proportional to Q .

For $\vec{E}$ is given by Coulomb's law:

$$\vec{E} = \frac{1}{4\pi\epsilon_0} \int \frac{\rho}{\lambda^2} \hat{r} d\tau, \quad \text{V} \cdot \text{m}^{-1}$$

so if we double ρ , we double $\vec{E}$.³⁴ Since $\vec{E}$ is proportional to Q , so also is $\vec{V}$. The constant of proportionality is called the **capacitance** of the arrangement:

$$C \equiv \frac{Q}{V} \quad [\text{V} \cdot \text{C}^{-1} \text{ or F}] \quad (3.21)$$

Capacitance is a **purely geometrical quantity**, determined by the sizes, shapes, and separation of the two (2) conductors. In SI units, C is measured in farad (F); a farad is a coulomb-per-volt. This turns out to be inconveniently large; more practical units are the microfarad (1×10^{-6} F) and the picofarad (1×10^{-12} F).

Notice V is, by definition, the potential of the **positive** conductor less that of the negative one; likewise, Q is the charge of the **positive** conductor. Accordingly, capacitance is an intrinsically positive quantity.³⁵

Charging a Capacitor




Figure 3.15

A parallel-plate capacitor, as shown in part A, consists of two flat conducting plates. Here one plate is positively charged and the other one is charged negatively. At a distance of d apart, an electric field ($\vec{E}$) is generated between the two (2) plates.

³⁴Doubling Q doubles ρ everywhere, it doesn't shift the charge around.

³⁵We may occasionally hear someone speak of the capacitance of a single conductor. In this case the "second conductor", with the negative charge, is an imaginary spherical shell of infinite radius surrounding the one conductor. It contributes **nothing** to the field, so the capacitance is given by Eq. (3.21), where V is the potential with infinity as the reference point.

To “charge up” a capacitor, so to say, we have to remove electrons from the positive plate and carry them to the negative plate. By doing so, we fight against the electric field, which is pulling them back toward the positive conductor and pushing them away from the negative one.

How much work does it take, then, to charge the capacitor up to a final amount Q ?

Suppose that at some intermediate stage in the process the charge on the positive plate is q , so the potential difference is q/C . According to Eq. (3.14), the work we need do to transport the next piece of charge, dq , is:

$$dW = \left(\frac{q}{C} \right) dq.$$

The total work necessary, then, to go from $q = 0$ to $q = Q$, is

$$W = \int_0^Q \left(\frac{q}{C} \right) dq = \frac{1}{2} \frac{Q^2}{C},$$

or, since $Q = CV$,

$$W = \frac{1}{2} CV^2$$

where V is the final potential of the capacitor.



Part III

Magnetic Fields

Part Contents

The experimental investigation by which Ampère established the law of the mechanical action between electric currents is one of the most brilliant achievements in science.

The whole, theory and experiment, seems as if it had leaped, full grown and full armed, from the brain of the “Newton of electricity”. It is perfect in form, and unassailable in accuracy, and it is summed up in a formula from which all the phenomena may be deduced, and which must always remain the cardinal formula of electro-dynamics.

(James Clerk Maxwell in A Treatise on Electricity and Magnetism (1873) quoted from 3rd edition (1892) Vol. 2, Ch. 3, p. 175.)



Part IV

Electromagnetic Fields

Part Contents

This velocity is so nearly that of light, that it seems we have strong reason to conclude that light itself is an electromagnetic disturbance in the form of waves propagated through the electromagnetic field according to electromagnetic laws

*(James Clerk Maxwell, in A Dynamical Theory of the Electromagnetic Field (1864)
Introduction, p. 466.)*



Part V

Appendix

Part Contents

Acronyms	79
--------------------	----

The end of a melody is not its goal: but nonetheless, had the melody not reached its end it would not have reached its goal either.

A parable.

(Friedrich Nietzsche)

Acronyms

P

PDE Partial Differential Equation
 Partial Differential Equation



The document is designed with no intention of publication and has only been designed for education purposes.

The current maintainer of this work along with the primary lecturer is
D. T. McGuiness, Ph.D. (Daniel.McGuiness@mci.edu).

