

## Monitor and Manage Devices in Customer Organizations




For supported software information, click here.

This article describes how to monitor the Versa Operating System<sup>TM</sup> (VOS<sup>TM</sup>) devices in a customer (tenant) organizations that a Versa Director node is managing. It also describes and how to perform device- and configuration-related operations on the device from the Director node.

# Display All VOS Devices

To display a list of all the VOS devices that a Director node is managing:

- 1. Select the Administration tab in the top menu bar.
- 2. Select Appliances in the left menu bar. The following screenshot shows that the Director node is managing seven VOS devices.




### Display a Tenant's VOS Devices


- 1. Select the Monitor tab in the top menu bar.
- 2. Select a provider and a tenant (organization) in the left menu bar.
- Select the Devices tab. The main pane displays the Controller and VOS devices in the customer organization. The
  Total Appliances field displays the number of VOS devices for the selected tenant. The screenshot below shows
  that the tenant Customer 1 has six VOS devices.

https://docs.versa-networks.com/Management\_and\_Orchestration/Versa\_Director/Monitoring\_with\_Versa\_Director/Monitor\_a... Updated: Thu, 24 Oct 2024 10:47:41 GMT

Copyright © 2024, Versa Networks, Inc.



- 4. To perform an action for a device, select the device by clicking the checkbox to the left of the device name.
- 5. In the Total Appliances horizontal bar, select an action to perform for a device. The action icons shown in the red box become active. The remaining sections in this article describe each of the actions.




#### Add a Device

To add a VOS device, click the Add icon. It is recommended that you use this action only to create the ServiceVNF device. You should create all other devices using the Workflows menu. For more information, see Create Devices and Device Groups.

#### Delete a Device

To delete a VOS device from the Versa Director or to modify a device's configuration, select the VOS device and then click the Delete icon.




To delete the VOS device from the Versa Director, do not click any options and then click Yes.

To modify the VOS device's configuration, click one or more of the following options and then click Yes:

- · Clean Configuration—Clean up the VOS device's configuration.
- Erase Running Configuration—Delete the configuration currently running on the VOS device.
- Reset to Factory Default Configuration and Image—Reset set the configuration and software image currently running on the VOS device to the factory-default configuration and image.
- Erase Running Configuration and Load Device Defaults—Delete the configuration currently running on the VOS device and load a configuration that contains the VOS device default values.


# Open a Shell To Access the CLI

To open a remote console connection through the SD-WAN network, select the VOS device and click the Appliance Shell icon. The console provides access to the CLI, which you can use to view the device's configuration and perform low-level debugging.




### Synchronize the Configuration to the Device

To synchronize the configuration from the Versa Director database to the selected VOS device, select the device and click the Sync to Appliance and then click Yes.



# Synchronize the Configuration from a Device

To synchronize the configuration from a VOS device to the Versa Director database, select the device and click the Sync from Appliance icon and then click Yes.



# Compare Configuration with the Device

To compare a VOS device's configuration in the Versa Director database with the configuration present on the VOS

device, select the device and click the Compare Configuration with Appliance icon. The Compare Configuration Details popup window displays. The following example shows that the configuration in the Versa Director database and on the VOS device are identical.




## Upgrade the Device

To upgrade the software package running on the VOS device, select the device and click the \_\_\_\_ Upgrade Selected Appliances icon. In the Upgrade Appliance popup window, select the software package name and then click OK to upload the software package and upgrade the device. To upload the software package but not upgrade the device, and then click OK, click Upload Only.




# Import the Device Configuration from a File

To import a VOS device's configuration from a configuration file, select the device and click the limport icon. Click Browse, select the configuration file, and then click OK.




### Export the Device Configuration to a File

To export a VOS device's configuration to a file, select the VOS device and click the Export icon. The file is downloaded to the local system.



### Display Devices in Card View


To display the VOS devices in the card view, click the Card icon.




Click the List button to go back to the list view.

### View Details about Devices Connected to WiFi and LTE


- 1. Select the Monitor tab in the top menu bar.
- 2. Select a provider and a customer (organization) in the left menu bar.
- 3. Select the Devices tab. The main pane displays the Controller and VOS devices in the customer organization.




- 4. Select a device on which WiFi or LTE is configured. The CPE Interfaces screen displays.
- 5. Select the Summary tab, and then click LTE and WiFi. This field displays only if the device has an LTE or a WiFi interface.



For WiFi interfaces, the following information displays:



For LTE interfaces, the following information is displayed:



6. Select the interface to view the details of the WiFi and LTE users and parameters.

# **Supported Software Information**

Releases 20.2 and later support all content described in this article.

#### **Additional Information**

Access the CLI on a VOS Device

**Configure Basic Features** 

Configure WiFi

Monitor VOS Devices and Organizations

Monitor VOS Devices in Real Time

Upgrade Software on Headend and Branch