

Conceiving You -- Riverside

Riverside. BPM est. Dark, heavy, pulsing. Fat low mids and a snarl when it hits. Built from the band's general sound; exact rig on the recording not verified.

GP-5 only, P/J bass, no pedalboard.

Module chain

NR -- Gate, always on.

THRE: 25.

Higher gain. 25 controls hum in the quiet gaps.

PRE -- COMP, always on.

Sustain: 55, VOL: 58.

Firmer compression. 55 tightens the heavy riffs.

DST -- Bass OD, on CTL.

Gain: 45, Blend: 58, VOL: 60, Bass: 55, Treble: 42.

Snarl for the heavy parts. Blend 58 is more wet than the other patches.

AMP/CAB -- NAM SnapTone, slot 56: ProgSVT (always on)

- Built from the `SVT CLEAN PUSHED (SVT-CL)` NAM and the Mesa215 IR, combined into one snaptone.
- Real Ampeg SVT-CL on the clean-pushed setting, into the Mesa215 2x15 IR.
- Modern prog: full, slightly pushed, articulate. Pushed SVT into the Mesa 2x15.
- Gain: 50, VOL: 60, Bass: 60, Middle: 55, Treble: 40
- Gain 50: the capture as built.
- Bass 60: more low end.
- Middle 55: a touch more midrange.
- Treble 40: top end pulled back noticeably.
- VOL 60: the level Michael set for this snaptone in the 2026-10-02 VOL audit. Trim here if the patch jumps in level against your others.
- Same in both CTL states. AMP and CAB are off in the `.prst`, so nothing stacks on the capture. The N->S block calls slot 56 directly.

EQ -- Bass EQ 2, always on.

50Hz: +3, 120Hz: +2, 400Hz: -1, 800Hz: +2, 4.5kHz: -1, VOL: 50.

Fat low end, slight mid cut, 800Hz for note bite.

MOD -- off. No modulation.

DLY -- off. No delay.

RVB -- Room, on CTL.

Mix: 12, Decay: 25, Trail: off.

Small room. Adds size without smear.

CTL footswitch

On CTL: DST (Bass OD), RVB (Room).

- **CTL off** -- Quiet and moody sections. SVT at moderate gain, fat and dark, dry. This is the resting state the patch loads into.
- **CTL on** -- Heavy sections. Bass OD adds a snarl, a touch of room opens it up.

Engage CTL for the heavy riffs. Back off for the atmospheric parts.