

Spider-Man: The Animated Series Theme (1994) (Rhythm Guitar)

-- Joe Perry

Main title theme from *Spider-Man: The Animated Series* (Fox Kids, 1994-1998). Driving hard-rock tempo, est. Performed by Joe Perry of Aerosmith. Songwriting credits vary by source: the Saban and Shuki Levy music team is credited, and Perry is credited on some lists. Treat the credit line as approximate.

This is an instrumental hard-rock theme with a heavy riff and a screaming lead melody over it. The patch targets 90s Aerosmith-era Perry: a Marshall pushed to crunch, mid-forward, not modern-scooped.

I haven't verified the exact gear Perry used on this recording. The tone is built from his general 90s rig sound.

Instrument: Stratocaster (HSS). Bridge humbucker for both sounds.

GP-5 only, Stratocaster (HSS), no pedalboard.

AMP: UK 800 (JCM800) + CAB: V30112 IR (User IR 10)

A JCM800 at medium gain is the classic hard-rock crunch. Perry is a Marshall player, and this is the most direct GP-5 route to that sound.

V30112 is the loaded guitar cab with the upper-mid bark a driven Marshall needs. EVM112 is too clean-voiced for this job.

Module chain

NR -- Gate, always on.

THRE: 35.

Tightens the stops in the riff. With gain 55 plus the Boost, the patch hisses without it.

PRE -- Boost (EP Booster), on CTL.

Gain: 50, +3dB: on, Bright: off.

Pushes the 800 into lead saturation and adds level so the melody jumps out over the band. Bright off keeps it from turning fizzy.

DST -- off. The 800 supplies the crunch. A pedal drive would push it past Perry's grittier, looser feel.

AMP -- UK 800, always on.

Gain: 55, PRES: 55, VOL: 60, Bass: 50, Middle: 60, Treble: 58.

Middle 60 is the key setting: 90s hard rock is mid-heavy. Gain 55 on the bridge humbucker gives crunchy chords that still articulate.

CAB -- User IR 10 (V30112), always on.

VOL: 60.

EQ -- Guitar EQ 2, always on.

100Hz: -2, 500Hz: 0, 1kHz: +1, 3kHz: +1, 6kHz: -2, VOL: 50.

Keeps the palm-mutes tight, adds a slight mid-presence lift, and takes the top-end fizz off.

MOD -- off.

DLY -- Analog, on CTL.

Mix: 16, Time: 380ms, F.Back: 22, Trail: on.

A dark, short tail behind the lead melody. It fills the space behind sustained notes without blurring fast runs.

RVB -- Room, always on.

Mix: 12, Decay: 30, Trail: on.

Just enough air to keep the riff from sounding direct-in.

CTL footswitch

On CTL: PRE (Boost), DLY (Analog).

- **CTL off** -- Rhythm. JCM800 crunch for the main riff and the power-chord hits. This is the resting state the patch loads into.
- **CTL on** -- Lead. Boosted 800 plus analog delay. Use it for the theme's lead melody and any bends and screams.

Engage CTL for the melody. Drop back for the riff sections.