

River Down Below -- Riverside

Riverside. BPM est. Epic, dynamic, slow-building. The bass has to be deep and full when the song swells, and gritty when it hits. Built from the band's general sound; exact rig on the recording not verified.

GP-5 only, P/J bass, no pedalboard.

Module chain

NR -- Gate, always on.

THRE: 18.

Moderate gain. 18 is enough for the rests.

PRE -- COMP, always on.

Sustain: 48, VOL: 58.

Steady level for a long dynamic song.

DST -- Bass OD, on CTL.

Gain: 35, Blend: 45, VOL: 60, Bass: 52, Treble: 48.

Grit for the payoff sections.

AMP/CAB -- NAM SnapTone, slot 56: ProgSVT (always on)

- Built from the `SVT CLEAN PUSHED (SVT-CL)` NAM and the Mesa215 IR, combined into one snaptone.
- Real Ampeg SVT-CL on the clean-pushed setting, into the Mesa215 2x15 IR.
- Moody prog build. Pushed SVT gives body with a bit of edge.
- Gain: 47, VOL: 50, Bass: 60, Middle: 55, Treble: 45
- Gain 47: a little under default. This part wants less push than the other ProgSVT patches.
- Bass 60: more low end.
- Middle 55: a touch more midrange.
- Treble 45: top end pulled back a little.
- VOL 50: the default. Trim here if the patch jumps in level against your others.
- Same in both CTL states. AMP and CAB are off in the `.prst`, so nothing stacks on the capture. The N->S block calls slot 56 directly.

EQ -- Bass EQ 1, always on.

33Hz: +2, 150Hz: +2, 600Hz: -1, 2kHz: +2, 8kHz: 0, VOL: 50.

Bass EQ 1 reaches lower. Sub lift at 33Hz, mid dip at 600Hz, some 2kHz for note definition.

MOD -- off. No modulation.

DLY -- off. No delay.

RVB -- Hall, on CTL.

Mix: 18, Decay: 40, Trail: off.

Sized for the swells. Mix 18 stays out of the way of the low end.

CTL footswitch

On CTL: DST (Bass OD), RVB (Hall).

- **CTL off** -- Verses and build-up. ProgSVT at moderate gain, full low end, dry. This is the resting state the patch loads into.
- **CTL on** -- Big sections. Bass OD adds grit and a hall reverb adds size.

Engage CTL for the swells and heavy payoffs. Back off for the quiet build.