

A function  $f: \mathbb{R}^n \rightarrow \mathbb{R}$

"from  $\mathbb{R}^n$  to  $\mathbb{R}$ "

is linear if  $f(x+y) = f(x) + f(y)$   $\forall x, y \in \mathbb{R}^n$

$f(\alpha x) = \alpha f(x)$  for  $\alpha \in \mathbb{R}$   
 $x \in \mathbb{R}^n$

Non example  $f(x, y) = x^2 - y^2$

$$f(1, 0) = 1$$

$$f(1, 0) = 1$$

$$f(2, 0) = 4 \neq 2 = f(1, 0) + f(1, 0)$$

Example  $f(x, y) = 3x - 4y$

$$\begin{aligned} f(\underbrace{x_1, y_1}_{z_1}) + f(\underbrace{x_2, y_2}_{z_2}) &= 3x_1 - 4y_1 + 3x_2 - 4y_2 \\ &= 3(x_1 + x_2) - 4(y_1 + y_2) \\ &= f(z_1 + z_2) \end{aligned}$$

For you:  $f(\alpha z) = \alpha f(z)$

---

E.g.  $a \in \mathbb{R}^n$ , fixed

$$f(x) = a^T x \quad (x \in \mathbb{R}^n)$$

$$f(x+y) = a^T (x+y)$$

$$= a_1(x_1+y_1) + \dots + a_n(x_n+y_n)$$

$$= a_1x_1 + a_1y_1 + \dots + a_nx_n + a_ny_n$$

$$= a^T x + a^T y$$

Similarly  $f(\alpha x) = a^T \alpha x = \alpha a^T x = \alpha f(x)$ .

So inner product against a fixed vector

is linear.

Examples of linear functions:


Given a time series, temps say

$$T = (T_1, \dots, T_n)$$

tell me the temperature at time  $k$ .

$$f(T) = T_k$$

Text has a nice civil engineering example:



Three positions across the beam.



Imagine point loads at  $x_1$ ,  $x_2$ ,  $x_3$ .

Want to measure the deflection (say)  $s$  of the beam at the mid-point  $m$  as a consequence of weights  $w_1$ ,  $w_2$ ,  $w_3$ .

For a bridge:  $w_i$  in metric tons

$$s \quad m \quad m \quad m$$

$$s(w_1, w_2, w_3) = c_1 w_1 + c_2 w_2 + c_3 w_3$$

$$= c^T w \quad c = (c_1, c_2, c_3) \\ w = (w_1, w_2, w_3)$$

What are the units of  $c_i$ ? mm / tone

$w_1$	$w_2$	$w_3$	Measured sag	Predicted sag
1	0	0	0.12	—
0	1	0	0.31	—
0	0	1	0.26	—
0.5	1.1	0.3	0.481	0.479
1.5	0.8	1.2	0.736	0.740

Claim: every linear function  $f: \mathbb{R}^n \rightarrow \mathbb{R}$  can be written

in the form  $f(x) = c^T x$  for some  $c \in \mathbb{R}^n$ .

Why is that? Let  $c_k = f(e_k)$   $e_k = (0, 0, \dots, 0, \underset{\text{slot } k}{\uparrow}, 0, \dots, 0)$

$$x = (x_1, \dots, x_n)$$

$$= x_1 e_1 + x_2 e_2 + \dots + x_n e_n$$

$$\begin{aligned}
 f(x) &= f(x_1 e_1 + x_2 e_2 + \dots + x_n e_n) \\
 &= f(x_1 e_1) + f(x_2 e_2) + \dots + f(x_n e_n) \\
 &= x_1 f(e_1) + x_2 f(e_2) + \dots + f(x_n e_n) \\
 &= c_1 x_1 + \dots + c_n x_n \\
 &= c^T x
 \end{aligned}$$

Suppose  $f$  is linear.

$$\begin{aligned}
 f(0) &= f(0+0) \\
 &= f(0) + f(0)
 \end{aligned}$$

$$\Rightarrow \boxed{f(0) = 0}$$

Your favorite lines

$$\begin{aligned}
 f(x) &= mx + b \\
 &\quad \boxed{b} \\
 \text{not linear unless } b &= 0.
 \end{aligned}$$

If  $f(x) = c_1x_1 + \dots + c_nx_n + b = c^T x + b$

we say  $f$  is affine.

They satisfy a kind of limited superposition:


$f$  is linear:  $f(\alpha x + \beta y) = \alpha f(x) + \beta f(y)$

$f$  is affine  $f(\alpha x + \beta y) = \alpha f(x) + \beta f(y)$

$$f \quad \alpha + \beta = 1$$



## Sensitivities



Insulated rod,  $\xrightarrow{\text{non homogeneous}}$  fixed taps at each end.

I measure the temperature at the fixed position  
(at steady state)

$f(T_1, T_2)$  is temp at  $x$  after waiting  
a while.

What happens if I change the temp at the left by a little bit  $\Delta T_1$ ? I expect a small change in temp at  $x$ , roughly proportional to the change  $\Delta T_1$ .

Ditto for  $T_2$ .

$$f(T_1 + \Delta T_1, T_2 + \Delta T_2) \approx f(T_1, T_2) + c_1 \Delta T_1 + c_2 \Delta T_2$$

The coefficients  $c_1, c_2$  are called sensitivities.

$$L(\Delta T_1, \Delta T_2) = c_1 \Delta T_1 + c_2 \Delta T_2 \quad 3$$

a linear function

$$c^T(\Delta T_1, \Delta T_2)$$

in the perturbations  $\Delta T_1, \Delta T_2$ .

They act as scale factors.

In fact you get these from calculus

$$f(x_1, x_2) = x_1 e^{x_2}$$

$$\nabla f = \begin{bmatrix} \frac{\partial f}{\partial x_1} \\ \frac{\partial f}{\partial x_2} \end{bmatrix} = \begin{bmatrix} e^{x_2} \\ x_1 e^{x_2} \end{bmatrix}$$

How you use it: Work at a point  $x_0 = (3, 0)$

$$f(3, 0) = 3$$

$$\nabla f = \begin{bmatrix} 1 \\ 3 \end{bmatrix}$$

$$\hat{f}(x_1, x_2) = 3 + 1(x_1 - 3) + 3 \cdot (x_2 - 0)$$

$$x = f(x_0) + \nabla f^T (x - x_0)$$

( $\Delta x$ )

$\hat{f}(x) \approx f(x)$  if  $x$  is close to  $x_0$ .

$\hat{f}(x_0) = f(x_0)$ , perfect

$$\hat{f}(3.2, -0.1) = 3 + 1(0.2) + 3(-0.1)$$

$$= 3 + 0.2 - 0.3$$

$$= 2.9$$

(vs 2.895)

Only close to  $(3, 0)$ , though.

$$f(1, -10) = 4.5 \times 10^{-5}$$

$$\begin{aligned}\hat{f}(1, -10) &= 3 + (-2) + 3 \cdot (10 - 0) \\ &= 31\end{aligned}$$

$\hat{f}$  is an affine function. (though frequently called  
the linear approx)