

THE FACEPLATE



- 1 UPDATE pill (new version out)
- 2 Preset menu
- 3 Bypass
- 4 Valve · At Input/Output · Echo Amp
- 5 12AX7 — glows with the drive
- 6 Big Frequency dial
- 7 Filter · Bank A/B · Pre/Post
- 8 Echo · Sync · Dub Send/Held
- 9 LFO Shape menu
- 10 Spring on/off
- 11 L/R output meters
- 12 Live chain readout
- 13 Output –24...+12 dB
- 14 Resize grip, 60–150 %

THE MODULES

- **VALVE** — triode preamp: Drive, Bias (even harmonics), Sag (tube compression), Tone (transformer), Mix. *At Output* moves it to the end of the chain; *Echo Amp* puts it inside the tape machine.
- **FILTER · BIG DIAL** — 11-step, 18 dB/oct passive high-pass + Impedance, Magnetism, Character, Dynamics, Artefacts, Gain.
- **ECHO · TWO TRACK** — Time, Feedback, Input, Output, Hiss, Mix, Wear. Sync swaps Time for a note division.
- **MOD · LFO / ENVELOPE** — Rate, LFO Depth, Env Depth, Sens, Speed: both steer the big dial ± 3 octaves.
- **SPRING TANK** — Spring (amount), Tension (decay), Drive (crash).
- **MASTER** — meters, chain readout, Output.


DIAL POSITIONS (HZ)

Step	1	2	3	4	5	6	7	8	9	10	11
Bank A	70	100	150	220	330	500	750	1.1k	1.8k	3.5k	7.5k
Bank B	50	80	120	170	240	350	520	800	1.3k	2.4k	5.0k

INSTALL

macOS: run `OLIVERB-macOS.pkg` (right-click → Open the first time).
Windows: run `OLIVERB-Windows-Setup.exe` (SmartScreen: More info → Run anyway).
Linux: copy `OLIVERB.vst3` to `~/vst3/`. Then rescan plug-ins — it's under **Deestech**. Installs over v1 and v2.0; 2.1.0 changes only the faceplate.

SIGNAL FLOW



Valve first (default) colours everything after it; **At Output** makes it a master tube stage after the spring. Filter **Pre**: repeats inherit the dial — sweeps drag the tail. **Post**: the filter carves the finished signal, tails included. The Master **chain readout** always shows the current order.

FIRST SOUND IN 60 SECONDS

1. Insert on a drum loop; load preset **Waterhouse Rockers**.
2. Turn valve **Drive** up, watch the 12AX7 glow: thicker, compressed, not louder.
3. Sweep the big **Frequency** dial — hear the corner peak and the clacks.
4. Push **Feedback** past 80 %; the repeats build toward self-oscillation.
5. Tap **Dub Send** to **Held** — the input stops, the loop keeps circling. Dub-out. Tap it back.

THE NUMBERS THAT MATTER Valve drive up to +36 dB, level-compensated; zero drive ≈ 1 % 2nd harmonic. Feedback unity = 80 % (beyond it the machine self-oscillates, safely). Echo time 20–2000 ms, tape-style pitch bend on changes. Mod range ± 3 octaves around the dial. Output is hard-limited — it cannot run away.

THE SIX MOVES

Tube glue	Preset <i>Valve Warmth</i> . Drive 30–50 %, Bias 60 %, Sag 20 %: weight without obvious distortion. Sag up for bloom; <i>At Output</i> to round off the tails.
Dub throw	Feedback + Mix high. Un-mute one hit, tap Dub Send to <i>Held</i> , let it circle and decay.
Ride the dial	Filter <i>Pre</i> , sweep Frequency mid-tail — every repeat bends with you. Add Artefacts for the clack.
Pitch-bend echo	Automate Time: small moves warble, big jumps dive-bomb.
Siren	Feedback past unity, no input. Tune with Time, filter with the dial, crash the spring.
Auto-wah	Env Depth positive, step 4–6, Impedance up. Negative depth ducks instead — an ungate.

RESIZE (14)

Drag the corner: 60–150 % of 980 × 930, sharp at any size.

UPDATE NOTICE (1)

An amber **UPDATE x.y.z** pill: click for notes, Download, or Skip.

IF SOMETHING'S WRONG

Not in the DAW	Rescan; check the VST3 folder; macOS: clear quarantine (manual §2).
Thicker than v1	That's the valve at its default 35 %. Switch it off for the v1 sound.
Tail never dies	Feedback ≥ 80 % — that's the instrument. Pull it down.
Too loud	Open Impedance + hot feedback adds real level: trim filter Gain or Output.