Computer Organization & Design

External Calls

(System Calls)

External Calls

- Functions provided to an executing program by system level software (operating system)
- Most system calls involve I/O
 - Input from user via keyboard
 - Output to console
 - File I/O
 - Other utilities

External Call Codes

- An integer value indicating the type of request
- a7 is the designated register for the external call code in RISC-V

1	print integer	11	print ASCII character
2	print single float	12	read character
4	print string	34	print integer (hex)
5	read integer	35	print integer (binary)
6	read single float	36	print integer (unsigned)
8	read string	57	close a file
9	system break	63	read from a file
10	program exit	64	write to a file
		1024	open a file

 There are additional external calls defined but we seldom use them in programs for this class

External Call Parameters

- Most external calls require that you furnish parameters or arguments
 - If you want to print an integer value, you must provide the value to be printed in register a0
 - If you want to print a string, you must provide the memory address where the string is defined in register a0
 - If you want to print a character, you must provide the ASCII code for that character in register a0
- a0 a6 function as argument registers for external calls (integer, character, string)
- fa0 is used for floating-point values read or printed (when we get there in Chapter 3)

Return Values

- Some external calls return a value to the program
 - E.g. user inputs a number, character or string
- a0 is used for integer and character return values
 - When a character is entered, no carriage return is needed; the character is read as soon as it is typed
 - This is called a "single character read"
- fa0 is used for floating-point return values

Strings as Input

- Strings are written directly to memory at the address specified in the a0 register prior to the external call
 - Length of string is determined by the value in register
 a1 (includes the null character)
 - If a1 = 1, only a null character is written
 - If a1 < 1, nothing is written
 - When the number of characters specified by a1 is reached (a1 minus 1), input automatically terminates
 - A carriage return will terminate the string but the newline character is added to the string value and becomes part of the string
 - The null character is added to the end of the string

External Call Process


- Place the external call code value in a7
- Place required argument values in a0, a1 ...
- Execute ecall instruction
- Copy any return values from a0 or fa0 to other registers
 - Subsequent external calls will overwrite the return registers


Sample Program

```
.data
prompt: .asciz "Enter an integer:\t"
reply: .word 0
    .text
main: lui s0, 0x10010 # memory base address in s0
   ori a7, zero, 4 # external code for print string in a7
   or a0, zero, s0 # load address of string in a0
                   # print string on console
   ecall
   ori a7, zero, 5 # external code for reading an integer
   ecall
                   # read reply - value placed in a0
   sw a0, 20(s0) # store the read number into memory
       ori a7, zero, 10# external call code for ending program
exit:
   ecall
```

Note: control characters (tab, newline) can be included in a string definition.

Output of Program





Prompt:

Entered value stored in memory.

Console Output Formatting

- All aspects of console output must be coded by the assembly language programmer.
 - If you want to separate values on a single line by a space or tab, you have print these values to the console at the appropriate locations
 - If you want to begin output on a new line, then you have to print the new line character to the console.
 - All of these output format characters are part of the ASCII character set and can be printed by defining them as arguments to a system call
 - Shortcut: if you want to tab or go to a new line after printing a string, you can include \t or \n to the end of the string definition

Sample Program with Formatting Ecalls

.data outstr1: .asciz "Good morning!\n"

outstr2: .asciz "Enter an integer:\t"

outstr3: .asciz "The number you entered was "

.text

main: lui s0, 0x10010 # define memory base addr

```
ori a7, zero, 4 # external code print string or a0, zero, s0 # address of outstr1 ecall # print string addi a0, s0, 15# address of outstr2 ecall # print string
```

Sample Program (continued)

```
ori a7, zero, 5
                    # external code read integer
       # read integer
   ecall
  or t0, zero, a0 # copy value to t0
  ori a7, zero, 4 # external code print string
  addi a0, s0, 34 # address of outstr3
                 # print string
   ecall
  ori a7, zero, 1 # external code print integer
                    # copy value to a0
  or a0, zero, t0
       # print value
   ecall
  ori a7, zero, 11 # external code print character
  ori a0, zero, 0x2e # ASCII code for period
                 # print period
   ecall
exit: ori a7, zero, 10 # external code for exit
                 # exit program
   ecall
```

Console Output of Sample Program

Good morning!
Enter an integer: 5
The number you entered was 5.
-- program is finished running (0) --

```
Messages Run I/O

Good morning!
Enter an integer: 5
The number you entered was 5.
-- program is finished running (0) --
```

Simplifying Main Program

- Console I/O requires multiple instructions
- The more I/O the longer an assembly language program will become
- Many of the functions may be identical but with different values
- Using subroutines for I/O is an appropriate way to reduce the size of a main program making it easier to understand and debug
- Subroutines are the next topic

Computer Organization & Design

Subroutines

The assembly language version of procedures, functions and methods

Procedures, Functions, Methods

- All HLLs provide for subdividing work into smaller parts
- Structured programming uses procedures and functions
- Object-oriented programming uses methods and classes
- There is a direct correlation between HLL techniques of subdivision and assembly (machine) language constructs

Subroutines

- Subroutines are the procedures, functions, methods of assembly language
 - Makes complex programs easier to understand
 - Allows reuse of code
 - Allows programmers to focus on a portion of a task
 - Helps reduce the length of main program
- Must adhere to specific programming rules
 - Appropriate register use
 - Global vs local data & how to define at assembly level
 - Storage allocation
 - Returning from the subroutine

Normal Steps in Subroutine Execution

- Place data needed by the subroutine (parameters, arguments) where they can be accessed
- Transfer control to the subroutine
- Allocate storage resources in the subroutine (registers, stack) required by the subroutine
- Execute the subroutine
- Place results data in a place where the calling program can access them
- Return control to the point of origin

Subroutine Register Usage

- In RISC-V, the following registers are used for subroutine calls
 - **a0 ... a7** argument registers to pass data and and for return values from subroutines
 - ra return address register
 - s0 ... s7 callee saved registers must be preserved and restored by callee


Caller & Callee Terminology

- The caller transfers execution to a subroutine
 - We say the subroutine was called
 - The caller is usually the main program but subroutines themselves can call other subroutines
- The callee is the subroutine that is to be executed when called
 - Subroutines will return back to the caller at the point the subroutine was called

Subroutine Instructions

- Jump and link (call the subroutine)
 - Format: jal ra, SubroutineAddress
 - Jumps to address of the subroutine and automatically saves the address of the next instruction to be returned to in register ra
- Jump and link register (return from subroutine)
 - Format: jalr zero, ra, 0
 - Last instruction in the subroutine and is the link back to the calling program


How Subroutine Calls Work



Since the program counter was incremented during the fetch of the jal instruction, it is the value of the PC that is saved into the ra register.

Where Do Subroutines Go?

- At the end of the assembly language program
- After the exit code instructions
- Subroutines are still part of the .text segment



Simple Subroutine Call Program

```
.data
num1: .word 0
   .text
main: lui s0, 0x10010
   jal ra, sub1 # call sub1
   jal ra, sub2 # call sub2
exit: ori a7, zero, 10
   ecall
sub1: sw s0, 0(s0)
                         # store s0
   jalr zero, ra, 0
                # return
sub2: lw s1, 0(s0)
                         # load s1
   jalr zero, ra, 0 # return
```

Global vs. Local Data

- HLL construct that differentiates data accessible from all code segments vs. data accessible only within the code block where it is defined
- Defining the concept of scope at the assembly language level is completely up to the programmer
 - Generally, the use of the stack, thread and global pointer registers can be used to further segment the data segment for local vs. global data
- Multiple data segments can also be defined within programs specifically for data to be accessed within subroutines

Stack

- LIFO (last-in first-out) data structure
- Where is it? In memory more specifically, in high program data space.
- Push place an item on the top of the stack
- Pop take an item off the top of the stack
- Stack grows from higher addresses to lower addresses
- In RISC-V assembler, use stack pointer register (sp)
 - Pushing values requires subtracting from sp
 - Popping values requires adding to sp

Stacks (continued)

- No push or pop assembly language instructions
- Programmer must manipulate the stack in code
- Two methods:
 - Allocating fixed number of locations in stack for data
 - sp is modified first, then data are stored using appropriate offsets
 - Dynamically manipulating stack
 - Data are stored first and sp is modified after each push operation
 - May not provide best performance but used when amount of data to be pushed is indeterminate

Code Example (Fixed Stack)

 First instructions in subroutine allocate and push data onto the stack

```
addi sp, sp, -12 # add immediate
sw s3, 0(sp)
sw s4, 4(sp)
sw s5, 8(sp)
```

- Must know how many items you need to push and data size
 - sp value adjusted in one instruction
 - Pushes done with sw instructions using constant offset values
 - Alignment restriction still applies

Code Example (continued)

 Last instructions in subroutine restore s registers and reset value of sp

```
lw s3, 0(sp)
lw s4, 4(sp)
lw s5, 8(sp)
addi sp, sp, 12
```

- Note the restore (pop) is reverse order of push.
- Only the needed s registers are saved and restored
 - Recall s (save) registers contain data that need to be retained across subroutine calls
 - Standard protocol for s usage

Same Example (Dynamic Allocation)

- To push, store data item, then immediately decrement sp
- To pop, increment sp, then load data item

Push sequence

```
sw s3, 0(sp)
addi sp, sp, -4
sw s4, 0(sp)
addi sp, sp, -4
sw s5, 0(sp)
addi sp, sp, -4
```

Pop sequence

```
addi sp, sp 4
lw s5, 0(sp)
addi sp, sp 4
lw s4, 0(sp)
addi sp, sp 4
lw s3, 0(sp)
```

 Method used when number of items is not known or stack access is done within a loop

Nested Subroutines

- Subroutines that call other subroutines
 - Also includes recursive subroutine calls
- What do we do with only one stack pointer?
- We use additional registers
 - Thread pointer (tp) subroutine base address
 - Register 8 (can also be used as a frame pointer (fp)
 - Global pointer (gp) static data base address
 - Register 3
- Caller and callee take responsibility for saving required data
 - Caller pushes required data onto stack before subroutine call
 - Callee pushes conventional data onto stack

Nested Subroutines (continued)

- Frame pointer contains address for the beginning of data saved by the caller
 - Saved argument registers (a registers)
 - Saved return address (ra register)
 - Saved local data (s and t registers)
- Stack pointer used by callee for s registers
- Global pointer contains base address of any globally declared data used by all subroutines

Example Program

 Defines multiple data segments for global vs. local data

```
# global data segment
     .data
num1:
         .byte 10
     .text
main:
         lui s0, 0x10010
    ial ra, sub1
exit: ori a7, zero, 10
    ecall
     .data 0x10010064
                             # local data for subroutine
num2:
         .byte 20
                   # continuation of text segment
     .text
sub1:
         sw s0, 0(sp)
                             # save global memory base address
    addi sp. sp. -4
                        # decrement stack pointer
    addi s0, s0, 0x64
                        # define local memory base address
         t0, 0(s0) # access local data
    lw
    addi sp, sp 4 # increment stack pointer
    lw s0, 0(sp) # restore global memory base address
    jalr zero, ra, 0 # return from subroutine
```

Computer Organization & Design

Pseudoinstructions

(sometimes called macro instructions)

Caution Required!!

Pseudoinstructions

- Pseudoinstructions are often common variations of machine language instructions
- They are not basic instructions and are not directly executed by the hardware
- Pseudoinstructions are used to extend the instruction set
- Sometimes makes assembly language programming a little easier
- Pseudoinstruction use in RARS requires changing the setting to allow them
- Be careful to follow syntax rules for basic instructions

Pseudoinstructions

- The assembler translates pseudoinstructions into basic (hardware native) instructions when the machine code is generated
- Each pseudoinstruction may represent one or more basic instructions
- Pseudoinstructions should not be used in place of basic instructions <u>unless</u> it adds clarity to the program

Use pseudoinstructions for assignments in this class only if directed to do so and use only those explicitly stated!


Example Pseudoinstruction

- Load Address (la)
 - This pseudoinstruction loads the address of a value into a register
 - Requires only knowledge of symbol name
 - Commonly used for string values associated with I/O
 - Syntax: la reg, symbol_name
 - Example: la a0, string
 - This instruction places the memory address of the symbol string into register a0
 - Conversion: auipc # add upper immediate to PC addi # add immediate offset
 - Assembler uses internal symbol table to derive 20-bit immediate and 12-bit immediate offset

AUIPC Instruction

- Add upper immediate to PC
- This instruction adds a 20-bit immediate value to the upper 20 bits of the program counter
- This instruction enables PC-relative addressing in RISC-V
- To form a complete 32-bit PC-relative address, auipc forms a partial result
- A subsequent addi instruction adds in the lower
 12 bits to complete the 32-bit address

Load Address Conversion



Other Pseudoinstruction Examples

- mv copy value from one register to another
 - Converted to add instruction with zero register
 - Example: mv t1, t0 □ add t1, zero, t0
- neg calculate the 2's complement value
 - Converted to subtract instruction with zero register
 - Example: neg t1, t0 □ sub t1, zero, t0

Other Pseudoinstruction Examples

- nop no operation
 - Converted to add immediate with zero & constant 0
 - Example: nop □ addi zero, zero, 0
- not bitwise complement of a value
 - Converted to exclusive or immediate operation with -1 constant
 - Example: not t1, t0 □ xori t1, t0, -1