
Layer 2 Switch Management

Lab Summary

Configure L2-Switch to allow remote management access from a Telnet session.

Figure 1 Lab Topology



Lab Configuration

Start Packet Tracer File: Layer 2 Switch Management

Click on the *L2-Switch* icon and select the *CLI* folder. Hit the <enter> key for user mode prompt (>).

- Step 1: Enter global configuration mode
 - L2-Switch> enable
 - L2-Switch# configure terminal
- Step 2: Configure an SVI for L2-Switch remote management.
 - L2-Switch(config)# interface vlan 11
 - L2-Switch(config-if)# description switch management
 - L2-Switch(config-if)# ip address 192.168.3.254 255.255.255.0
 - L2-Switch(config-if)# no shutdown
 - L2-Switch(config-if)# exit
- Step 3: Configure an IP default gateway address for packet forwarding to router-2.
 - L2-Switch(config)# ip default-gateway 192.168.3.2
- Step 4: Configure enable password for remote management access (mandatory).
 - L2-Switch(config)# enable password cisconet
- Step 5: Enable default VTY lines 0 4 for remote management access to L2-Switch.
 - L2-Switch(config)# line vty 0 4
 - L2-Switch(config-line)# password cisco

- L2-Switch(config-line)# login
- L2-Switch(config-line)# end
- L2-Switch# copy running-config startup-config

Step 6: Verify Lab

Verify the configuration is correct on switch-2.

L2-Switch# show running-config

Start Telnet session from host-1, router-1 and router-2 to L2-Switch.

host: c:\> telnet 192.168.3.254

Password: **cisco** L2-Switch > **enable** Password: **cisconet** L2-Switch# **exit**

router-1# telnet 192.168.3.254

Password: **cisco** L2-Switch > **enable** Password: **cisconet** L2-Switch# **exit**

router-2# telnet 192.168.3.254

password: **cisco** L2-Switch > **enable** password: **cisconet** L2-Switch# **exit**

Lab Notes

The **ip default-gateway** command is required on L2-Switch to allow Layer 3 connectivity between switch-2 and router-2. The SVI must be in the same subnet as the default gateway (192.168.3.0/24).