# EBU6018 Advanced Transform Methods

## Wigner-Ville Distribution

**Andy Watson** 

#### Wigner-Ville Distribution

So far we have looked at transforms that compute the correlation between a <u>signal</u> and <u>basis functions that</u> <u>are functions of time and frequency (or of scale and translation)</u>. The time-frequency resolution is determined by the basis functions.

These have been the STFT and the Wavelet Transform.

An alternative approach is to compute directly:

- Time-frequency energy density- signal's energy density in both time and frequency
- (c.f. power spectrum: energy in frequency only)
- An example of this is the Wigner-Ville distribution

## Looking back: Comparison of STFT and CWT

#### Similarities:

- signal is multiplied by a function, and the transform is computed separately for different segments of signals.
- can be written in inner product form

$$STFT(b,\omega) = \left\langle s(t), \gamma(t-b)e^{j\omega t} \right\rangle$$

$$CWT(b,a) = \left\langle s(t), \frac{1}{\sqrt{a}}\psi\left(\frac{t-b}{a}\right) \right\rangle$$

#### Difference:

- Fixed time duration and freq bandwidths of  $\gamma(t)$
- Variable time duration and bandwidth of  $\psi(t)$

## Looking forward: An "instantaneous power spectrum"

Recall the power spectrum:

Power spectrum of a signal is the Fourier Transform of its

$$P(\omega) = |S(\omega)|^2 = \int_{-\infty}^{\infty} R(\tau)e^{-j\omega\tau}d\tau$$
 the Fourier Transform of autocorrelation function

where  $R(\tau)$  is the autocorrelation function (acf)

$$R(\tau) = \int_{-\infty}^{\infty} s(t)s * (t - \tau)dt = \int_{-\infty}^{\infty} s(t + \tau/2)s * (t - \tau/2)dt$$

What happens if we use *instantaneous* autocorrelation:

$$R(t,\tau) = s(t + \tau/2)s*(t - \tau/2)$$

The WVD is the Fourier Transform of

instead of  $R(\tau) = \int_{-\infty}^{\infty} R(t,\tau)dt$  ? We get the instantaneous

autocorrelation function

$$WVD_{S}(t,\omega) = \int_{-\infty}^{\infty} s(t+\tau/2)s^{*}(t-\tau/2)e^{-j\omega\tau}d\tau$$

which is the Wigner - Ville Distribution (WVD).

#### Cross-WVD vs auto-WVD

Since we can define a cross - correlation, we can also define a cross - Wigner - Ville distribution:

$$WVD_{s,g}(t,\omega) = \int_{-\infty}^{\infty} s(t+\tau/2)g * (t-\tau/2)e^{-j\omega\tau} d\tau$$

Taking complex conjugates we find

$$WVD_{s,g}(t,\omega) = WVD*_{g,s}(t,\omega)$$

So for the usual WVD ("auto - WVD") we have

$$WVD_{S}(t,\omega) = WVD_{S,S}(t,\omega) = WVD *_{S}(t,\omega)$$

so the auto - WVD is always real.

#### **Example: Gaussian function**

Signal 
$$s(t) = \sqrt[4]{\frac{\alpha}{\pi}} e^{-\alpha t^2/2}$$
 (normalized to unit energy)

For WVD, we get

$$WVDs(t,\omega) = \sqrt{\frac{\alpha}{\pi}} \int_{-\infty}^{\infty} \exp\left\{-\frac{\alpha}{2} \left[ \left(t + \frac{\tau}{2}\right)^{2} + \left(t - \frac{\tau}{2}\right)^{2} \right] \right\} e^{-j\omega\tau} d\tau$$

$$= e^{-\alpha t^{2}} \sqrt{\frac{\alpha}{\pi}} \int_{-\infty}^{\infty} \exp\left\{-\frac{\alpha}{4}\tau^{2}\right\} e^{-j\omega\tau} d\tau \qquad \text{Gaussian in time,}$$


$$= 2 \exp\left\{-\left[\alpha t^{2} + \frac{1}{\alpha}\omega^{2}\right]\right\} \qquad \text{Gaussian in t-f}$$

i.e. concentrated around (0,0).

lpha controls spread :

"time - width": 
$$|t| < \sqrt{\frac{1}{\alpha}}$$

"freq - width":  $|\omega| < \sqrt{\alpha}$ 



EBU6018

#### Example 2: Gaussian chirplet

Signal:

$$s(t) = \sqrt[4]{\frac{\alpha}{\pi}} \exp\left\{-\frac{\alpha}{2}t^2 + j\frac{\beta}{2}t^2\right\}$$

Power spectrum: 
$$|S(\omega)|^2 = \sqrt{\frac{4\pi(\alpha^2 + \beta^2)}{\alpha}} \exp\left\{-\frac{\alpha}{\alpha^2 + \beta^2}\omega^2\right\}$$

tells us which freqs s(t) contains, not when. Compare :


$$WVDs(t,\omega) = \sqrt{\frac{\alpha}{\pi}} \int_{-\infty}^{\infty} e^{-\frac{\alpha}{2} \left[ \left( t + \frac{\tau}{2} \right)^2 + \left( t - \frac{\tau}{2} \right)^2 \right] + \frac{j\beta}{2} \left[ \left( t + \frac{\tau}{2} \right)^2 - \left( t - \frac{\tau}{2} \right)^2 \right]} e^{-j\omega \tau} d\tau$$

$$= e^{-\alpha t^2} \sqrt{\frac{\alpha}{\pi}} \int_{-\infty}^{\infty} e^{-\frac{\alpha}{4}\tau^2} e^{-j(\omega - \beta t)\tau} d\tau$$

$$= 2e^{-\left[ \alpha t^2 + \frac{1}{\alpha} (\omega - \beta t)^2 \right]}$$

i.e. energy concentrated at  $\omega = \beta t$ , changing with time.

### Illustration: chirplet



#### Time-limited or band-limited signals


If s(t) is time-limited, i.e. s(t) = 0 outside some interval  $[t_{0}, t_{1}]$ , then the WVD is also time-limited, i.e.

$$WVD_s(t,\omega) = 0 \text{ for } t \notin [t_0,t_1]$$

since no value for  $\tau$  can make both  $s(t + \tau/2)$  and  $s(t - \tau/2)$  non-zero if t is outside this range.

A similar result is true for freq band-limited signals.

## Example: WVD of a Time-limited signal



## WVD Properties: Time Marginal Condition

$$\frac{1}{2\pi} \int_{-\infty}^{\infty} WVD_{S}(t,\omega)d\omega = \int_{-\infty}^{\infty} s\left(t + \frac{\tau}{2}\right) s * \left(t - \frac{\tau}{2}\right) \frac{1}{2\pi} \int_{-\infty}^{\infty} e^{-j\omega\tau} d\omega d\tau$$
$$= \int_{-\infty}^{\infty} s\left(t + \frac{\tau}{2}\right) s * \left(t - \frac{\tau}{2}\right) \delta(\tau) d\tau$$
$$= |s(t)|^{2}$$

So intregral over frequency of WVD is the signal power density at time *t* 

Compare similar result for probability densities:

$$p_X(x) = \int_{-\infty}^{\infty} p_{X,Y}(x,y) dy$$

#### Frequency Marginal Condition

$$\int_{-\infty}^{\infty} WVD_{S}(t,\omega)dt = \int_{-\infty}^{\infty} s\left(t + \frac{\tau}{2}\right)s * \left(t - \frac{\tau}{2}\right)\int_{-\infty}^{\infty} e^{-j\omega\tau} dt d\tau$$

$$= \int_{-\infty}^{\infty} e^{-j\omega\tau} \int_{-\infty}^{\infty} s(t)s * \left(t - \tau\right)dt d\tau$$

$$= \int_{-\infty}^{\infty} e^{-j\omega\tau} R(\tau)d\tau$$

$$= |S(\omega)|^{2}$$

So intregral over time of WVD is the power spectral density We also have :

$$\frac{1}{2\pi} \int_{-\infty}^{-\infty} \int_{-\infty}^{\infty} WVD_{S}(t,\omega)dtd\omega = \frac{1}{2\pi} \int_{-\infty}^{-\infty} |S(\omega)|^{2} d\omega = \int_{-\infty}^{\infty} |s(t)|^{2} dt$$

i.e. the WVD is unitary: the energy in  $WVD_s(t,\omega)$  is equal to energy in original signal s(t).

#### Time-shift & Freq-moduln. invariant

If the WVD of s(t) is  $WVD_s(t,\omega)$ , then the WVD of time - shifted signal  $s_0(t) = s(t-t_0)$  is a time - shifted WVD :  $WVD_{s_0}(t,\omega) = WVD_s(t-t_0,\omega)$ 

Further, the WVD of frequency - modulated signal

$$s_1(t)=s(t)e^{j\omega_1t}$$
 is a frequency - shifted WVD :  $WVD_{s_1}(t,\omega)=WVD_s(t,\omega-\omega_1)$ 

(Both follow immediately from the formulas for WVD)

#### WVD of multiple signals: Cross-terms


Wigner-Ville Distribution has many useful properties, and better resolution than STFT spectrogram. BUT Applications are limited due to *cross-term interference*.

Consider composite signal  $s(t) = s_1(t) + s_2(t)$ . Then  $WVD_s(t,\omega) = WVD_{s_1}(t,\omega) + WVD_{s_2}(t,\omega) + 2\operatorname{Re}\{WVD_{s_1,s_2}(t,\omega)\}$  i.e. not only the sum of WVDs, but also the cross - term  $WVD_{s_1,s_2}(t,\omega)$ 


Also, cross - term is included at double the magnitude of the auto - terms, so often obscures useful patterns.

#### Example of cross-terms

WVD gives cross-terms for all but simplest signals, e.g.:



#### Example: sum of two sinusoids



#### Example: sum of sinusoids (cont)

If  $s(t) = \exp(j\omega_0 t)$  then

$$WVD_{S}(t,\omega) = \int_{-\infty}^{\infty} \exp\left\{j\omega_{0}\left(t + \frac{t}{2} - t + \frac{t}{2}\right)\right\} e^{-j\omega t} d\tau = 2\pi\delta(\omega - \omega_{0})$$

i.e. the WVD is a "ridge" along frequency  $\omega_0$ .

Now let  $s(t) = \exp(j\omega_1 t) + \exp(j\omega_2 t)$ . The power spectrum is

$$|S(\omega)|^2 = 2\pi\delta(\omega_1) + 2\pi\delta(\omega_2)$$

while the WVD is

$$WVD_{S}(t,\omega) = 2\pi\delta(\omega - \omega_{1}) + 2\pi\delta(\omega - \omega_{2}) + 4\pi\delta(\omega - \omega_{\mu})\cos(\omega_{d}t)$$

where 
$$\omega_{\mu} = \frac{\omega_1 + \omega_2}{2}$$
 and  $\omega_d = \omega_1 - \omega_2$ .


#### Example (cont): cross-term

Get a large cross - term  $4\pi\delta(\omega-\omega_{\mu})\cos(\omega_{d}t)$  which varies as  $\cos((\omega_{1}-\omega_{2})t)$  at  $\omega_{d}$ , mid - way between the auto - terms. While the auto - terms are + ve, this oscillates + ve & - ve Average of the cross - term is zero :


$$\int_{-\infty}^{\infty} 4\pi \delta(\omega - \omega_{\mu}) \cos(\omega_{d} t) dt = 0 \qquad \omega_{d} \neq 0$$

This suggests we may be able to remove these by *smoothing* (see later.)


#### Example: 3-tone test signal




## Wigner-Ville Distribution



#### Another example: Frequency pulses



## Compare spectrogram



#### Wigner-Ville Distribution

Since the cross-terms WVD are usually strongly oscillating, try removing them by using 2D low-pass filtering, to give a "smoothed Wigner - Ville distribution" (SWVD):

$$SWVD_S(t,\omega) = \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} \phi(x,y)WVD_S(t-x,\omega-y)dxdy$$

where  $\phi(x, y)$  is a 2D low - pass filter.

Example: 2D Gaussian

$$\phi(x,y) = e^{-\alpha t^2 - \beta \omega^2} \qquad \alpha, \beta > 0$$

We have a trade-off:

more smoothing  $\rightarrow$  less cross - terms, BUT more smoothing  $\rightarrow$  reduced resolution

#### STFT Spectrogram from WVD

In general, WVD can have - ve values.

But if  $\alpha\beta \ge 1$  in the Gausian 2D filter, then the smoothed WVD will be non-negative.

Special case: when  $\alpha\beta = 1$  in  $\phi(x, y) = e^{-\alpha t^2 - \beta\omega^2}$ then  $\phi(x, y)$  is actually a WVD of a Gaussian function.

The STFT spectrogram is a smoothed WVD, with the WVD of the analysis function  $\gamma(t)$  doing the smoothing :

$$|STFT_{S}(t,\omega)|^{2} = \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} WVD_{\gamma}(x,y)WVD_{S}(t-x,\omega-y)dxdy$$

(Quan p163) Convolution of the WVD of s(t) and the WVD of the STFT window function

#### Wavelet Scalogram from WVD

The scalogram (square of the wavelet transform) can be written in terms of the WVD:


$$SCAL_{S}(a,b) = |CWT_{S}(a,b)|^{2}$$

$$= \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} WVD_{S}(x,y)WVD_{\psi}\left(\frac{x-b}{a},ay\right)dxdy$$

where  $WVD_S(x, y)$  is the WVD of the signal s(t) and  $WVD_{\psi}\left(\frac{x-b}{a}, ay\right)$  is the WVD of the mother wavelet  $\psi(t)$ .

This operation is known as affine correlation.

#### From WVD to ...?



Both the STFT spectrogram and the WT scalogram are smoothed versions of the WVD, explaining why the WVD has the best time-frequency resolution EBU6018

Slide no: 26

#### Summary: Wigner-Ville Distribution

#### Kind of Decomposition

Time-Frequency

#### Analyzing Function

Uses the signal itself. Motivated by time-frequency energy density (c.f. a probability density).

#### Variable

Time and Frequency. Has high resolution in both time and frequency.

#### Suited for

Simple signals (non-stationary), e.g. linear chirp, gaussian pulse

#### Notes

More complex signals lead to undesired "cross-terms". Can be suppressed with smoothing, but lose high resolution in the process.