# EBU6018 Advanced Transform Methods


# The Wavelet Transform

**Andy Watson** 

# The Wavelet Transform

What is a "Wavelet"?

- a "small wave"
   We can make a family of wavelets by:
- scaling and shifting a base or mother wavelet
- to create daughter wavelets (sometimes called baby wavelets)



Same wavelet, just scaled and time-shifted

# Applications of Wavelets

- Relatively new method of evaluating and processing signals
- Works on nonstationary data
- Two main applications are in feature extraction and trend analysis
- Useful in many types of applications
  - Pattern recognition
    - Biotech: distinguish normal from pathological membranes
    - Biometrics: facial/corneal/fingerprint recognition
  - Feature extraction
    - Metallurgy: characterization of rough surfaces
  - Trend detection:
    - Finance: exploring variation of stock prices
  - Perfect reconstruction
    - Communications: wireless channel signals
  - Video compression JPEG 2000

# The Wavelet

Consider scaling and translating the function y

$$\psi(t) \to \psi\left(\frac{t-b}{a}\right)$$

- a determines the centre frequency.
- b determines the translation.
- Time frequency centre of  $\psi((t-b)/a)$  are b (time centre) and  $\langle \omega \rangle/a$  (frequency centre)  $\langle \omega \rangle$  is mean freq of  $\psi$
- Daughter wavelets:

$$\psi_{a,b}(t) = \frac{1}{\sqrt{a}} \psi \left(\frac{t-b}{a}\right)$$
Mother Wavelet

## Continuous Wavelet Transform

$$CWT(a,b) = \frac{1}{\sqrt{|a|}} \int_{-\infty}^{\infty} s(t) \psi^* \left(\frac{t-b}{a}\right) dt$$
Scale
$$= \int_{-\infty}^{\infty} s(t) \psi_{a,b}^*(t) dt = \langle s, \psi_{a,b} \rangle$$
Translation

- The continuous wavelet transform, CWT(a,b) is a function of two real variables.
- Compare short-time Fourier Transform:

$$STFT(t,\omega) = \int_{-\infty}^{\infty} s(\tau) \gamma^*(\tau - t) e^{-j\omega t} d\tau$$

• Have  $\psi_{a,b}^{*}(t)$  instead of  $\gamma^{*}(\tau - t)e^{-j\omega t}$ 

# CWT: Time-Frequency Analysis

 CWT provides a time-frequency as well as timescale representation.

$$CWT(a,b) = TF(t = b, \omega = \langle \omega \rangle / a)$$


We can define the Scalogram

$$SCAL(a,b) = |CWT(a,b)|^2$$

• Compare Spectrogram:  $|STFT(t,\omega)|^2$ 

## The Windowed Fourier Transform


- Harmonic wave e<sup>-jwt</sup>
   (to perform the FT)
- A window γ(t)
   (this will be moved across the signal)
- A windowed wave
   γ(τ-t) e<sup>-jwt</sup>
   (the basis function)




EBU6018 7

# **CWT versus STFT**


CWT: Variable time-frequency resolution



Different width; Same no of cycles




STFT: Constant time-frequency resolution



Same width;

Different no of cycles



# Scaling of a signal

Consider time-scaling a signal: 
$$r(t) = s(t/\alpha)$$

This changes Fourier Transform: 
$$R(\omega) = \alpha S(\alpha \omega)$$

So changes energy: 
$$E_r = \int_{-\infty}^{\infty} \left| s(t/\alpha) \right|^2 dt = \int_{-\infty}^{\infty} \left| s(\tau) \right|^2 d(\tau \alpha) = \alpha E$$
  
New centre freq:

$$\langle \omega \rangle_R = \frac{1}{2\pi E_R} \int_{-\infty}^{\infty} \omega |R(\omega)|^2 d\omega$$

$$= \frac{1}{2\pi\alpha E} \int_{-\infty}^{\infty} \omega \left| \alpha S(\alpha \omega) \right|^{2} d\omega \qquad R(\omega) = \alpha S(\alpha \omega)$$

$$= \frac{1}{2\pi\alpha E} \int_{-\infty}^{\infty} \frac{\Omega}{\alpha} |\alpha S(\Omega)|^2 d\frac{\Omega}{\alpha} \qquad \Omega = \alpha \omega$$

$$= \frac{1}{2\pi\alpha E} \int_{-\infty}^{\infty} \Omega |S(\Omega)|^2 d\Omega = \frac{\langle \omega \rangle}{\alpha}$$
 Scaled centre freq

EBU6018

Slide no: 9


# Scaling (cont)

## New frequency width:

$$\begin{split} &\Delta_{\omega}^{2}(R) = \frac{1}{2\pi E_{R}} \int_{-\infty}^{\infty} \omega^{2} \left| R(\omega) \right|^{2} d\omega - \left\langle \omega \right\rangle_{R}^{2} \\ &= \frac{1}{2\pi \alpha E} \int_{-\infty}^{\infty} \omega^{2} \left| \alpha S(\alpha \omega) \right|^{2} d\omega - \left( \left\langle \omega \right\rangle / \alpha \right)^{2} \\ &= \frac{1}{2\pi \alpha E} \int_{-\infty}^{\infty} \left( \Omega / \alpha \right)^{2} \left| \alpha S(\Omega) \right|^{2} d\frac{\Omega}{\alpha} - \left\langle \omega \right\rangle^{2} / \alpha^{2} \\ &= \frac{1}{2\pi \alpha^{2} E} \int_{-\infty}^{\infty} \Omega^{2} \left| S(\Omega) \right|^{2} d\Omega - \left\langle \omega \right\rangle^{2} / \alpha^{2} \\ &= \frac{\Delta_{\omega}^{2}(S)}{\alpha^{2}} \qquad \text{Scaled frequency resolution} \end{split}$$

# Partition of the time-frequency plane


- High scale (low frequency)
  - large window size, better frequency resolution
- Low scale (high frequency)
  - small window size, better time resolution.



**time** 18

# Time-Freq Partition: STFT

FT: Equal time and frequency resolution



(WT: Logarithmic scale of frequency resolution)

# Inverse CWT: The Admissability Criterion

- We can construct an Inverse FT to reconstruct s(t)
  Can we do the same for CWT?
- Yes: provided that the Admissibility Condition is satisfied:

$$C_{\Psi} = \int_{-\infty}^{\infty} \frac{\left|\Psi(\omega)\right|^2}{\left|\omega\right|} d\omega < \infty$$

where  $\Psi(\omega) = \int_{-\infty}^{\infty} \psi(t) e^{-j\omega t} dt$  is the Fourier Transform of  $\psi(t)$ 

Reconstruction:

$$s(t) = \frac{1}{C_{\Psi}} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} \frac{1}{a^2} CWT(a,b) \psi_{a,b}(t) dadb$$

# Admissibility Condition (cont)

- Square of the Fourier transform must decay faster than
   1/w.
- Admissibility is measure of signal's band-limitedness.
- Admissibility implies zero average:

$$\Psi(0) = \int_{-\infty}^{\infty} \psi(t) e^{-j0t} dt = \int_{-\infty}^{\infty} \psi(t) dt = 0$$

because otherwise

$$\frac{\left|\Psi(\omega)\right|^2}{\left|\omega\right|} \to \infty \quad \text{as} \quad \omega \to 0$$

# Comparison of STFT and CWT

#### Similarities:

- signal is multiplied by a function, and the transform is computed separately for different segments of signals.
- can be written in inner product form

$$STFT(b,\omega) = \left\langle s(t), \gamma(t-b)e^{j\omega t} \right\rangle \quad CWT(b,a) = \left\langle s(t), \frac{1}{\sqrt{a}}\psi\left(\frac{t-b}{a}\right) \right\rangle$$

Time-frequency window area remains constant.

#### Difference:

- Fixed time duration and freq bandwidths of  $\gamma(t)$
- Variable time duration and bandwidth of  $\psi(t)$

# Comparison of Bases

- Fourier Transform
  - Basis is global (across all time)
  - Sinusoids with frequencies in arithmetic progression
- Gabor Transform (STFT)
  - Basis is local (in time)
  - Sinusoid times Gaussian
  - Fixed-width Gaussian "window"
- Wavelet Transform
  - Basis is local (in time)
  - Frequencies in geometric progression
  - Basis has constant shape independent of scale

## Problems with CWT

#### Redundancy (because continuous)

 Basis functions for CWT are shifted and scaled versions of each other. Usually do not form an orthonormal base.

## Infinite solution space

 The result holds an infinite number of wavelets: hard to solve and hard to find the desired results out of the transformed data.

## Efficiency

 Most transforms cannot be solved analytically. Solutions have to be calculated numerically: time-consuming.
 Must find efficient algorithms.

#### Solution?

Multiresolution Analysis