

How to set up Grok Bot to build ComfyUI workflows

This guide is for anyone who wants a desktop assistant (Grok Bot) that can help design and write ComfyUI workflow JSON — not for shipping a specific app. The same idea works with Cursor, Claude Code, or any AGENTS.md-aware tool; we focus on Grok Bot.

Recommended mode: BUILD workflows only (graphs, nodes, docs). Let your GPU run jobs unless you explicitly ask the bot to queue one.

What you need

- Windows PC with an NVIDIA GPU (16 GB VRAM is a comfortable target)
- ComfyUI Desktop or a standard ComfyUI install
- Python 3.10+ on that PC
- Grok Bot (and optionally Cursor on the same PC for local MCP)
- Tailscale — only if Grok Bot's computer is separate from the ComfyUI PC

1. Install ComfyUI

1. Install ComfyUI Desktop (or clone ComfyUI and create its venv).
2. Start it once and confirm the UI opens at <http://127.0.0.1:8188>.
3. Note the install folder — custom nodes live under `custom_nodes\`.

```
C:\Users\<You>\...\ComfyUI
```

2. Keep models in one shared folder

Point every Comfy instance at one models root (extra-model-paths / Desktop instance paths). Use the usual subfolders: `diffusion_models`, `text_encoders`, `vae`, `loras`, etc.

```
D:\ComfyUI\models\  
diffusion_models\  
text_encoders\  
vae\  
loras\
```

Optional: shared input and output directories so all instances read/write the same places.

3. Install the Comfy CLI + MCP bridge (on the ComfyUI PC)

This lets Cursor (and tools that speak MCP) talk to your local ComfyUI.

```
python -m venv %USERPROFILE%\venvs\comfy-mcp  
%USERPROFILE%\venvs\comfy-mcp\Scripts\activate  
pip install -U comfy-cli comfy-mcp  
comfy --help
```

Point `comfy-cli` at your ComfyUI install (set-default / workspace as the CLI asks).

Then create or edit `%USERPROFILE%\cursor\mcp.json`:

```
{  
  "mcpServers": {  
    "comfy-mcp": {  
      "command": "C:\\Users\\<You>\\.venvs\\comfy-mcp\\Scripts\\comfy-mcp.exe",  
      "env": {  
        "COMFY_BIN": "C:\\Users\\<You>\\.venvs\\comfy-mcp\\Scripts\\comfy.exe"  
      }  
    }  
  }  
}
```

1. Restart Cursor.
2. Keep ComfyUI running on 127.0.0.1:8188 while you work.

4. Install the Comfy agent skills

The comfy CLI can write official skills into Cursor, Claude Code, and AGENTS.md. For workflow building, install at least: comfy, comfy-debug, and comfy-director. Skip comfy-build / comfy-deploy / comfy-relay unless you need them.

On the PC (PowerShell or Terminal), after the venv is active:

```
comfy skills list
comfy skills install --skill comfy --skill comfy-debug --skill comfy-director
comfy skills status
```

Default --scope user writes into ~/.cursor/, ~/.claude/, and ~/AGENTS.md. Use --scope project to keep skills inside one repo instead.

Paste this into Grok Bot (skills install prompt)

If you prefer the bot to drive the install on your machine, send something like:

Set up ComfyUI workflow building for me on this Windows PC.

- 1) Ensure a Python venv exists at %USERPROFILE%\venvs\comfy-mcp with comfy-cli and comfy-mcp installed (upgrade if present).
- 2) Point comfy-cli at my ComfyUI install (ask me for the path if you cannot find it).
- 3) Write Cursor MCP config at %USERPROFILE%\cursor\mcp.json for comfy-mcp (command + COMFY_BIN pointing at that venv).
- 4) Run: comfy skills install --skill comfy --skill comfy-debug --skill comfy-director (user scope). Skip comfy-build, comfy-deploy, and comfy-relay unless I ask.
- 5) Confirm with comfy skills status and tell me to restart Cursor + keep ComfyUI on http://127.0.0.1:8188.

My preference: BUILD workflows only (JSON graphs, docs, fixes). Do not queue or run jobs unless I explicitly ask. Optimize graphs for my GPU: <GPU model / VRAM>.

That prompt also works almost unchanged for Claude Code or another AGENTS.md bot — swap the product name and keep the same CLI steps.

5. Tell Grok Bot how you want to work

After skills are installed, give it standing preferences once:

- GPU model and VRAM (so it picks sensible checkpoints / quants)
- Build-only unless asked to run
- Where you keep workflows and models
- Any custom nodes you already rely on

6. Optional: Grok Bot on another computer (Tailscale)

If Grok Bot's machine is not the ComfyUI PC, put both on the same Tailscale tailnet. Start Comfy listening beyond localhost:

```
python main.py --listen 0.0.0.0 --port 8188
# or --listen <this-PC-tailscale-ip>
```

Point the bot's Comfy MCP / CLI at http://<ComfyUI-PC-tailscale-ip>:8188. Until --listen is set, Cursor on the ComfyUI PC still works via 127.0.0.1, but a remote Grok Bot cannot reach the API.

7. Daily loop

1. Start ComfyUI (add --listen if the bot is remote).
2. Open Grok Bot (and Cursor if you use local MCP).
3. Ask for workflows, node wiring, or fixes — run locally when you are ready.

4. New weights go into the shared models folders; refresh Comfy after downloads.

That's it

ComfyUI + shared models + comfy-cli/MCP + three skills (comfy / comfy-debug / comfy-director) + a short preference note to Grok Bot. Everything else is downloading the model files your graphs name.