What is a Dielectric?

A dielectric is an electrical insulator that can be polarized by an applied electric field. Polarization is the process of electric dipole formation, where positive and negative charges within the material separate at a molecular or atomic level due to an external electric field. Dielectric materials are fundamental components of capacitors.

Capacitance

Capacitance (C) is a measure of a component's ability to store electrical charge. It is defined as the ratio of charge (Q) stored on either plate to the voltage (V) applied across it: $C=Q/V$. Its unit is Farads (F).

Vacuum Capacitor: For a parallel plate capacitor with a vacuum between the plates, capacitance is $C0=Q0/V=\epsilon 0A/l$, where A is the plate area, l is the distance between plates, and $\epsilon 0$ is the permittivity of free space ($8.85\times10-12$ F/m).

Dielectric Capacitor: When a dielectric material is placed between the plates, it increases the capacitance. The total charge becomes $Q=Q0+\Delta Q=(\epsilon 0E+P)A$, where P is the polarization. The new capacitance is $C=\epsilon A/l$, where ϵ is the permittivity of the dielectric material.

Dielectric Constant (ϵr): Also known as relative permittivity, it's the ratio of a material's permittivity to that of free space: $\epsilon r=\epsilon/\epsilon 0$. It can also be expressed as $\epsilon r=1+\chi$, where χ is the electric susceptibility.

Types of Polarization: There are three main types of polarization that contribute to a material's total polarization

Electronic Polarization: Occurs in all dielectric materials. It results from the displacement of the negatively charged electron cloud relative to the positive nucleus under an electric field. It only exists while an electric field is present.

Ionic Polarization: Found only in ionic materials. An applied field displaces cations in one direction and anions in the other, creating a net dipole moment.

Orientation Polarization: Occurs in substances possessing permanent dipole moments. The applied field rotates these permanent moments into alignment with the field. This effect is counteracted by thermal vibrations, so it decreases with increasing temperature.

Frequency Dependence: A dielectric's response to an alternating electric field depends on frequency. Each polarization mechanism has a relaxation frequency, the reciprocal of the minimum reorientation time. If the field frequency exceeds this, dipoles cannot keep up, and that mechanism no longer contributes to the dielectric constant (ϵr), causing it to drop abruptly.

Electronic polarization is the fastest and persists up to very high optical frequencies (10^{15} Hz).

Ionic polarization is slower and typically drops off in the infrared region (10^{12} - 10^{13} Hz).

Orientation polarization is the slowest, usually ceasing in the microwave or lower frequency radio regions (10^{9} Hz and below).

Dielectric Loss and Strength:

Dielectric Loss: The absorption of electrical energy by a dielectric subjected to an alternating electric field. It is most significant near relaxation frequencies. Low dielectric loss is desired for most applications.

Dielectric Strength: The maximum electric field a material can withstand before electrical breakdown occurs. High fields can excite many electrons into the conduction band, causing high current, localized heating, and irreversible damage.

Special Dielectric Materials

Ferroelectric Materials: Exhibit spontaneous polarization even without an external electric field, which can be reversed by applying a field. They have extremely high dielectric constants (e.g., BaTiO3)and are used in sensors, actuators, and memory (FRAM).

Piezoelectric Materials: Generate an electric field (voltage) when mechanically strained, and conversely, deform when an electric field is applied. Common examples include Quartz, GaN, AlN, and PZT, used in sensors, oscillators, and RF filters.

Applications in Electronics

MOS Transistors: The Metal-Oxide-Semiconductor structure is crucial for logic and memory devices. As devices shrink, the gate dielectric (SiO2) becomes too thin (~2nm), leading to excessive leakage current.

High-k Dielectrics: To maintain capacitance ($C=\epsilon A/t$) without shrinking thickness (t) further, materials with a higher dielectric constant (high-k), like Hafnium-based oxides (HfO2), have replaced SiO2. This allows for a thicker physical layer that reduces leakage while maintaining the same equivalent electrical performance (Equivalent Oxide Thickness, EOT).

Memory: High-k dielectrics are essential for capacitors in DRAM (Dynamic Random Access Memory) to store sufficient charge in tiny cells and in Flash memory structures.

High-k dielectrics are essential for capacitors in DRAM (Dynamic Random Access Memory) to store sufficient charge in tiny cells and in Flash memory structures.

Defects in Crystals:

Types of Crystalline Defects: Perfect crystalline order is an idealization; real materials always contain defects. These are classified by their dimensionality:

0D: Point Defects: localized to one or a few atomic sites.

Vacancy: An atom is missing from its normal lattice site. The number of vacancies (N_v) increases exponentially with temperature: $N_v=Nexp(-Qv/kT)$. [N is the total number of atomic sites (per m^3), $Q\upsilon$ is the energy required for the formation of a vacancy (J/mol or eV/atom)]

Self-Interstitial: An atom from the crystal is crowded into a small interstitial void space. This is energetically unfavorable and rare in low concentrations.

Impurities:

1. Substitutional: An impurity atom replaces a host atom.

2. Interstitial: An impurity atom occupies an interstitial void.

In Ionic Solids: To maintain charge neutrality, defects often occur in pairs:

Frenkel Defect: A cation vacancy-interstitial pair.


Schottky Defect: A paired cation and anion vacancy.


Traps are localized (in space also) energy levels near the midgap. They can capture/emit electron or hole. Determines switching speed and leakage current.

Role in Semiconductors: Impurities are intentionally added (doping) to control electrical properties. Donors (e.g., P, As in Si) add electrons, while acceptors (e.g., B, Al in Si) add holes. Unintentional "trap" states near mid-gap can degrade performance by increasing leakage.

1D: Line Defects: dislocations**:** Dislocations are line defects that facilitate plastic deformation in materials.


Edge Dislocation: Formed by an extra half-plane of atoms terminating within the crystal. The Burgers vector (b), which defines the magnitude and direction of lattice distortion, is perpendicular to the dislocation line.





Screw Dislocation: Formed by shear stress that shifts one part of the crystal relative

to another. The atomic planes spiral around the dislocation line. The Burgers vector is parallel to the dislocation line.




Mixed Dislocation: Most real dislocations have both edge and screw components.

Burgers vector : Displacement vector that “closes the loop” when traversing an equal number of lattice steps around the defect.

Edge dislocation: Burgers vector is perpendicular to dislocation line

Screw dislocation: Burgers vector is parallel to the dislocation line



Movement (Slip): Dislocations move along specific crystallographic planes (slip planes) in specific directions (slip directions) under stress, allowing materials to deform

plastically without breaking all bonds simultaneously.

Impact: While they enable ductility, a very high density of dislocations can impede their own motion, leading to material strengthening (work hardening). In electronic devices, they can act as leakage paths.

2D: Planar Defects: grain boundaries, stacking faults, external surfaces.

External Surfaces: Surface atoms have fewer neighbors and higher energy than bulk atoms

Grain Boundaries: Interfaces separating individual crystals (grains) of different crystallographic orientations in a polycrystalline material.

Stacking Faults: Errors in the stacking sequence of atomic planes (e.g., ABCABABC... instead of ABCABC...).

3D: Volume Defects: voids, precipitates, cracks.

These are macroscopic defects like pores, cracks, voids, and foreign inclusions introduced during processing. They can severely degrade mechanical and electrical integrity. Examples in GaN include micropipes, pits, and voids.

What are Phonons?

A phonon is a quantized vibration of atoms in a solid lattice. Just as photons are quanta of light (electromagnetic waves), phonons are quanta of vibrational energy in a crystal lattice. Atoms in a solid can be modeled as masses connected by springs; their vibrations create waves of displacement that travel through the lattice. Quantum mechanically, these waves have discrete energy packets called phonons, which are **bosons**.

Types of Phonons There are two main types of phonons based on their vibration mode:

Acoustic Phonons: Atoms vibrate in phase with each other (same direction). They have low energy (low frequency, long wavelength) and propagate at the speed of sound in the material. There are typically three acoustic modes: one longitudinal acoustic (LA) where atoms move along the wave direction, and two transverse acoustic (TA) where atoms move perpendicular to the wave direction. They are responsible for carrying sound and heat (thermal conductivity) in solids.

Optical Phonons: Atoms in the basis vibrate out of phase; one sublattice moves opposite to the other. They have higher energy and frequency (e.g., ~60 meV in Silicon). They only exist in crystals with more than one atom per primitive cell. They can interact with electromagnetic radiation, particularly infrared light, hence the name "optical". Modes

include one longitudinal optical (LO) and two transverse optical (TO). They are important in infrared absorption, Raman scattering, and electron-phonon interactions which affect carrier mobility.


Lattice Vibration Models

Monoatomic Linear Chain: Considers identical atoms of mass M separated by distance a, connected by springs with constant K. Equation of motion for the nth atom:

$$M\frac{d^2u_n}{dt^2} = K[(u_{n+1} - u_n) + (u_{n-1} - u_n)]$$

Assuming a traveling wave solution $u_n = u_0 e^{i(\omega t - kna)}$, the dispersion relation is derived as:

Dispersion relation: $\omega = 2\sqrt{\frac{K}{M}}\left|\sin\left(\frac{ka}{2}\right)\right|$



This describes the acoustic phonon branch.

Diatomic Linear Chain: Considers two different atoms with masses M1 and M2 in the unit cell. Equations of motion are coupled for the two atomic displacements un and vn. Solving these leads to a dispersion relation with two branches:

Equation of motion (1): $M_1\frac{d^2u_n}{dt^2} = K(v_n - u_n) + K(v_{n-1} - u_n)$

Equation of motion (2): $M_2\frac{d^2v_n}{dt^2} = K(u_n - v_n) + K(u_{n+1} - v_n)$

Assume a traveling wave solution: $u_n = u_0 e^{i(\omega t - kna)}, \quad v_n = v_0 e^{i(\omega t - kna)}$

$$\begin{bmatrix} 2K - M_1\omega^2 & -K(1 + e^{-ika}) \\ -K(1 + e^{ika}) & 2K - M_2\omega^2 \end{bmatrix} \begin{bmatrix} u_0 \\ v_0 \end{bmatrix} = 0$$

For non-trivial solutions, determinant = 0

Dispersion relation:


$$\omega^2 = K\left(\frac{1}{M_1}+\frac{1}{M_2}\right) \pm K\sqrt{\left(\frac{1}{M_1}+\frac{1}{M_2}\right)^2 - \frac{4\sin^2(ka/2)}{M_1 M_2}}$$

"+" sign → Optical branch (high frequency)
"–" sign → Acoustic branch (low frequency

The "+" sign corresponds to the Optical branch (higher frequency), and the "-" sign corresponds to the Acoustic branch (lower frequency). A bandgap can exist between the optical and acoustic branches where no vibrational modes are allowed.

Vibrational models of a diatomic lattice

9



Adjacent atoms are displaced in the same (opposite) direction for acoustical (optical) phonons

Phonons in Semiconductors

Dispersion Relation: Real materials like Silicon have complex, anisotropic phonon dispersion relations with multiple acoustic (LA, TA) and optical (LO, TO) branches.

Electrical Resistance: In extrinsic semiconductors, resistivity increases with temperature because increased phonon scattering reduces charge carrier mobility.

Indirect Bandgap Transitions: In indirect bandgap semiconductors (like Si), electron-hole recombination requires a phonon to conserve momentum because the photon alone cannot provide the large momentum change required. This makes light

emission inefficient in such materials.

Mechanical Properties

Stress and Strain

Stress (σ): Defined as force per unit area. It's a second-rank tensor σ_{ij} representing forces acting on various crystal planes. Normal stress components (σ_{11},σ_{22} ,σ_{33}) act perpendicular to faces. Shear stress components (σ_{12},σ_{21},etc.) act parallel to faces.

Strain (ϵ): A measure of deformation. It's related to the displacement gradient and is also a second-rank tensor. Normal strain components (ϵ_{11},ϵ_{22},ϵ_{33}) represent stretching or compression. Shear strain components (ϵ_{12},ϵ_{21},etc.) represent distortion of angles.

Generalized Hooke's Law: In the linear elastic regime, stress and strain are proportional. $\epsilon_{ij}=S_{ijkl}\sigma_{kl}$, where S_{ijkl} is the fourth-rank elastic compliance tensor.

$\sigma_{ij}=C_{ijkl}\epsilon_{kl}$, where C_{ijkl} is the fourth-rank elastic stiffness tensor.

Symmetry: Crystal symmetry reduces the number of independent elastic constants from 81 to fewer (e.g., 3 for cubic crystals like Si, 2 for isotropic materials).

Cubic Crystals: For cubic materials, Hooke's law can be simplified using a condensed matrix notation, relating strain vector to stress vector via a 6x6 compliance matrix involving only S_{11},S_{12},S_{44}.

Isotropic Materials: Characterized by just two independent constants: Young's modulus (Y) and Poisson's ratio (ν).

$$Y=1/S11$$

$$\nu=-S12/S11$$

Shear modulus $G=Y/(2(1+\nu))$.

Electromechanical Coupling

Piezoresistivity: A change in electrical electrical resistivity due to applied

stress/strain.

It's caused by stress-induced changes in the band structure, which alters carrier effective mass and scattering rates (mobility).

The relative change in resistivity is $\rho\Delta\rho ij=\sum k,l\pi ijkl\sigma kl$, where $\pi ijkl$ is the fourth-rank piezoresistance tensor.

Used in pressure sensors (like Bosch BMP085) where a diaphragm deflection under pressure causes stress in piezoresistors, changing their resistance.

Also used in transistors (strained silicon) to enhance carrier mobility and drive current.

Piezoelectricity:

Direct Effect: Stress induces electric polarization (charge) in crystals lacking a center of inversion (e.g., Quartz, PZT).

Converse Effect: An applied electric field induces mechanical strain.

Constitutive equations couple strain (S), stress (T), electric field (E), and displacement (D) via elastic compliance (s), piezoelectric (d), and permittivity (ϵ) tensors:

$Sij=\sum k,lsijklTkl+\sum kdkjitEk$

$Di=\sum j,kdijkTjk+\sum j\epsilon ijEj$

Applications include crystal resonators for timing (quartz watches), sensors, and actuators.