BLM2041 Signals and Systems

Week 4

The Instructors:

Prof. Dr. Nizamettin Aydın naydin@yildiz.edu.tr

Asist. Prof. Dr. Ferkan Yilmaz ferkan@yildiz.edu.tr

Systems Properties


Systems

- A system transforms input signals into output signals.
- A system is a function mapping input signals into output signals.
- We will concentrate on systems with one input and one output i.e. single-input, single-output (SISO) systems.
- Notation:
 - o y = Sx or y = S(x), meaning the system S acts on an input signal x to produce output signal y.
 - y = Sx does not (in general) mean multiplication!

Systems Properties

Block diagrams

Systems often denoted by block diagram:



- Lines with arrows denote signals (not wires).
- Boxes denote systems; arrows show inputs & outputs.
- Special symbols for some systems.


Systems Properties

Examples

(with input signal x and output signal y)

Scaling system: y(t) = ax(t)

- Called an amplifier if |a| > 1.
- Called an attenuator if |a| < 1.
- Called inverting if a < 0.
- a is called the gain or scale factor.
- Sometimes denoted by triangle or circle in block diagram:



Systems Properties

Differentiator: y(t) = x'(t)



Integrator: $y(t) = \int_a^t x(\tau) d\tau$ (a is often 0 or $-\infty$)

Common notation for integrator:



Systems Properties

time shift system: y(t) = x(t - T)

- called a *delay system* if T > 0
- ullet called a *predictor system* if T<0

convolution system:

$$y(t) = \int x(t-\tau)h(\tau) d\tau,$$

where h is a given function (you'll be hearing much more about this!)

Systems Properties

Examples with multiple inputs

Inputs $x_1(t)$, $x_2(t)$, and Output y(t))

• summing system:
$$y(t) = x_1(t) + x_2(t)$$

• difference system:
$$y(t) = x_1(t) - x_2(t)$$

$$x_1 + y$$

• multiplier system:
$$y(t) = x_1(t)x_2(t)$$

$$x_1 \longrightarrow x_2 \xrightarrow{y}$$

Systems Properties


Interconnection of Systems

We can interconnect systems to form new systems,

• cascade (or series): y = G(F(x)) = GFx $F \qquad G \qquad Y$


(note that block diagrams and algebra are reversed)

• sum (or parallel): y = Fx + Gx



Systems Properties

• feedback: y = F(x - Gy)




In general,

- Block diagrams are a symbolic way to describe a connection of systems.
- \bullet We can just as well write out the equations relating the signals.
- We can go back and forth between the system block diagram and the system equations.

Systems Properties

Example: Integrator with feedback



Input to integrator is x - ay, so

$$\int_{-\tau}^{\tau} (x(\tau) - ay(\tau)) d\tau = y(t)$$

Another useful method: the *input* to an integrator is the derivative of its output, so we have

$$x - ay = y'$$

Systems Properties

Linearity

A system F is **linear** if the following two properties hold:

• homogeneity: if x is any signal and a is any scalar,

$$F(ax) = aF(x)$$

9 superposition: if x and \tilde{x} are any two signals,

$$F(x + \tilde{x}) = F(x) + F(\tilde{x})$$

In words, linearity means:

- Scaling before or after the system is the same.
- Summing before or after the system is the same.

Linearity means the following pairs of block diagrams are equivalent, *i.e.*, have the same output for any input(s)



Examples of linear systems: scaling system, differentiator, integrator, running average, time shift, convolution, modulator, sampler.

Examples of nonlinear systems: sign detector, multiplier (sometimes), comparator, quantizer, adaptive filter

Systems Properties

• Multiplier as a modulator, $y(t) = x(t)\cos(2\pi ft)$, is linear.



• Multiplier as a squaring system, $y(t) = x^2(t)$ is nonlinear.



Systems Properties

System Memory

- A system is memoryless if the output depends only on the present input.
 - Ideal amplifier
 - Ideal gear, transmission, or lever in a mechanical system
- A system with memory has an output signal that depends on inputs in the past or future.
 - ▶ Energy storage circuit elements such as capacitors and inductors
 - Springs or moving masses in mechanical systems
- A causal system has an output that depends only on past or present inputs
 - Any real physical circuit, or mechanical system.

Systems Properties

Time-Invariance

- A system is time-invariant if a time shift in the input produces the same time shift in the output.
- ullet For a system F,

$$y(t) = Fx(t)$$


implies that

$$y(t-\tau) = Fx(t-\tau)$$

for any time shift τ .

Systems Properties

ullet Implies that delay and the system F commute. These block diagrams are equivalent:



 \bullet Time invariance is an important system property. It greatly simplifies the analysis of systems.

Systems Properties

System Stability

- Stability important for most engineering applications.
- Many definitions
- If a bounded input

$$|x(t)| \leq M_x < \infty$$


always results in a bounded output

$$|y(t)| \leq M_y < \infty,$$

where $M_{\rm x}$ and $M_{\rm y}$ are finite positive numbers, the system is Bounded Input Bounded Output (BIBO) stable.

3

Example: Cruise control, from introduction,



The output v is

$$y = H(k(x - y))$$

We'll see later that this system can become unstable if k is too large (depending on H)

- Positive error adds gas
 Delay car velocity change, speed overshoots
- Negative error cuts gas off
- Delay in velocity change, speed undershoots

Systems Properties

System Invertibility


- A system is invertible if the input signal can be recovered from the output signal.
- If F is an invertible system, and

$$v = F_2$$

then there is an inverse system F^{INV} such that

$$x = F^{INV}y = F^{INV}Fx$$

so $F^{INV}F = I$, the identity operator.



Systems Properties

Systems Described by Differential Equations

Many systems are described by a linear constant coefficient ordinary differential equation (LCCODE):

$$a_n y^{(n)}(t) + \dots + a_1 y'(t) + a_0 y(t) = b_m x^{(m)}(t) + \dots + b_1 x'(t) + b_0 x(t)$$

with given initial conditions

$$y^{(n-1)}(0), \ldots, y'(0), y(0)$$

(which fixes y(t), given x(t))

- *n* is called the *order* of the system
- ullet $b_0,\ldots,b_m,a_0,\ldots,a_n$ are the *coefficients* of the system

Systems Properties

This is important because LCCODE systems are linear when initial conditions are all zero.

- Many systems can be described this way
- If we can describe a system this way, we know it is linear

Note that an LCCODE gives an implicit description of a system.

- It describes how x(t), y(t), and their derivatives interrelate
- It doesn't give you an explicit solution for y(t) in terms of x(t)

Soon we'll be able to explicitly express y(t) in terms of x(t)

Systems Properties

Examples

Simple examples

• scaling system ($a_0 = 1$, $b_0 = a$)

$$y = ax$$

ullet integrator ($a_1=1,\ b_0=1$)

$$y' = x$$

ullet differentiator ($a_0=1,\ b_1=1$)


$$y = x'$$

ullet integrator with feedback (a few slides back, $a_1=1, a_0=a, b_0=1)$

$$y' + ay = x$$

Systems Properties

2nd Order Circuit Example



By Kirchoff's voltage law


$$x - Li' - Ri - y = 0$$


Using i = Cy',

$$x - LCy'' - RCy' - y = 0$$

$$LCy'' + RCy' + y = x$$

which is an LCCODE. This is a linear system.





Discrete-Time Systems

- Many of the same block diagram elements
- Scaling and delay blocks common
- The system equations are difference equations

$$a_0y[n] + a_1y[n-1] + \ldots = b_0x[n] + b_1x[n-1] + \ldots$$

where x[n] is the input, and y[n] is the output.

Systems Properties Discrete-Time System Example $x[n] \xrightarrow{Delay \ by \ T} y[n]$

• The input into the delay is

$$e[n] = x[n] - ay[n]$$

• The output is y[n] = e[n-1], so

$$y[n] = x[n-1] - ay[n-1].$$