

Percona Server for MongoDB 4.4 Documentation

Release 4.4.17-17

Percona LLC and/or its affiliates 2015-2022

CONTENTS

I	About Percona Server for MongoDB	
II	Installation	7
III	Features	19
IV	How to	65
V	Release Notes	103
VI	Reference	119

Percona Server for MongoDB is a free, enhanced, fully compatible, source available, drop-in replacement for MongoDB 4.4 Community Edition with enterprise-grade features. It requires no changes to MongoDB applications or code.

Hint: To see which version of *Percona Server for MongoDB* you are using check the value of the psmdbVersion key in the output of the buildInfo database command. If this key does not exist, *Percona Server for MongoDB* is not installed on the server.

Percona Server for MongoDB provides the following features:

- MongoDB's default WiredTiger engine
- Percona Memory Engine storage engine
- Data at Rest Encryption
- External authentication using OpenLDAP or Active Directory
- Audit logging to track and query database interactions of users or applications
- Hot Backup for the default WiredTiger
- Profiling Rate Limit to decrease the impact of the profiler on performance

To learn more about the features, available in *Percona Server for MongoDB*, see *Percona Server for MongoDB Feature Comparison*

CONTENTS 1

2 CONTENTS

Part I About Percona Server for MongoDB

PERCONA SERVER FOR MONGODB FEATURE COMPARISON

Percona Server for MongoDB 4.4 is based on MongoDB 4.4. *Percona Server for MongoDB* extends MongoDB Community Edition to include the functionality that is otherwise only available in MongoDB Enterprise Edition.

	PSMDB	MongoDB
Storage Engines	WiredTiger (default) Percona Memory Engine	WiredTiger (default) In-Memory (Enterprise only)
Encryption-at-Rest	• Key servers = Hashicorp Vault, KMIP • Fully open source	 Key server = KMIP Enterprise only
Hot Backup	YES (replica set)	NO
LDAP Authentication	• (legacy) LDAP authentication with SASL	Enterprise only
LDAP Authorization	YES	Enterprise only
Kerberos Authentication	YES	Enterprise only
Audit Logging	YES	Enterprise only
Log redaction	YES	Enterprise only
SNMP Monitoring	NO	Enterprise only

1.1 Profiling Rate Limiting

Profiling Rate Limiting was added to *Percona Server for MongoDB* in v3.4 with the --rateLimit argument. Since v3.6, MongoDB Community (and Enterprise) Edition includes a similar option slowOpSampleRate. Please see *Profiling Rate Limit* for more information.



Part II Installation

INSTALLING PERCONA SERVER FOR MONGODB

Percona provides installation packages of *Percona Server for MongoDB* for the most 64-bit Linux distributions. Find the full list of supported platforms on the Percona Software and Platform Lifecycle page.

The recommended installation method is from *Percona* repositories. Follow the links below for the installation instructions for your operating system.

- Install on Debian or Ubuntu
- Install on RHEL or CentOS

2.1 Alternative Install Instructions

You can also download packages from the Percona website and install them manually using dpkg or rpm.

Note: In this case, you will have to make sure that all dependencies are satisfied.

If you want more control over the installation, you can install Percona Server for MongoDB from binary tarballs.

Note: This method is for advanced users with specific needs that are not addressed by DEB and RPM packages.

If you want to run *Percona Server for MongoDB* in a Docker container, see *Running Percona Server for MongoDB* in a Docker Container.

2.2 Upgrade Instructions

If you are currently using MongoDB, see *Upgrading from MongoDB*.

If you are running an earlier version of Percona Server for MongoDB, see Upgrading from Version 4.2.

2.3 Uninstall Instructions

To uninstall Percona Server for MongoDB, see Uninstalling Percona Server for MongoDB.

2.3.1 Installing Percona Server for MongoDB on Debian and Ubuntu

Use this document to install *Percona Server for MongoDB* from Percona repositories on DEB-based distributions.

Note: *Percona Server for MongoDB* should work on other DEB-based distributions, but it is tested only on platforms listed on the Percona Software and Platform Lifecycle page.

- Package Contents
- Installing from Percona repositories
 - Configure Percona repository
 - Install the latest version
 - Install a specific version
- Running Percona Server for MongoDB

Package Contents

Package	Contains
percona-server-mongodb	The mongo shell, import/export tools, other client utilities, server software, default
	configuration, and init.d scripts.
percona-server-mongodb-	The mongod server, default configuration files, and init.d scripts
server	
percona-server-mongodb-	The mongo shell
shell	
percona-server-mongodb-	The mongos sharded cluster query router
mongos	
percona-server-mongodb-	Mongo tools for high-performance MongoDB fork from Percona
tools	
percona-server-mongodb-	Debug symbols for the server
dbg	

Installing from Percona repositories

It is recommended to install *Percona Server for MongoDB* from official Percona repositories using the **percona-release** utility.

Configure Percona repository

1. Fetch **percona-release** packages from Percona web:

```
\ wget https://repo.percona.com/apt/percona-release_latest.
$(lsb_release -sc)_all. \ deb
```

2. Install the downloaded package with **dpkg**:

```
$ sudo dpkg -i percona-release_latest.$(lsb_release -sc)_all.deb
```

Once you install this package the *Percona* repositories should be added. You can check the repository setup in the /etc/apt/sources.list.d/percona-release.list file.

3. Enable the repository:

```
$ sudo percona-release enable psmdb-44 release
```

4. Remember to update the local cache:

```
$ sudo apt update
```

Install the latest version

Run the following command to install the latest version of *Percona Server for MongoDB*:

```
$ sudo apt install percona-server-mongodb
```

Install a specific version

To install a specific version of *Percona Server for MongoDB*, do the following:

1. List available versions:

```
$ sudo apt-cache madison percona-server-mongodb
```

Sample Output

```
percona-server-mongodb | 4.4.0-1.buster | http://repo.percona.com/psmdb-44/apt_

⇒buster/main amd64 Packages
```

2. Install a specific version packages. You must specify each package with the version number. For example, to install *Percona Server for MongoDB* 4.4.0-1, run the following command:

```
$ sudo apt install percona-server-mongodb=4.4.0-1.buster percona-server-mongodb-

→mongos=4.4.0-1.buster percona-server-mongodb-shell=4.4.0-1.buster percona-server-

→mongodb-server=4.4.0-1.buster percona-server-mongodb-tools=4.4.0-1.buster
```

Running Percona Server for MongoDB

By default, *Percona Server for MongoDB* stores data files in /var/lib/mongodb/ and configuration parameters in /etc/mongod.conf.

Starting the service

Percona Server for MongoDB is started automatically after installation unless it encounters errors during the installation process.

You can also manually start it using the following command:

\$ sudo systemctl start mongod

Confirming that the service is running

Check the service status using the following command:

\$ sudo systemctl status mongod

Stopping the service

Stop the service using the following command:

\$ sudo systemctl stop mongod

Restarting the service

Restart the service using the following command:

\$ sudo systemctl restart mongod

2.3.2 Installing Percona Server for MongoDB on Red Hat Enterprise Linux and CentOS

Use this document to install Percona Server for MongoDB on RPM-based distributions from Percona repositories.

Note: Percona Server for MongoDB should work on other RPM-based distributions (for example, Amazon Linux AMI and Oracle Linux), but it is tested only on platforms listed on the Percona Software and Platform Lifecycle page.¹

- Package Contents
- Installing from Percona repositories
 - Configure Percona repository
 - Install the latest version
 - Install a specific version

¹ We support only the current stable RHEL 6 and CentOS 6 releases, because there is no official (i.e. RedHat provided) method to support or download the latest OpenSSL on RHEL and CentOS versions prior to 6.5. Similarly, and also as a result thereof, there is no official Percona way to support the latest Percona Server builds on RHEL and CentOS versions prior to 6.5. Additionally, many users will need to upgrade to OpenSSL 1.0.1g or later (due to the Heartbleed vulnerability), and this OpenSSL version is not available for download from any official RHEL and CentOS repositories for versions 6.4 and prior. For any officially unsupported system, src.rpm packages can be used to rebuild Percona Server for any environment. Please contact our support service if you require further information on this.

- Running Percona Server for MongoDB
 - Running after reboot

Package Contents

Package	Contains
percona-server-mongodb	The mongo shell, import/export tools, other client utilities, server software, default
	configuration, and init.d scripts.
percona-server-mongodb-	The mongod server, default configuration files, and init.d scripts
server	
percona-server-mongodb-	The mongo shell
shell	
percona-server-mongodb-	The mongos sharded cluster query router
mongos	
percona-server-mongodb-	Mongo tools for high-performance MongoDB fork from Percona
tools	
percona-server-mongodb-	Debug symbols for the server
dbg	

Installing from Percona repositories

The preferable way to install *Percona Server for MongoDB* is from Percona repositories. Percona repositories are managed using the **percona-release** tool.

Configure Percona repository

1. Install percona-release:

```
$ sudo yum install https://repo.percona.com/yum/percona-release-latest.noarch.rpm
```

Example of Output

```
Retrieving https://repo.percona.com/yum/percona-release-latest.noarch.rpm

Preparing...  ############################# [100%]

1:percona-release  ############################ [100%]
```

2. Enable the repository: percona-release enable psmdb-44 release

See also:

More information about how to use the percona-release tool https://www.percona.com/doc/percona-repo-config/index.html

Install the latest version

To install the latest version of *Percona Server for MongoDB*, use the following command:

\$ sudo yum install percona-server-mongodb

Install a specific version

To install a specific version of *Percona Server for MongoDB*, do the following:

1. List available versions:

\$ sudo yum list percona-server-mongodb --showduplicates

Sample Output

2. Install a specific version packages. For example, to install *Percona Server for MongoDB* 4.4.0-1, run the following command:

\$ sudo yum install percona-server-mongodb-4.4.0-1.el8

Running Percona Server for MongoDB

Note: If you are using SELinux in enforcing mode, you must customize your SELinux user policies to allow access to certain /sys and /proc files for OS-level statistics. Also, you must customize directory and port access policies if you are using non-default locations.

Please refer to Configure SELinux section of MongoDB Documentation for policy configuration guidelines.

Percona Server for MongoDB stores data files in /var/lib/mongodb/ by default. The configuration file is /etc/mongod.conf.

Starting the service

Percona Server for MongoDB is not started automatically after installation. Start it manually using the following command:

\$ sudo systemctl start mongod

Confirming that service is running

Check the service status using the following command: systemctl status mongod

\$ sudo systemctl status mongod

Stopping the service

Stop the service using the following command: systemctl stop mongod

\$ sudo systemctl stop mongod

Restarting the service

Restart the service using the following command: systemctl restart mongod

\$ sudo systemctl restart mongod

Running after reboot

The mongod service is not automatically started after you reboot the system.

For RHEL or CentOS versions 5 and 6, you can use the chkconfig utility to enable auto-start as follows:

\$ sudo chkconfig --add mongod

For RHEL or CentOS version 7, you can use the systemctl utility:

\$ sudo systemctl enable mongod

2.3.3 Installing Percona Server for MongoDB from Binary Tarball

You can find links to the binary tarballs under the Generic Linux menu item on the Percona website

There are two tarballs available:

- percona-server-mongodb-<version>-x86_64.glibc2.17.tar.gz is the general tarball, compatible with any supported operating system except Ubuntu 22.04.
- percona-server-mongodb-<version>-x86_64.glibc2.35.tar.gz is the tarball for Ubuntu 22.04.

Preconditions

The following packages are required for the installation.

On Debian / Ubuntu

- libcurl4
- libsasl2-modules
- libsasl2-modules-gssapi-mit

On Red Hat Enterprise Linux and derivatives

- libcurl
- cyrus-sasl-gssapi
- cyrus-sasl-plain

Check that they are installed in your operating system. Otherwise install them.

Procedure

1. Fetch and extract the correct binary tarball. For example, if you are running Debian 10 ("buster"):

2. Add the location of the binaries to the PATH variable:

```
$ export PATH=~/percona-server-mongodb-4.4.15-15/bin/:$PATH
```

3. Create the default data directory:

```
$ mkdir -p /data/db
```

4. Make sure that you have read and write permissions for the data directory and run mongod.

2.3.4 Running Percona Server for MongoDB in a Docker Container

Docker images of *Percona Server for MongoDB* are hosted publicly on Docker Hub at https://hub.docker.com/r/percona/percona-server-mongodb/.

For more information about using Docker, see the Docker Docs.

Note: Make sure that you are using the latest version of Docker. The ones provided via apt and yum may be outdated and cause errors.

Note: By default, Docker will pull the image from Docker Hub if it is not available locally.

To run the latest *Percona Server for MongoDB* 4.4 in a Docker container, use the following command:

Run this command as root or by using the **sudo** command

```
$ docker run -d --name psmdb --restart always \
percona/percona-server-mongodb:4.4
```

The previous command does the following:

- The docker run command instructs the docker daemon to run a container from an image.
- The -d option starts the container in detached mode (that is, in the background).
- The --name option assigns a custom name for the container that you can use to reference the container within a Docker network. In this case: psmdb.
- The --restart option defines the container's restart policy. Setting it to always ensures that the Docker daemon will start the container on startup and restart it if the container exits.
- percona/percona-server-mongodb:4.4 is the name and version tag of the image to derive the container from.

See also:

Docker Documentation: the full list of tags https://hub.docker.com/r/percona/percona-server-mongodb/tags/

Connecting from Another Docker Container

The *Percona Server for MongoDB* container exposes standard MongoDB port (27017), which can be used for connection from an application running in another container. To link the application container to the psmdb container, use the --link psmdb option when running the container with your app.

Connecting with the Mongo Shell

To start another container with the mongo shell that connects to your *Percona Server for MongoDB* container, run the following comand: docker run -it --link psmdb --rm percona/percona-server-mongodb:mongo mongo -h psmdb

Percona Server for MongoDB 4.4 Documentation, Release 4.4.17-17	

Part III

Features

CHAPTER

THREE

PERCONA MEMORY ENGINE

Percona Memory Engine is a special configuration of WiredTiger that does not store user data on disk. Data fully resides in the main memory, making processing much faster and smoother. Keep in mind that you need to have enough memory to hold the data set, and ensure that the server does not shut down.

- Using Percona Memory Engine
- Switching storage engines
- Configuring Percona Memory Engine

The *Percona Memory Engine* is available in *Percona Server for MongoDB* along with the default MongoDB engine WiredTiger.

3.1 Using Percona Memory Engine

As of version 3.2, *Percona Server for MongoDB* runs with WiredTiger by default. You can select a storage engine using the --storageEngine command-line option when you start mongod. Alternatively, you can set the storage.engine variable in the configuration file (by default, /etc/mongod.conf):

storage:

dbPath: <dataDir>
engine: inMemory

See also:

MongoDB Documentation: Configuration File Options

- storage.engine Options
- storage.wiredTiger Options
- storage.inmemory Options

3.2 Switching storage engines

3.2.1 Considerations

If you have data files in your database and want to change to Percona Memory Engine, consider the following:

- Data files created by one storage engine are not compatible with other engines, because each one has its own data model.
- When changing the storage engine, the **mongod** node requires an empty dbPath data directory when it is restarted. Though Percona Memory Engine stores all data in memory, some metadata files, diagnostics logs and statistics metrics are still written to disk. This is controlled with the --inMemoryStatisticsLogDelaySecs option.

Creating a new dbPath data directory for a different storage engine is the simplest solution. Yet when you switch between disk-using storage engines (e.g. from WiredTiger to *Percona Memory Engine*), you may have to delete the old data if there is not enough disk space for both. Double-check that your backups are solid and/or the replica set nodes are healthy before you switch to the new storage engine.

3.2.2 Procedure

To change a storage engine, you have the following options:

• If you simply want to temporarily test Percona Memory Engine, set a different data directory for the dbPath variable in the configuration file. Make sure that the user running **mongod** has read and write permissions for the new data directory.

```
$ service mongod stop
$ # In the configuration file, set the inmemory
$ # value for the storage.engine variable
$ # Set the <newDataDir> for the dbPath variable
$ service mongod start
```

• If you want to permanently switch to Percona Memory Engine and do not have any valuable data in your database, clean out the dbPath data directory (by default, /var/lib/mongodb) and edit the configuration file:

```
$ service mongod stop
$ rm -rf <dbpathDataDir>
$ # Update the configuration file by setting the new
$ # value for the storage.engine variable
$ # set the engine-specific settings such as
$ # storage.inMemory.engineConfig.inMemorySizeGB
$ service mongod start
```

- If there is data that you want to migrate and make compatible with Percona Memory Engine, use the following methods:
 - for replica sets, use the "rolling restart" process. Switch to the Percona Memory Engine on the secondary node. Clean out the dbPath data directory and edit the configuration file:

```
$ service mongod stop
$ rm -rf <dbpathDataDir>
$ # Update the configuration file by setting the new
$ # value for the storage.engine variable
$ # set the engine-specific settings such as
```

(continues on next page)

(continued from previous page)

```
$ # storage.inMemory.engineConfig.inMemorySizeGB
$ service mongod start
```

Wait for the node to rejoin with the other nodes and report the SECONDARY status.

Repeat the procedure to switch the remaining nodes to Percona Memory Engine.

- for a standalone instance or a single-node replica set, use the mongodump and mongorestore utilities:

```
$ mongodump --out <dumpDir>
$ service mongod stop
$ rm -rf <dbpathDataDir>
$ # Update the configuration file by setting the new
$ # value for the storage.engine variable
$ # set the engine-specific settings such as
$ # storage.inMemory.engineConfig.inMemorySizeGB
$ service mongod start
$ mongorestore <dumpDir>
```

3.2.3 Switching engines with encrypted data

Using *Data at Rest Encryption* means using the same storage.* configuration options as for WiredTiger. To change from normal to *Data at Rest Encryption* mode or backward, you must clean up the dbPath data directory, just as if you change the storage engine. This is because **mongod** cannot convert the data files to an encrypted format 'in place'. It must get the document data again either via the initial sync from another replica set member, or from imported backup dump.

3.3 Configuring Percona Memory Engine

You can configure the Percona Memory Engine using either command-line options or corresponding parameters in the /etc/mongod.conf file. The configuration file is formatted in YAML. For example:

```
storage:
   engine: inMemory
   inMemory:
    engineConfig:
       inMemorySizeGB: 140
       statisticsLogDelaySecs: 0
```

Setting parameters in the previous example configuration file is the same as starting the mongod daemon with the following options:

```
$ mongod --storageEngine=inMemory \
--inMemorySizeGB=140 \
--inMemoryStatisticsLogDelaySecs=0
```

The following options are available (with corresponding YAML configuration file parameters):

```
--inMemorySizeGB
```

```
Config storage.inMemory.engineConfig.inMemorySizeGB

Default 50% of total memory minus 1024 MB, but not less than 256 MB
```

Specifies the maximum memory in gigabytes to use for data.

--inMemoryStatisticsLogDelaySecs

 $\textbf{Config} \ \texttt{storage.inMemory.engineConfig.statisticsLogDelaySecs}$

Default 0

Specifies the number of seconds between writes to statistics log. If 0 is specified then statistics are not logged.

CHAPTER

FOUR

HOT BACKUP

Percona Server for MongoDB includes an integrated open source hot backup system for the default WiredTiger storage engine. It creates a physical data backup on a running server without notable performance and operating degradation.

Note: Hot backups are done on mongod servers independently, without synchronizing them across replica set members and shards in a cluster. To ensure data consistency during backups and restores, we recommend using Percona Backup for MongoDB.

- Making a backup
- Saving a backup to a TAR archive
- View backup status
- Streaming hot backups to a remote destination
 - Credentials
 - Examples
- Restoring data from backup

4.1 Making a backup

To take a hot backup of the database in your current dbpath, do the following:

• Make sure to provide access to the backup directory for the mongod user

```
chown mongod:mongod <backupDir>
```

• Run the createBackup command as administrator on the admin database and specify the backup directory.

```
> use admin
switched to db admin
> db.runCommand({createBackup: 1, backupDir: "<backup_data_path>"})
{ "ok" : 1 }
```

The backup taken is the snapshot of the mongod server's dataDir at the moment of the createBackup command start

If the backup was successful, you should receive an { "ok" : 1 } object. If there was an error, you will receive a failing ok status with the error message, for example:

```
> db.runCommand({createBackup: 1, backupDir: ""})
{ "ok" : 0, "errmsg" : "Destination path must be absolute" }
```

4.2 Saving a backup to a TAR archive

Implementation details

This feature was implemented in *Percona Server for MongoDB* 4.2.1-1.

To save a backup as a *tar* archive, use the *archive* field to specify the destination path:

```
> use admin
...
> db.runCommand({createBackup: 1, archive: <path_to_archive>.tar })
```

4.3 View backup status

As of version 4.4.8-9, you can view the backup status using the \$currentOp aggregation stage. You can also use the currentOp command though it is considered legacy.

Run the \$currentOp against the admin database:

Sample output

```
"type" : "op",
"host" : "bionic:27017",
"desc" : "conn1251",
"connectionId" : 1251,
"client" : "127.0.0.1:52898",
"appName" : "MongoDB Shell",
"clientMetadata" : {
    "application" : {
        "name" : "MongoDB Shell"
    },
    "driver" : {
        "name" : "MongoDB Internal Client",
        "version" : "4.4.8-9"
    },
    "os" : {
        "type" : "Linux",
        "name" : "Ubuntu".
```

(continues on next page)

(continued from previous page)

```
"architecture" : "x86_64",
          "version" : "18.04"
     }
  },
  "active" : true,
  "currentOpTime": "2021-08-12T11:39:57.675+0000",
  "opid" : 222817,
  "lsid" : {
     "id" : UUID("6f8d06fc-842b-420c-a43f-495db7bd6d88"),
     "uid" : BinData(0,"47DEQpj8HBSa+/TImW+5JCeuQeRkm5NMpJWZG3hSuFU=")
  },
  "secs_running" : NumberLong(1),
  "microsecs_running" : NumberLong(1516769),
  "op" : "command",
  "ns" : "admin.$cmd",
  "command" : {
     "createBackup" : 1,
      "backupDir" : "/tmp/mongo",
      "lsid" : {
         "id" : UUID("6f8d06fc-842b-420c-a43f-495db7bd6d88")
      "$db" : "admin"
  "msg" : "Hot Backup: copying data bytes Hot Backup: copying data bytes:
  971530240/1147213741 84%",
  "progress" : {
     "done": 971530240.
     "total" : 1147213741
  },
  "numYields" : 0,
  "locks" : {
  },
  "waitingForLock" : false,
  "lockStats" : {
  },
  "waitingForFlowControl" : false,
 "flowControlStats" : {
 }
}
```

4.4 Streaming hot backups to a remote destination

Percona Server for MongoDB enables uploading hot backups to an Amazon S3 or a compatible storage service, such as MinIO.

This method requires that you provide the *bucket* field in the *s3* object:

In addition to the mandatory *bucket* field, the s3 object may contain the following fields:

Field	Type	Description
bucket	string	The only mandatory field. Names are subject to restrictions
		described in the Bucket Restrictions and Limitations section
		of Amazon S3 documentation
path	string	The virtual path inside the specified bucket where the backup
		will be created. If the <i>path</i> is not specified then the backup is
		created in the root of the bucket. If there are any objects under
		the specified path, the backup will not be created and an error
		will be reported.
endpoint	string	The endpoint address and port - mainly for AWS S3 compati-
		ble servers such as the <i>MinIO</i> server. For a local MinIO server,
		this can be "127.0.0.1:9000". For AWS S3 this field can be
		omitted.
scheme	string	"HTTP" or "HTTPS" (default). For a local MinIO server
		started with the <i>minio server</i> command this should field should
		contain HTTP.
useVirtualAddressing	bool	The style of addressing buckets in the URL. By default 'true'.
		For MinIO servers, set this field to false . For more informa-
		tion, see Virtual Hosting of Buckets in the Amazon S3 docu-
		mentation.
region	string	The name of an AWS region. The default region is
		US_EAST_1 . For more information see AWS Service End-
		points in the Amazon S3 documentation.
profile	string	The name of a credentials profile in the <i>credentials</i> configura-
		tion file. If not specified, the profile named default is used.
accessKeyId	string	The access key id
secretAccessKey	string	The secret access key

4.4.1 Credentials

If the user provides the access key id and the secret access key parameters, these are used as credentials.

If the *access key id* parameter is not specified then the credentials are loaded from the credentials configuration file. By default, it is ~/.aws/credentials.

An example of the credentials file

```
[default]
aws_access_key_id = ABC123XYZ456QQQAAAFFF
aws_secret_access_key = zuf+secretkey0secretkey1secretkey2
[localminio]
aws_access_key_id = ABCABCABCABC55566678
aws_secret_access_key = secretaccesskey1secretaccesskey2secretaccesskey3
```

4.4.2 Examples

Backup in root of bucket on local instance of MinIO server

```
> db.runCommand({createBackup: 1, s3: {bucket: "backup20190901500",
scheme: "HTTP",
endpoint: "127.0.0.1:9000",
useVirtualAddressing: false,
profile: "localminio"}})
```

Backup on MinIO testing server with the default credentials profile

The following command creates a backup under the virtual path "year2019/day42" in the backup bucket:

```
> db.runCommand({createBackup: 1, s3: {bucket: "backup", path: "year2019/day42", endpoint: "sandbox.min.io:9000", useVirtualAddressing: false}})
```

Backup on AWS S3 service using default settings

```
> db.runCommand({createBackup: 1, s3: {bucket: "backup", path: "year2019/day42"}})
```

See also:

AWS Documentation: Providing AWS Credentials https://docs.aws.amazon.com/sdk-for-cpp/v1/developer-guide/credentials.html

4.5 Restoring data from backup

Restoring from backup on a standalone server

To restore your database on a standalone server, stop the mongod service, clean out the data directory and copy files from the backup directory to the data directory. The mongod user requires access to those files to start the service. Therefore, make the mongod user the owner of the data directory and all files and subdirectories under it, and restart the mongod service.

Run the following commands as root or by using the **sudo** command

```
# Stop the mongod service
$ systemctl stop mongod
# Clean out the data directory
$ rm -rf /var/lib/mongodb/*
# Copy backup files
```

(continues on next page)

(continued from previous page)

```
$ cp -RT <backup_data_path> /var/lib/mongodb/
# Grant permissions to data files for the mongod user
$ chown -R mongod:mongod /var/lib/mongodb/
# Start the mongod service
$ systemctl start mongod
```

Restoring from backup in a replica set

The recommended way to restore the replica set from a backup is to restore it into a standalone node and then initiate it as the first member of a new replica set.

Note: If you try to restore the node into the existing replica set and there is more recent data, the restored node detects that it is out of date with the other replica set members, deletes the data and makes an initial sync.

Run the following commands as root or by using the sudo command

The restore steps are the following:

1. Stop the mongod service:

```
$ systemctl stop mongod
```

2. Clean the data directory and then copy the files from the backup directory to your data directory. Assuming that the data directory is /var/lib/mongodb/, use the following commands:

```
$ rm -rf /var/lib/mongodb/*
$ cp -RT <backup_data_path> /var/lib/mongodb/
```

3. Grant permissions to the data files for the mongod user

```
$ chown -R mongod:mongod /var/lib/mongodb/
```

4. Make sure the replication is disabled in the config file and start the mongod service.

```
$ systemctl start mongod
```

5. Connect to your standalone node via the mongo shell and drop the local database

```
> mongo
> use local
> db.dropDatabase()
```

- 6. Restart the node with the replication enabled
 - Shut down the node.

```
$ systemctl stop mongod
```

- Edit the configuration file and specify the replication.replSetname option
- Start the mongod node:

```
$ systemctl start mongod
```

7. Initiate a new replica set

```
# Start the mongo shell
> mongo
# Initiate a new replica set
> rs.initiate()
```

PROFILING RATE LIMIT

Percona Server for MongoDB can limit the number of queries collected by the database profiler to decrease its impact on performance. Rate limit is an integer between 1 and 1000 and represents the fraction of queries to be profiled. For example, if you set it to 20, then every 20th query will be logged. For compatibility reasons, rate limit of 0 is the same as setting it to 1, and will effectively disable the feature meaning that every query will be profiled.

The MongoDB database profiler can operate in one of three modes:

- 0: Profiling is disabled. This is the default setting.
- 1: The profiler collects data only for *slow* queries. By default, queries that take more than 100 milliseconds to execute are considered *slow*.
- 2: Collects profiling data for all database operations.

Mode 1 ignores all *fast* queries, which may be the cause of problems that you are trying to find. Mode 2 provides a comprehensive picture of database performance, but may introduce unnecessary overhead.

With rate limiting you can collect profiling data for all database operations and reduce overhead by sampling queries. Slow queries ignore rate limiting and are always collected by the profiler.

5.1 Comparing to the sampleRate option

The sampleRate option (= slowOpSampleRate config file option) is a similar concept to rateLimit. But it works at different profile level, completely ignores operations faster than slowOpsThresholdMs (a.k.a. slowMs), and affects the log file printing, too.

	sampleRate	rateLimit
Affects profiling level 1	yes	no
Affects profiling level 2	no	yes
Discards/filters slow ops	yes	no
Discards/filters fast ops	no	yes
Affects log file	yes	no
Example value of option	0.02	50

rateLimit is a better way to have continuous profiling for monitoring or live analysis purposes. sampleRate requires setting slowOpsThresholdMs to zero if you want to sample all types of operations. sampleRate has an effect on the log file which may either decrease or increase the log volume.

5.2 Enabling the Rate Limit

To enable rate limiting, set the profiler mode to 2 and specify the value of the rate limit. Optionally, you can also change the default threshold for slow queries, which will not be sampled by rate limiting.

For example, to set the rate limit to 100 (profile every 100th *fast* query) and the slow query threshold to 200 (profile all queries slower than 200 milliseconds), run the mongod instance as follows:

```
$ mongod --profile 2 --slowms 200 --rateLimit 100
```

To do the same at runtime, use the profile command. It returns the *previous* settings and "ok" : 1 indicates that the operation was successful:

```
| > db.runCommand( { profile: 2, slowms: 200, ratelimit: 100 } );
{ "was" : 0, "slowms" : 100, "ratelimit" : 1, "ok" : 1 }
```

To check the current settings, run profile: -1:

```
> db.runCommand( { profile: -1 } );
{ "was" : 2, "slowms" : 200, "ratelimit" : 100, "ok" : 1 }
```

If you want to set or get just the rate limit value, use the profilingRateLimit parameter on the admin database:

```
> db.getSiblingDB('admin').runCommand( { setParameter: 1, "profilingRateLimit": 100 } );
{ "was" : 1, "ok" : 1 }
> db.getSiblingDB('admin').runCommand( { getParameter: 1, "profilingRateLimit": 1 } );
{ "profilingRateLimit" : 100, "ok" : 1 }
```

If you want rate limiting to persist when you restart mongod, set the corresponding variables in the MongoDB configuration file (by default, /etc/mongod.conf):

```
operationProfiling:
  mode: all
  slowOpThresholdMs: 200
  rateLimit: 100
```

Note: The value of the operationProfiling.mode variable is a string, which you can set to either off, slowOp, or all, corresponding to profiling modes 0, 1, and 2.

5.3 Profiler Collection Extension

Each document in the system.profile collection includes an additional rateLimit field. This field always has the value of 1 for *slow* queries and the current rate limit value for *fast* queries.

AUTHENTICATION

Authentication is the process of verifying a client's identity. Normally, a client needs to authenticate themselves against the MongoDB server user database before doing any work or reading any data from a mongod or mongos instance.

By default, *Percona Server for MongoDB* provides a SCRAM (Salted Challenge Response Authentication Mechanism) authentication mechanism where clients authenticate themselves by providing their user credentials. In addition, you can integrate *Percona Server for MongoDB* with a separate service, such as OpenLDAP or Active Directory. This enables users to access the database with the same credentials they use for their emails or workstations.

You can use any of these authentication mechanisms supported in *Percona Server for MongoDB*:

- SCRAM (default)
- x.509 certificate authentication
- LDAP authentication with SASL
- Kerberos Authentication
- Authentication and authorization with direct binding to LDAP

6.1 SCRAM

SCRAM is the default authentication mechanism. *Percona Server for MongoDB* verifies the credentials against the user's name, password and the database where the user record is created for a client (authentication database). For how to enable this mechanism, see *Enabling Authentication*.

6.2 x.509 certificate authentication

This authentication mechanism enables a client to authenticate in *Percona Server for MongoDB* by providing an x.509 certificate instead of user credentials. Each certificate contains the subject field defined in the DN (Distinguished Name) format. In *Percona Server for MongoDB*, each certificate has a corresponding user record in the \$external database. When a user connects to the database, *Percona Server for MongoDB* matches the subject value against the usernames defined in the \$external database.

For production use, we recommend using valid CA (Certified Authority) certificates. For testing purposes, you can generate and use self-signed certificates.

x.509 authentication is compatible with with *LDAP authorization* to enable you to control user access and operations in *Percona Server for MongoDB*. For configuration guidelines, refer to *Set up x.509 authentication and LDAP authorization*.

See also:

MongoDB Documentation: x.509

Percona Blog: Setting up MongoDB with Member x509 auth and SSL + easy-rsa

6.3 LDAP authentication with SASL

6.4 Overview


LDAP authentication with SASL (Simple Authentication and Security Layer) means that both the client and the server establish a SASL session using the SASL library. Then authentication (bind) requests are sent to the LDAP server through the SASL authentication daemon (saslauthd) that acts as a remote proxy for the mongod server.

The following components are necessary for external authentication to work:

- LDAP Server: Remotely stores all user credentials (i.e. user name and associated password).
- SASL Daemon: Used as a MongoDB server-local proxy for the remote LDAP service.
- SASL Library: Used by the MongoDB client and server to create data necessary for the authentication mechanism.

The following image illustrates this architecture:

MongoDB Client



An authentication session uses the following sequence:

- 1. A mongo client connects to a running mongod instance.
- 2. The client creates a PLAIN authentication request using the SASL library.
- 3. The client then sends this SASL request to the server as a special Mongo command.
- 4. The mongod server receives this SASL Message, with its authentication request payload.
- 5. The server then creates a SASL session scoped to this client, using its own reference to the SASL library.
- 6. Then the server passes the authentication payload to the SASL library, which in turn passes it on to the saslauthd daemon.

- 7. The saslauthd daemon passes the payload on to the LDAP service to get a YES or NO authentication response (in other words, does this user exist and is the password correct).
- 8. The YES/NO response moves back from saslauthd, through the SASL library, to mongod.
- 9. The mongod server uses this YES/NO response to authenticate the client or reject the request.
- 10. If successful, the client has authenticated and can proceed.

For configuration instructions, refer to Setting up LDAP authentication with SASL.

6.5 Kerberos Authentication

Percona Server for MongoDB supports Kerberos authentication starting from release 4.2.6-6.


This authentication mechanism involves the use of a *Key Distribution Center (KDC)* - a symmetric encryption component which operates with tickets. A *ticket* is a small amount of encrypted data which is used for authentication. It is issued for a user session and has a limited lifetime.

When using Kerberos authentication, you also operate with principals and realms.

A realm is the logical network, similar to a domain, for all Kerberos nodes under the same master KDC.

A *principal* is a user or a service which is known to Kerberos. A principal name is used for authentication in Kerberos. A service principal represents the service, e.g. mongodb. A user principal represents the user. The user principal name corresponds to the username in the **\$external** database in *Percona Server for MongoDB*.

The following diagram shows the authentication workflow:



The sequence is the following:

- 1. A mongo client sends the Ticket-Grantng Ticket (TGT) request to the Key Distribution Center (KDC)
- 2. The KDC issues the ticket and sends it to the mongo client.
- 3. The mongo client sends the authentication request to the mongo server presenting the ticket.

Percona Server for MongoDB 4.4 Documentation, Release 4.4.17-17

- 4. The mongo server validates the ticket in the KDC.
- 5. Upon successful ticket validation, the authentication request is approved and the user is authenticated.

Kerberos authentication in *Percona Server for MongoDB* is implemented the same way as in MongoDB Enterprise.

See also:

MongoDB Documentation: Kerberos Authentication

LDAP AUTHORIZATION

LDAP authorization allows you to control user access and operations in your database environment using the centralized user management storage – an LDAP server. You create and manage user credentials and permission information in the LDAP server. In addition, you create roles in the admin database with the names that exactly match the LDAP group Distinguished Name. These roles define what privileges the users who belong to the corresponding LDAP group.

7.1 Supported authentication mechanisms

LDAP authorization is compatible with the following authentication mechanisms:

- x.509 certificate authentication
- Kerberos Authentication
- Authentication and authorization with direct binding to LDAP

7.2 Authentication and authorization with direct binding to LDAP

Starting with release 4.2.5-5, you can configure *Percona Server for MongoDB* to communicate with the LDAP server directly to authenticate and also authorize users.


The advantage of using this mechanism is that it is easy to setup and does not require pre-creating users in the dummy \$external db. Nevertheless, the --authenticationDatabase connection argument will still need to be specified as \$external.

The following example illustrates the connection to Percona Server for MongoDB from the mongo shell:

```
mongo -u "CN=alice,CN=Users,DC=engineering,DC=example,DC=com" -p --

→authenticationDatabase '$external' --authenticationMechanism PLAIN
```

The following diagram illustrates the authentication and authorization flow:



- 1. A user connects to the db providing their credentials
- 2. If required, *Percona Server for MongoDB transforms the username* to match the DN in the LDAP server according to the mapping rules specified for the --ldapUserToDNMapping parameter.
- 3. *Percona Server for MongoDB* queries the LDAP server for the user identity and /or the LDAP groups this user belongs to.
- 4. The LDAP server evaluates the query and if a user exists, returns their LDAP groups.
- 5. Percona Server for MongoDB authorizes the user by mapping the DN of the returned groups against the roles assigned to the user in the admin database. If a user belongs to several groups they receive permissions associated with every group.

7.2.1 Username transformation

If clients connect to *Percona Server for MongoDB* with usernames that are not LDAP DN, these usernames must be converted to the format acceptable by LDAP.

To achieve this, the --ldapUserToDNMapping parameter is available in *Percona Server for MongoDB* configuration.

The --ldapUserToDNMapping parameter is a JSON string representing an ordered array of rules expressed as JSON documents. Each document provides a regex pattern (match field) to match against a provided username. If that pattern matches, there are two ways to continue:

- If there is the substitution value, then the matched pattern becomes the username of the user for further processing.
- If there is the ldapQuery value, the matched pattern is sent to the LDAP server and the result of that LDAP query becomes the DN of the user for further processing.

Both substitution and ldapQuery should contain placeholders to insert parts of the original username – those placeholders are replaced with regular expression submatches found on the match stage.

So having an array of documents, *Percona Server for MongoDB* tries to match each document against the provided name and if it matches, the name is replaced either with the substitution string or with the result of the LDAP query.

LDAP referrals

As of version 4.2.10-11, *Percona Server for MongoDB* supports LDAP referrals as defined in RFC 4511 4.1.10. For security reasons, referrals are disabled by default. Double-check that using referrals is safe before enabling them.

To enable LDAP referrals, set the ldapFollowReferrals server parameter to true using the *setParameter* command or by editing the configuration file.

setParameter:

ldapFollowReferrals: true

Connection pool

As of version 4.2.10-11, *Percona Server for MongoDB* always uses a connection pool to LDAP server to process bind requests. The connection pool is enabled by default. The default connection pool size is 2 connections.

You can change the connection pool size either at the server startup or dynamically by specifying the value for the ldapConnectionPoolSizePerHost server parameter.

For example, to set the number of connections in the pool to 5, use the setParameter command:

```
Command line

$ db.adminCommand( { setParameter: 1, ldapConnectionPoolSizePerHost: 5 } )

Configuration file:

setParameter:
    ldapConnectionPoolSizePerHost: 5
```

Support for multiple LDAP servers

As of version 4.2.12-13, you can specify multiple LDAP servers for failover. *Percona Server for MongoDB* sends bind requests to the first server defined in the list. When this server is down or unavailable, it sends requests to the next server and so on. Note that *Percona Server for MongoDB* keeps sending requests to this server even after the unavailable server recovers.

Specify the LDAP servers as a comma-separated list in the format <host>:<port> for the -ldapServers option.

You can define the option value at the server startup by editing the configuration file.

```
security:
   authorization: "enabled"
   ldap:
      servers: "ldap1.example.net,ldap2.example.net"
```

You can change ldapServers dynamically at runtime using the *setParameter*.

See also:

MongoDB Documentation:

- Authenticate and Authorize Users Using Active Directory via Native LDAP
- LDAP referrals

7.3 Configuration

For how to configure LDAP authorization with the native LDAP authentication, see *Setting up LDAP authentication* and authorization using NativeLDAP.

CHAPTER

EIGHT

AUDITING

Auditing allows administrators to track and log user activity on a MongoDB server. With auditing enabled, the server will generate an audit log file. This file contains information about different user events including authentication, authorization failures, and so on.

To enable audit logging, specify where to send audit events using the --auditDestination option on the command line or the auditLog.destination variable in the configuration file.

If you want to output events to a file, also specify the format of the file using the --auditFormat option or the auditLog.format variable, and the path to the file using the --auditPath option or the auditLog.path variable.

To filter recorded events, use the *--auditFilter* option or the auditLog.filter variable.

For example, to log only events from a user named *tim* and write them to a JSON file /var/log/psmdb/audit.json, start the server with the following parameters:

```
mongod \
  --dbpath data/db
  --auditDestination file \
  --auditFormat JSON \
  --auditPath /var/log/psmdb/audit.json \
  --auditFilter '{ "users.user" : "tim" }'
```

The options in the previous example can be used as variables in the MongoDB configuration file:

```
storage:
  dbPath: data/db
auditLog:
  destination: file
  format: JSON
  path: /var/log/psmdb/audit.json
  filter: '{ "users.user" : "tim" }'
```

This example shows how to send audit events to the syslog. Specify the following parameters:

```
mongod \
--dbpath data/db
--auditDestination syslog \
```

Alternatively, you can edit the MongoDB configuration file:

```
storage:
dbPath: data/db
```

(continues on next page)

(continued from previous page)

auditLog:
 destination: syslog

Note: If you start the server with auditing enabled, it cannot be disabled dynamically during runtime.

8.1 Audit Options

The following options control audit logging:

--auditDestination

Variable auditLog.destination

Type String

Enables auditing and specifies where to send audit events:

- console: Output audit events to stdout.
- file: Output audit events to a file specified by the --auditPath option in a format specified by the --auditFormat option.
- syslog: Output audit events to syslog.

--auditFilter

Variable auditLog.filter

Type String

Specifies a filter to apply to incoming audit events, enabling the administrator to only capture a subset of them. The value must be interpreted as a query object with the following syntax:

```
{ <field1>: <expression1>, ... }
```

Audit log events that match this query will be logged. Events that do not match this query will be ignored.

For more information, see Audit Filter Examples.

--auditFormat

Variable auditLog.format

Type String

Specifies the format of the audit log file, if you set the --auditDestination option to file.

The default value is JSON. Alternatively, you can set it to BSON.

--auditPath

Variable auditLog.path

Type String

Specifies the fully qualified path to the file where audit log events are written, if you set the --auditDestination option to file.

If this option is not specified, then the auditLog.json file is created in the server's configured log path. If log path is not configured on the server, then the auditLog.json file is created in the current directory (from which mongod was started).

Note: This file will rotate in the same manner as the system log path, either on server reboot or using the logRotate command. The time of rotation will be added to the old file's name.

8.2 Audit Message Syntax

Audit logging writes messages in JSON format with the following syntax:

```
{
  atype: <String>,
  ts : { "$date": <timestamp> },
  local: { ip: <String>, port: <int> },
  remote: { ip: <String>, port: <int> },
  users : [ { user: <String>, db: <String> }, ... ],
  roles: [ { role: <String>, db: <String> }, ... ],
  param: <document>,
  result: <int>
}
```

atype Event type

ts Date and UTC time of the event

local Local IP address and port number of the instance

remote Remote IP address and port number of the incoming connection associated with the event

users Users associated with the event

roles Roles granted to the user

param Details of the event associated with the specific type

result Exit code (0 for success)

8.3 Audit Filter Examples

The following examples demonstrate the flexibility of audit log filters.

```
• Standard Query Selectors
```

- Regular Expressions
- Read and Write Operations

```
auditLog:
   destination: file
    filter: '{atype: {$in: [
        "authenticate", "authCheck",
```

(continues on next page)

(continued from previous page)

```
"renameCollection", "dropCollection", "dropDatabase",
    "createUser", "dropUser", "dropAllUsersFromDatabase", "updateuser",
    "grantRolesToUser", "revokeRolesFromUser", "createRole", "updateRole",
    "dropRole", "dropAllRolesFromDatabase", "grantRolesToRole", "revokeRolesFromRole

"",

"grantPrivilegesToRole", "revokePrivilegesFromRole",
    "replSetReconfig",
    "enableSharding", "shardCollection", "addShard", "removeShard",
    "shutdown",
    "applicationMessage"
]}}'
```

8.3.1 Standard Query Selectors

You can use query selectors, such as \$eq, \$in, \$gt, \$lt, \$ne, and others to log multiple event types.

For example, to log only the dropCollection and dropDatabase events:

· Command line:

```
--auditDestination file --auditFilter '{ atype: { $in: [ "dropCollection", 

→"dropDatabase" ] } }'
```

• Config file:

```
auditLog:
   destination: file
   filter: '{ atype: { $in: [ "dropCollection", "dropDatabase" ] } }'
```

8.3.2 Regular Expressions

Another way to specify multiple event types is using regular expressions.

For example, to filter all drop operations:

· Command line:

```
--auditDestination file --auditFilter '{ "atype" : /^drop.*/ }'
```

• Config file:

```
auditLog:
  destination: file
  filter: '{ "atype" : /^drop.*/ }'
```

8.3.3 Read and Write Operations

By default, operations with successful authorization are not logged, so for this filter to work, enable auditAuthorizationSuccess parameter, as described in *Enabling Auditing of Authorization Success*.

For example, to filter read and write operations on all the collections in the test database:

Note: The dot (.) after the database name in the regular expression must be escaped with two backslashes (\\).

· Command line:

```
--setParameter auditAuthorizationSuccess=true --auditDestination file --auditFilter

→'{ atype: "authCheck", "param.command": { $in: [ "find", "insert", "delete",

→"update", "findandmodify" ] }, "param.ns": /^test\\./ } }'
```

• Config file:

8.4 Enabling Auditing of Authorization Success

By default, only authorization failures for the authCheck action are logged by the audit system. authCheck is for authorization by role-based access control, it does not concern authentication at logins.

To enable logging of authorization successes, set the auditAuthorizationSuccess parameter to true. Audit events will then be triggered by every command, including CRUD ones.

Warning: Enabling the auditAuthorizationSuccess parameter heavily impacts the performance compared to logging only authorization failures.

You can enable it on a running server using the following command:

```
db.adminCommand( { setParameter: 1, auditAuthorizationSuccess: true } )
```

To enable it on the command line, use the following option when running mongod or mongos process:

```
--setParameter auditAuthorizationSuccess=true
```

You can also add it to the configuration file as follows:

```
setParameter:
auditAuthorizationSuccess: true
```

48 Chapter 8. Auditing

CHAPTER

NINE

LOG REDACTION

Percona Server for MongoDB can prevent writing sensitive data to the diagnostic log by redacting messages of events before they are logged. To enable log redaction, run mongod with the --redactClientLogData option.

Note: Metadata such as error or operation codes, line numbers, and source file names remain visible in the logs.

Log redaction is important for complying with security requirements, but it can make troubleshooting and diagnostics more difficult due to the lack of data related to the log event. For this reason, debug messages are not redacted even when log redaction is enabled. Keep this in mind when switching between log levels.

You can permanently enable log redaction by adding the following to the configuration file:

```
security:
redactClientLogData: true
```

To enable log redaction at runtime, use the setParameter command as follows:

```
db.adminCommand(
   { setParameter: 1, redactClientLogData : true }
)
```

CHAPTER

TEN

DATA AT REST ENCRYPTION

• Encrypting Rollback Files

Data at rest encryption for the WiredTiger storage engine in *MongoDB* was introduced in MongoDB Enterprise version 3.2 to ensure that encrypted data files can be decrypted and read by parties with the decryption key.

Differences from Upstream

The data encryption at rest in *Percona Server for MongoDB* is introduced in version 3.6 to be compatible with data encryption at rest interface in *MongoDB*. In the current release of *Percona Server for MongoDB*, the data encryption at rest does not include support for Amazon AWS key management service. Instead, *Percona Server for MongoDB* is *integrated with HashiCorp Vault*. Starting with release 4.4.13-13, *Percona Server for MongoDB* supports the secure transfer of keys using *Key Management Interoperability Protocol (KMIP)*. This allows users to store encryption keys in their favorite KMIP-compatible key manager. when they set up encryption at rest.

Two types of keys are used for data at rest encryption:

- Database keys to encrypt data. They are stored internally, near the data that they encrypt.
- The master key to encrypt database keys. It is kept separately from the data and database keys and requires external management.

To manage the master key, use one of the supported key management options:

- Integration with an external key server (recommended). Percona Server for MongoDB is integrated with HashiCorp Vault for this purpose and supports the secure transfer of keys using Key Management Interoperability Protocol (KMIP).
- Local key management using a keyfile.

Note that you can use only one of the key management options at a time. However, you can switch from one management option to another (e.g. from a keyfile to HashiCorp Vault). Refer to *Migrating from Key File Encryption to HashiCorp Vault Encryption* section for details.

Important: You can only enable data at rest encryption and provide all encryption settings on an empty database, when you start the mongod instance for the first time. You cannot enable or disable encryption while the *Percona Server for MongoDB* server is already running and / or has some data. Nor can you change the effective encryption mode by simply restarting the server. Every time you restart the server, the encryption settings must be the same.

10.1 HashiCorp Vault Integration

Percona Server for MongoDB is integrated with HashiCorp Vault. HashiCorp Vault supports different secrets engines. *Percona Server for MongoDB* only supports the HashiCorp Vault back end with KV Secrets Engine - Version 2 (API) with versioning enabled.

See also:

Percona Blog: Using Vault to Store the Master Key for Data at Rest Encryption on Percona Server for MongoDB

HashiCorp Vault Documentation: How to configure the KV Engine

HashiCorp Vault Parameters

Command line	Config file	Туре	Description
vaultServerName	security.vault.serverName	string	The IP address of the Vault server
vaultPort	security.vault.port	int	The port on the Vault server
vaultTokenFile	security.vault.tokenFile	string	The path to the vault token file. The token file is used by <i>MongoDB</i> to access HashiCorp Vault. The vault token file consists of the raw vault token and does not include any additional strings or parameters. Example of a vault token file: s.uTrHtzsZnEE7KyHeA797CkWA
vaultSecret	security.vault.secret	string	The path to the vault secret. Every replica set member must have its own distinct vault secret. It is recommended to use different secret paths for every database node. Note that vault secrets path format must be: <vault_secret_mount>/data/ <custom_path> where: • <vault_secret_mount> is your Vault KV Secrets Engine; • data is the mandatory path prefix required by Version 2 API; • <custom_path> is your secrets path Example: secret_v2/data/psmdb-test/ <rul> -rs1-27017</rul></custom_path></vault_secret_mount></custom_path></vault_secret_mount>
vaultRotateMasterKey	secu- rity.vault.rotateMasterKey	switch	Enables master key rotation
vaultServerCAFile	secu-	string	The path to the TLS certificate file
	rity.vault.serverCAFile		
vaultDisableTLSForTest-	secu-	switch	Disables secure connection to
ing	rity.vault.disableTLSForTes	ting	HashiCorp Vault using SSL/TLS client certificates

Config file example

security:

enableEncryption: true

vault:

serverName: 127.0.0.1

port: 8200

tokenFile: /home/user/path/token

secret: secret/data/hello

During the first run of the *Percona Server for MongoDB*, the process generates a secure key and writes the key to the vault.

During the subsequent start, the server tries to read the master key from the vault. If the configured secret does not exist, vault responds with HTTP 404 error.

10.1.1 Namespaces

Namespaces are isolated environments in Vault that allow for separate secret key and policy management.

You can use Vault namespaces with *Percona Server for MongoDB*. Specify the namespace(s) for the security.vault. secret option value as follows:

```
<namespace>/secret/data/<secret_path>
```

For example, the path to secret keys for namespace test on the secrets engine secret will be test/secret/<my_secret_path>.

Note: You have the following options of how to target a particular namespace when configuring Vault:

1. Set the VAULT_NAMESPACE environment variable so that all subsequent commands are executed against that namespace. Use the following command to set the environment variable for the namespace test:

```
$ export VAULT_NAMESPACE=test
```

2. Provide the namespace with the -namespace flag in commands

See also:

HashiCorp Vault Documentation:

- Namespaces https://www.vaultproject.io/docs/enterprise/namespaces
- Secure Multi-Tenancy with Namespaces https://learn.hashicorp.com/tutorials/vault/namespaces

10.1.2 Key Rotation

Key rotation is replacing the old master key with a new one. This process helps to comply with regulatory requirements.

To rotate the keys for a single mongod instance, do the following:

- 1. Stop the mongod process
- 2. Add --vaultRotateMasterKey option via the command line or security.vault.rotateMasterKey to the config file.
- 3. Run the mongod process with the selected option, the process will perform the key rotation and exit.
- 4. Remove the selected option from the startup command or the config file.
- 5. Start mongod again.

Rotating the master key process also re-encrypts the keystore using the new master key. The new master key is stored in the vault. The entire dataset is not re-encrypted.

Key rotation in replica sets

Every mongod node in a replica set must have its own master key. The key rotation steps are the following:

- 1. Rotate the master key for the secondary nodes one by one.
- 2. Step down the primary and wait for another primary to be elected.
- 3. Rotate the master key for the previous primary node.

10.2 Local key management using a keyfile

The key file must contain a 32 character string encoded in base64. You can generate a random key and save it to a file by using the **openss1** command:

```
$ openssl rand -base64 32 > mongodb-keyfile
```

Then, as the owner of the mongod process, update the file permissions: only the owner should be able to read and modify this file. The effective permissions specified with the chmod command can be:

- 600 only the owner may read and modify the file
- 400 only the owner may read the file.

```
$ chmod 600 mongodb-keyfile
```

Enable the data encryption at rest in *Percona Server for MongoDB* by setting these options:

- --enableEncryption to enable data at rest encryption
- --encryptionKeyFile to specify the path to a file that contains the encryption key

```
$ mongod ... --enableEncryption --encryptionKeyFile <fileName>
```

By default, *Percona Server for MongoDB* uses the AES256-CBC cipher mode. If you want to use the AES256-GCM cipher mode, then use the encryptionCipherMode parameter to change it.

If mongod is started with the --relaxPermChecks option and the key file is owned by root, then mongod can read the file based on the group bit set accordingly. The effective key file permissions in this case are:

- 440 both the owner and the group can only read the file, or
- 640 only the owner can read and the change the file, the group can only read the file.

See also:

MongoDB Documentation: Configure Encryption https://docs.mongodb.com/manual/tutorial/configure-encryption/#local-key-management

Percona Blog: WiredTiger Encryption at Rest with Percona Server for MongoDB https://www.percona.com/blog/2018/11/01/wiredtiger-encryption-at-rest-percona-server-for-mongodb/

All these options can be specified in the configuration file:

```
security:
    enableEncryption: <boolean>
    encryptionCipherMode: <string>
    encryptionKeyFile: <string>
    relaxPermChecks: <boolean>
```

See also:

MongoDB Documentation: How to set options in a configuration file https://docs.mongodb.com/manual/reference/configuration-options/index.html#configuration-file

10.3 Migrating from Key File Encryption to HashiCorp Vault Encryption

The steps below describe how to migrate from the key file encryption to using HashiCorp Vault.

Note: This is a simple guideline and it should be used for testing purposes only. We recommend to use Percona Consulting Services to assist you with migration in production environment.

Assumptions

We assume that you have installed and configured the vault server and enabled the KV Secrets Engine as the secrets storage for it.

1. Stop mongod.

```
$ sudo systemctl stop mongod
```

2. Insert the key from keyfile into the HashiCorp Vault server to the desired secret path.

Note: Vault KV Secrets Engine uses different read and write secrets paths. To insert data to vault, specify the secret path without the data/prefix.

3. Edit the configuration file to provision the HashiCorp Vault configuration options instead of the key file encryption options.

```
security:
    enableEncryption: true
    vault:
        serverName: 10.0.2.15
        port: 8200
        secret: secret/data/dc/psmongodb1
        tokenFile: /etc/mongodb/token
        serverCAFile: /etc/mongodb/vault.crt
```

4. Start the mongod service

```
$ sudo systemctl start mongod
```

10.4 Using the Key Management Interoperability Protocol (KMIP)

Percona Server for MongoDB adds support for secure transfer of keys using the OASIS Key Management Interoperability Protocol (KMIP). The KMIP implementation was tested with the PyKMIP server and the HashiCorp Vault Enterprise KMIP Secrets Engine.

KMIP enables the communication between key management systems and the database server. KMIP provides the following benefits:

- Streamlines encryption key management
- Eliminates redundant key management processes

Starting with version 4.4.15-15, you can specify multiple KMIP servers for failover. On startup, *Percona Server for MongoDB* connects to the servers in the order listed and selects the one with which the connection is successful.

Starting with version 4.4.16-16, the kmipKeyIdentifier option is no longer mandatory. When left blank, the database server creates a key on the KMIP server and uses that for encryption. When you specify the identifier, the key with such an ID must exist on the keystore.

Percona Server for MongoDB cannot encrypt existing data. If there is data in place, see the steps how to encrypt existing data.

KMIP parameters

Option	Туре	Description					
kmipServestName The hostname or IP address of the KMIP server. As of version 4.4.15-15, multiple KMIP							
		servers are supported as the comma-separated list, e.g. kmip1.example.com,kmip2.					
		example.com					
kmipPort	num-	The port used to communicate with the KMIP server. When undefined, the default port 5696					
	ber	is used.					
kmipServ	kmipServextCARgi Tene path to the CA certificate file. CA file is used to validate secure client connection to the						
		KMIP server.					
kmipClienstCiengt ThecpatthFtolthe PEM file with the KMIP client private key and the certificate chain. The							
		database server uses this PEM file to authenticate the KMIP server.					
kmipKeyI	detmitnig	Expr ional starting with version 4.4.16-16. The identifier of the KMIP key. If the key does not					
		exist, the database server creates a key on the KMIP server with the specified identifier. When					
		you specify the identifier, the key with such an ID must exist on the key storage. You can only					
		use this setting for the first time you enable encryption.					
kmipRotate	kmipRotateMaschenKeyntrols master keys rotation. When enabled, generates the new master key version						
		and re-encrypts the keystore. Available as of version 4.4.14-14. Requires the unique					
		kmipKeyIdentifier for every mongod node.					
kmipClie	nsticieng	t If he catse Rouse word the KMIP client private key or certificate. Use this parameter only if the					
		KMIP client private key or certificate is encrypted. Available starting with version 4.4.15-15.					

10.5 Key rotation

Starting with release 4.4.14-14, the support for master key rotation is added. This enables users to comply with data security regulations when using KMIP.

10.6 Configuration

Considerations

Make sure you have obtained the root certificate, and the keypair for the KMIP server and the mongod client. For testing purposes you can use the OpenSSL to issue self-signed certificates. For production use we recommend you use the valid certificates issued by the key management appliance.

To enable data-at-rest encryption in *Percona Server for MongoDB* using KMIP, edit the /etc/mongod.conf configuration file as follows:

```
security:
    enableEncryption: true
    kmip:
        serverName: <kmip_server_name>
        port: 5696
        clientCertificateFile: </path/client_certificate.pem>
        serverCAFile: </path/ca.pem>
        keyIdentifier: <key_name>
```

Alternatively, you can start Percona Server for MongoDB using the command line as follows:

10.5. Key rotation 57

```
$ mongod --enableEncryption \
   --kmipServerName <kmip_servername> \
   --kmipPort 5696 \
   --kmipServerCAFile <path_to_ca_file> \
   --kmipClientCertificateFile <path_to_client_certificate> \
   --kmipKeyIdentifier <kmip_identifier>
```

Important Configuration Options

Percona Server for MongoDB supports the encryptionCipherMode option where you choose one of the following cipher modes:

- AES256-CBC
- AES256-GCM

By default, the AES256-CBC cipher mode is applied. The following example demonstrates how to apply the AES256-GCM cipher mode when starting the **mongod** service:

```
$ mongod ... --encryptionCipherMode AES256-GCM
```

See also:

MongoDB Documentation: encryptionCipherMode Option https://docs.mongodb.com/manual/reference/program/mongod/#cmdoption-mongod-encryptionciphermode

10.7 Encrypting Rollback Files

Starting from version 3.6, *Percona Server for MongoDB* also encrypts rollback files when data at rest encryption is enabled. To inspect the contents of these files, use **perconadecrypt**. This is a tool that you run from the command line as follows:

```
$ perconadecrypt --encryptionKeyFile FILE --inputPath FILE --outputPath FILE [--
→encryptionCipherMode MODE]
```

When decrypting, the cipher mode must match the cipher mode which was used for the encryption. By default, the --encryptionCipherMode option uses the AES256-CBC mode.

Parameters of perconadecrypt

Option	Purpose
-encryptionKeyFile	The path to the encryption key file
-encryptionCipher-	The cipher mode for decryption. The supported values are AES256-CBC or AES256-
Mode	GCM
-inputPath	The path to the encrypted rollback file
-outputPath	The path to save the decrypted rollback file

ADDITIONAL TEXT SEARCH ALGORITHM - NGRAM

The ngram text search algorithm is useful for searching text for a specific string of characters in a field of a collection. This feature can be used to find exact sub-string matches, which provides an alternative to parsing text from languages other than the list of European languages already supported by MongoDB Community's full text search engine. It may also turn out to be more convenient when working with the text where symbols like dash('-'), underscore('_'), or slash("/") are not token delimiters.

Unlike MongoDB full text search engine, *ngram* search algorithm uses only the following token delimiter characters that do not count as word characters in human languages:

- · Horizontal tab
- Vertical tab
- · Line feed
- Carriage return
- Space

The *ngram* text search is slower than MongoDB full text search.

11.1 Usage

To use *ngram*, create a text index on a collection setting the default_language parameter to **ngram**:

```
mongo > db.collection.createIndex({name:"text"}, {default_language: "ngram"})
```

ngram search algorithm treats special characters like individual terms. Therefore, you don't have to enclose the search string in escaped double quotes (\") to query the text index. For example, to search for documents that contain the date 2021-02-12, specify the following:

```
mongo > db.collection.find({ $text: { $search: "2021-02-12" } })
```

However, both *ngram* and MongoDB full text search engine treat words with the hyphen-minus – sign in front of them as negated (e.g. "-coffee") and exclude such words from the search results.

See also:

MongoDB documentation:

- · Text search
- · Text indexes
- \$text operator

N	Iore	in	forma	tion	about	ngram	imp	lementation:

 $\bullet\ https://github.com/percona/percona-server-mongodb/blob/v4.4/src/mongo/db/fts/ngram-tokenizer.md$

CHAPTER

TWELVE

\$BACKUPCURSOR AND \$BACKUPCURSOREXTEND AGGREGATION STAGES

\$backupCursor and \$backupCursorExtend aggregation stages expose the WiredTiger API which allows making consistent backups. Running these stages allows listing and freezing the files so you can copy them without the files being deleted or necessary parts within them being overwritten.

- \$backupCursor outputs the list of files and their size to copy.
- \$backupCursorExtend outputs the list of WiredTiger transaction log files that have been updated or newly added since the \$backupCursor was first run. Saving these files enables restoring the database to any arbitrary time between the \$backupCursor and \$backupCursorExtend execution times.

They are available in *Percona Server for MongoDB* starting with version 4.4.6-8.

Percona provides Percona Backup for MongoDB (PBM) – a light-weight open source solution for consistent backups and restores across sharded clusters. PBM relies on these aggregation stages for physical backups and restores. However, if you wish to develop your own backup application, this document describes the \$backupCursor and \$backupCursorExtend aggregation stages.

12.1 Usage

You can run these stages in any type of MongoDB deployment. If you need to back up a single node in a replica set, first run the \$backupCursor, then the \$backupCursorExtend and save the output files to the backup storage.

To make a consistent backup of a sharded cluster, run both aggregation stages on one node from each shard and the config server replica set. It can be either the primary or the secondary node. Note that since the secondary node may lag in syncing the data from the primary one, you will have to wait for the exact same time before running the \$backupCursorExtend.

Note that for standalone MongoDB node with disabled oplogs, you can only run the \$backupCursor aggregation stage.

12.1.1 Get a list of all files to copy with \$backupCursor

```
var bkCsr = db.getSiblingDB("admin").aggregate([{$backupCursor: {}}])
bkCsrMetadata = bkCsr.next().metadata
```

Sample output:

```
[
{
    metadata: {
        backupId: UUID("35c34101-0107-44cf-bdec-fad285e07534"),
        dbpath: '/var/lib/mongodb',
        oplogStart: { ts: Timestamp({ t: 1666631297, i: 1 }), t: Long("-1") },
        oplogEnd: { ts: Timestamp({ t: 1666631408, i: 1 }), t: Long("1") },
        checkpointTimestamp: Timestamp({ t: 1666631348, i: 1 })
    }
},
```

Store the metadata document somewhere, because you need to pass the backupId parameter from this document as the input parameter for the \$backupCursorExtend stage. Also you need the oplogEnd timestamp. Make sure that the \$backupCursor is complete on all shards in your cluster.

Note: Note that when running \$backupCursor in a standalone node deployment, oplogStart, oplogEnd, checkpointTimesatmp values may be absent. This is because standalone node deployments don't have oplogs.

12.1.2 Run \$backupCursorExtend to retrieve the WiredTiger transaction logs

Pass the backupId from the metadata document as the first parameter. For the timestamp parameter, use the maximum (latest) value among the oplogEnd timestamps from all shards and config server replica set. This will be the target time to restore.

Sample output:

```
{ "filename" : "/data/plain_rs/n1/data/journal/WiredTigerLog.0000000042" }
{ "filename" : "/data/plain_rs/n1/data/journal/WiredTigerLog.00000000043" }
{ "filename" : "/data/plain_rs/n1/data/journal/WiredTigerLog.00000000044" }
```

12.1.3 Loop the \$backupCursor

Prevent the backup cursor from closing on timeout (default -10 minutes). This is crucial since it prevents overwriting backup snapshot file blocks with new ones if the files take longer than 10 minutes to copy. Use the getMore command for this purpose.

12.1.4 Copy the files to the storage

Now you can copy the output of both aggregation stages to your backup storage.

After the backup is copied to the storage, terminate the getMore command and close the cursor.

Note: Save the timestamp that you passed for the \$backupCursorExtend stage somewhere since you will need it for the restore.

Based on the material from Percona blog

Based on the blog post: Experimental Feature: \$backupCursorExtend in Percona Server for MongoDB by Akira Kurogane

12.1. Usage 63

Percona Server for MongoDB 4.4 Documentation, Release 4.4.17-17						

Part IV

How to

CHAPTER

THIRTEEN

ENABLING AUTHENTICATION

By default, Percona Server for MongoDB does not restrict access to data and configuration.

Enabling authentication enforces users to identify themselves when accessing the database. This documents describes how to enable built-in authentication mechanism. *Percona Server for MongoDB* also supports the number of external authentication mechanisms. To learn more, refer to *Authentication*.

You can enable authentication either automatically or manually.

13.1 Automatic setup

To enable authentication and automatically set it up, run the /usr/bin/percona-server-mongodb-enable-auth. sh script as root or using sudo.

This script creates the dba user with the root role. The password is randomly generated and printed out in the output. Then the script restarts *Percona Server for MongoDB* with access control enabled. The dba user has full superuser privileges on the server. You can add other users with various roles depending on your needs.

For usage information, run the script with the -h option.

13.2 Manual setup

To enable access control manually:

1. Add the following lines to the configuration file:

```
security:
authorization: enabled
```

2. Run the following command on the admin database:

```
> db.createUser({user: 'USER', pwd: 'PASSWORD', roles: ['root'] });
```

3. Restart the mongod service:

```
$ systemctl restart mongod
```

4. Connect to the database as the newly created user:

```
$ mongo --port 27017 -u 'USER' -p 'PASSWORD' --authenticationDatabase "admin"
```

See also:

MongoDB Documentation: Enable Access Control https://docs.mongodb.com/v4.4/tutorial/enable-authentication/

SETTING UP LDAP AUTHENTICATION WITH SASL

This document describes an example configuration suitable only to test out the external authentication functionality in a non-production environment. Use common sense to adapt these guidelines to your production environment.

To learn more about how the authentication works, see LDAP authentication with SASL.

14.1 Environment setup and configuration

The following components are required:

- slapd: OpenLDAP server.
- libsasl2 version 2.1.25 or later.
- saslauthd: SASL Authentication Daemon (distinct from libsasl2).

The following steps will help you configure your environment:

- Configuring saslauthd
 - OpenLDAP server
 - Microsoft Windows Active Directory
- Sanity check
- Configuring libsasl2
- Configuring mongod Server
 - Create a root user
 - Enable external authentication
 - Add an external user to Percona Server for MongoDB

Assumptions

Before we move on to the configuration steps, we assume the following:

- 1. You have the LDAP server up and running and have configured users on it. The LDAP server is accessible to the server with *Percona Server for MongoDB* installed. This document focuses on OpenLDAP server. If you use Microsoft Windows Active Directory, refer to the *Microsoft Windows Active Directory* section for saslauthd configuration.
- 2. You must place these two servers behind a firewall as the communications between them will be in plain text.

 This is because the SASL mechanism of PLAIN can only be used when authenticating and credentials will be sent in plain text.
- 3. You have sudo privilege to the server with the *Percona Server for MongoDB* installed.

14.1.1 Configuring saslauthd

1. Install the SASL packages. Depending on your OS, use the following command:

RedHat and CentOS

\$ sudo yum install -y cyrus-sasl

Note: For *Percona Server for MongoDB* versions earlier than 4.0.26-21, 4.4.8-9, 4.2.16-17, also install the cyrus-sasl-plain package.

Debian and Ubuntu

\$ sudo apt install -y sasl2-bin

2. Configure SASL to use 1dap as the authentication mechanism.

Note: Back up the original configuration file before making changes.

RedHat and CentOS

Specify the 1dap value for the --MECH option using the following command:

\$ sudo sed -i -e s/^MECH=pam/MECH=ldap/g /etc/sysconfig/saslauthd

Alternatively, you can edit the /etc/sysconfig/saslauthd configuration file:

MECH=1dap

Debian and Ubuntu

Use the following commands to enable the saslauthd to auto-run on startup and to set the ldap value for the --MECHANISMS option:

```
$ sudo sed -i -e s/^MECH=pam/MECH=ldap/g /etc/sysconfig/saslauthdsudo sed -i -e s/^

MECHANISMS="pam"/MECHANISMS="ldap"/g /etc/default/saslauthd

$ sudo sed -i -e s/^START=no/START=yes/g /etc/default/saslauthd
```

Alternatively, you can edit the /etc/default/sysconfig/saslauthd configuration file:

```
START=yes
MECHANISMS="ldap"
```

3. Create the /etc/saslauthd.conf configuration file and specify the settings that saslauthd requires to connect to a local LDAP service:

OpenLDAP server

The following is the example configuration file. Note that the server address MUST match the OpenLDAP installation:

```
ldap_servers: ldap://localhost
ldap_mech: PLAIN
ldap_search_base: dc=example,dc=com
ldap_filter: (cn=%u)
ldap_bind_dn: cn=admin,dc=example,dc=com
ldap_password: secret
```

Note the LDAP password (ldap_password) and bind domain name (ldap_bind_dn). This allows the saslauthd service to connect to the LDAP service as admin. In production, this would not be the case; users should not store administrative passwords in unencrypted files.

Microsoft Windows Active Directory

In order for LDAP operations to be performed against a Windows Active Directory server, a user record must be created to perform the lookups.

The following example shows configuration parameters for saslauthd to communicate with an Active Directory server:

```
ldap_servers: ldap://localhost
ldap_mech: PLAIN
ldap_search_base: CN=Users,DC=example,DC=com
ldap_filter: (sAMAccountName=%u)
ldap_bind_dn: CN=ldapmgr,CN=Users,DC=<AD Domain>,DC=<AD TLD>
ldap_password: ld@pmgr_Pa55word
```

In order to determine and test the correct search base and filter for your Active Directory installation, the Microsoft LDP GUI Tool can be used to bind and search the LDAP-compatible directory.

4. Start the saslauthd process and set it to run at restart:

```
$ sudo systemctl start saslauthd
$ sudo systemctl enable saslauthd
```

5. Give write permissions to the /run/saslauthd folder for the mongod. Either change permissions to the /run/saslauthd folder:

```
$ sudo chmod 755 /run/saslauthd
```

Or add the mongod user to the sasl group:

```
$ sudo usermod -a -G sasl mongod
```

14.1.2 Sanity check

Verify that the saslauthd service can authenticate against the users created in the LDAP service:

```
$ testsaslauthd -u christian -p secret -f /var/run/saslauthd/mux
```

This should return 0:0K "Success". If it doesn't, then either the user name and password are not in the LDAP service, or sasaluthd is not configured properly.

14.1.3 Configuring libsasl2

The mongod also uses the SASL library for communications. To configure the SASL library, create a configuration file.

The configuration file **must** be named mongodb.conf and placed in a directory where libsasl2 can find and read it. libsasl2 is hard-coded to look in certain directories at build time. This location may be different depending on the installation method.

In the configuration file, specify the following:

```
pwcheck_method: saslauthd
```

 $saslauthd_path: \ /var/run/saslauthd/mux$

log_level: 5
mech_list: plain

The first two entries (pwcheck_method and saslauthd_path) are required for mongod to successfully use the saslauthd service. The log_level is optional but may help determine configuration errors.

See also:

SASL documentation:

14.1.4 Configuring mongod Server

The configuration consists of the following steps:

- Creating a user with the **root** privileges. This user is required to log in to *Percona Server for MongoDB* after the external authentication is enabled.
- Editing the configuration file to enable the external authentication

Create a root user

Create a user with the **root** privileges in the admin database. If you have already created this user, skip this step. Otherwise, run the following command to create the admin user:

```
> use admin
switched to db admin
> db.createUser({"user": "admin", "pwd": "$3cr3tP4ssw0rd", "roles": ["root"]})
Successfully added user: { "user" : "admin", "roles" : [ "root" ] }
```

Enable external authentication

Edit the etc/mongod.conf configuration file to enable the external authentication:

```
security:
   authorization: enabled

setParameter:
   authenticationMechanisms: PLAIN, SCRAM-SHA-1
```

Restart the mongod service:

```
$ sudo systemctl restart mongod
```

Add an external user to Percona Server for MongoDB

User authentication is done by mapping a user object on the LDAP server against a user created in the \$external database. Thus, at this step, you create the user in the \$external database and they inherit the roles and privileges. Note that the username must exactly match the name of the user object on the LDAP server.

Connect to *Percona Server for MongoDB* and authenticate as *the root user*.

Use the following command to add an external user to Percona Server for MongoDB:

```
> db.getSiblingDB("$external").createUser( {user : "christian", roles: [ {role: "read", ⊔ ⊔ db: "test"} ]} );
```

14.2 Authenticate as an external user in *Percona Server for MongoDB*

When running the mongo client, a user can authenticate against a given database using the following command:

```
> db.getSiblingDB("$external").auth({ mechanism:"PLAIN", user:"christian", pwd:"secret", user:"christian", user:"christia
```

Alternatively, a user can authenticate while connecting to Percona Server for MongoDB:

Based on the material from Percona Database Performance Blog

This section is based on the blog post Percona Server for MongoDB Authentication Using Active Directory by *Doug Duncan*:

SETTING UP LDAP AUTHENTICATION AND AUTHORIZATION USING NATIVELDAP

This document describes an example configuration of LDAP authentication and authorization using direct binding to an LDAP server (Native LDAP). We recommend testing this setup in a non-production environment first, before applying it in production.

15.1 Assumptions

- The setup of an LDAP server is out of scope of this document. We assume that you are familiar with the LDAP server schema.
- 2. You have the LDAP server up and running and it is accessible to the servers with Percona Server for MongoDB installed.
- 3. This document primarily focuses on OpenLDAP used as the LDAP server and the examples are given based on the OpenLDAP format. If you are using Active Directory, refer to the *Active Directory configuration* section.
- 4. You have the sudo privilege to the server with the Percona Server for MongoDB installed.

15.2 Prerequisites

- In this setup we use anonymous binds to the LDAP server. If your LDAP server disallows anonymous binds, create the user that *Percona Server for MongoDB* will use to connect to and query the LDAP server. Define this user's credentials for the security.ldap.bind.queryUser and security.ldap.bind.queryPassword parameters in the mongod.conf configuration file.
- In this setup, we use the following OpenLDAP groups:

dn: cn=testusers,dc=percona,dc=com

objectClass: groupOfNames

cn: testusers

member: cn=alice,dc=percona,dc=com

dn: cn=otherusers,dc=percona,dc=com

objectClass: groupOfNames

cn: otherusers

member: cn=bob,dc=percona,dc=com

15.3 Setup procedure

15.3.1 Configure TLS/SSL connection for *Percona Server for MongoDB*

By default, *Percona Server for MongoDB* establishes the TLS connection when binding to the LDAP server and thus, it requires access to the LDAP CA certificates. To make *Percona Server for MongoDB* aware of the certificates, do the following:

- 1. Place the certificate in the certs directory. The path to the certs directory is:
 - On Debian / Ubuntu: /etc/ssl/certs/
 - On RHEL / CentOS: /etc/openldap/certs/
- 2. Specify the path to the certificates in the ldap.conf file:

Debian / Ubuntu

```
tee -a /etc/openldap/ldap.conf <<EOF
TLS_CACERT /etc/ssl/certs/my_CA.crt
EOF</pre>
```

RHEL / CentOS

```
tee -a /etc/openldap/ldap.conf <<EOF
TLS_CACERT /etc/openldap/certs/my_CA.crt
EOF</pre>
```

15.3.2 Create roles for LDAP groups in Percona Server for MongoDB

Percona Server for MongoDB authorizes users based on LDAP group membership. For every group, you must create the role in the admin database with the name that exactly matches the DN of the LDAP group.

Percona Server for MongoDB maps the user's LDAP group to the roles and determines what role is assigned to the user. *Percona Server for MongoDB* then grants privileges defined by this role.

To create the roles, use the following command:

(continues on next page)

(continued from previous page)

```
roles: [ "read"]
}
)
```

15.3.3 Percona Server for MongoDB configuration

Access without username transformation

This section assumes that users connect to *Percona Server for MongoDB* by providing their LDAP DN as the username.

1. Edit the *Percona Server for MongoDB* configuration file (by default, /etc/mongod.conf) and specify the following configuration:

The {PROVIDED_USER} variable substitutes the provided username before authentication or username transformation takes place.

Replace ldap.example.com with the hostname of your LDAP server. In the LDAP query template, replace the domain controllers percona and com with those relevant to your organization.

2. Restart the mongod service:

```
$ sudo systemctl restart mongod
```

3. Test the access to Percona Server for MongoDB:

```
mongo -u "cn=alice,dc=percona,dc=com" -p "secretpwd" --authenticationDatabase '

→$external' --authenticationMechanism 'PLAIN'
```

Access with username transformation

If users connect to *Percona Server for MongoDB* with usernames that are not LDAP DN, you need to transform these usernames to be accepted by the LDAP server.

Using the --ldapUserToDNMapping configuration parameter allows you to do this. You specify the match pattern as a regexp to capture a username. Next, specify how to transform it - either to use a substitution value or to query the LDAP server for a username.

If you don't know what the substitution or LDAP query string should be, please consult with the LDAP administrators to figure this out.

Note that you can use only the query or the substitution stage, the combination of two is not allowed.

Substitution

1. Edit the *Percona Server for MongoDB* configuration file (by default, /etc/mongod.conf) and specify the userToDNMapping parameter:

```
security:
 authorization: "enabled"
 ldap:
   servers: "ldap.example.com"
   transportSecurity: tls
   authz:
      queryTemplate: "dc=percona,dc=com??sub?(&
userToDNMapping: >-
         Ε
          {
            match: ([^@]+)@percona\.com",
            substitution: "CN={0},DC=percona,DC=com"
          }
         ]
setParameter:
 authenticationMechanisms: "PLAIN"
```

The {USER} variable substitutes the username transformed during the userToDNMapping stage.

Modify the given example configuration to match your deployment.

2. Restart the mongod service:

```
$ sudo systemctl restart mongod
```

3. Test the access to Percona Server for MongoDB:

```
mongo -u "alice@percona.com" -p "secretpwd" --authenticationDatabase '

⇒$external' --authenticationMechanism 'PLAIN'
```

LDAP query

1. Edit the *Percona Server for MongoDB* configuration file (by default, /etc/mongod.conf) and specify userToDNMapping parameter:

(continues on next page)

(continued from previous page)

The {USER} variable substitutes the username transformed during the userToDNMapping stage.

Modify the given example configuration to match your deployment, For example, replace 1dap. example.com with the hostname of your LDAP server. Replace the domain controllers (DC) percona and com with those relevant to your organization. Depending on your LDAP schema, further modifications of the LDAP query may be required.

2. Restart the mongod service:

```
$ sudo systemctl restart mongod
```

3. Test the access to Percona Server for MongoDB:

15.3.4 Active Directory configuration

Microsoft Active Directory uses a different schema for user and group definition. To illustrate *Percona Server for MongoDB* configuration, we will use the following AD (Active Directory) users:

```
dn:CN=alice,CN=Users,DC=testusers,DC=percona,DC=com
userPrincipalName: alice@testusers.percona.com
memberOf: CN=testusers,CN=Users,DC=percona,DC=com

dn:CN=bob,CN=Users,DC=otherusers,DC=percona,DC=com
userPrincipalName: bob@otherusers.percona.com
memberOf: CN=otherusers,CN=Users,DC=percona,DC=com
```

The following are respective AD groups:

```
dn:CN=testusers,CN=Users,DC=percona,DC=com
member:CN=alice,CN=Users,DC=testusers,DC=example,DC=com
dn:CN=otherusers,CN=Users,DC=percona,DC=com
member:CN=bob,CN=Users,DC=otherusers,DC=example,DC=com
```

Use one of the given *Percona Server for MongoDB* configurations for user authentication and authorization in Active Directory:

No username transformation

1. Edit the mongod configuration file:

2. Restart the mongod service:

```
$ sudo systemctl restart mongod
```

3. Test the access to Percona Server for MongoDB:

```
mongo -u "CN=alice,CN=Users,DC=testusers,DC=percona,DC=com" -p "secretpwd" ---authenticationDatabase '$external' --authenticationMechanism 'PLAIN'
```

Username substitution

1. Edit the mongod configuration file:

2. Restart the mongod service:

```
$ sudo systemctl restart mongod
```

3. Test the access to Percona Server for MongoDB:

```
mongo -u "alice@percona.com" -p "secretpwd" --authenticationDatabase '

⇒$external' --authenticationMechanism 'PLAIN'
```

LDAP query

1. Edit the mongod configuration file:

2. Restart the mongod service:

```
$ sudo systemctl restart mongod
```

3. Test the access to Percona Server for MongoDB:

```
mongo -u "alice" -p "secretpwd" --authenticationDatabase '$external' --

→authenticationMechanism 'PLAIN'
```

Modify one of this example configuration to match your deployment.

Based on the material from Percona Database Performance Blog

This document is based on the following blog posts:

- Percona Server for MongoDB LDAP Enhancements: User-to-DN Mapping by Igor Solodovnikov
- · Authenticate Percona Server for MongoDB Users via Native LDAP by Ivan Groenewold

Percona Server for MongoDB 4.4 Documentation, Release 4.4.17-17						

SET UP X.509 AUTHENTICATION AND LDAP AUTHORIZATION

x.509 certificate authentication is one of the supported authentication mechanisms in *Percona Server for MongoDB*. It is compatible with *LDAP authorization* to enable you to control user access and operations in your database environment.

This document provides the steps on how to configure and use x.509 certificates for authentication in *Percona Server for MongoDB* and authorize users in the LDAP server.

16.1 Considerations

- 1. For testing purposes, in this tutorial we use OpenSSL to issue self-signed certificates. For production use, we recommend using certificates issued and signed by the CA in *Percona Server for MongoDB*. Client certificates must meet the client certificate requirements.
- 2. The setup of the LDAP server and the configuration of the LDAP schema is out of scope of this document. We assume that you have the LDAP server up and running and accessible to *Percona Server for MongoDB*.

16.2 Setup procedure

16.2.1 Issue certificates

1. Create a directory to store the certificates. For example, /var/lib/mongocerts.

```
$ sudo mkdir -p /var/lib/mongocerts
```

2. Grant access to the mongod user to this directory:

```
$ sudo chown mongod:mongod /var/lib/mongocerts
```

Generate the root Certificate Authority certificate

The root Certificate Authority certificate will be used to sign the SSL certificates.

Run the following command and in the -subj flag, provide the details about your organization:

- C Country Name (2 letter code);
- ST State or Province Name (full name);
- L Locality Name (city);
- O Organization Name (company);

• CN - Common Name (your name or your server's hostname).

Generate server certificate

- 1. Create the server certificate request and key. In the -subj flag, provide the details about your organization:
 - C Country Name (2 letter code);
 - ST State or Province Name (full name);
 - L Locality Name (city);
 - O Organization Name (company);
 - CN Common Name (your name or your server's hostname) .

```
$ sudo openssl req -nodes -newkey rsa:4096 -keyout server.key -out server.csr -subj -\"/C=US/ST=California/L=SanFrancisco/0=Percona/OU=server/CN=localhost"
```

2. Sign the server certificate request with the root CA certificate:

```
$ sudo openssl x509 -req -in server.csr -CA ca.crt -CAkey ca.key -set_serial 01 -

→out server.crt
```

3. Combine the server certificate and key to create a certificate key file. Run this command as the root user:

```
$ cat server.key server.crt > server.pem
```

Generate client certificates

1. Generate client certificate request and key. In the -subj flag, specify the information about clients in the DN format.

2. Sign the client certificate request with the root CA certificate.

```
$ openssl x509 -req -in client.csr -CA ca.crt -CAkey ca.key -set_serial 02 -out 

→client.crt
```

3. Combine the client certificate and key to create a certificate key file.

```
$ cat client.key client.crt > client.pem
```

16.2.2 Set up the LDAP server

The setup of the LDAP server is out of scope of this document. Please work with your LDAP administrators to set up the LDAP server and configure the LDAP schema.

16.2.3 Configure mongod server

The configuration consists of the following steps:

- Creating a role that matches the user group on the LDAP server
- Editing the configuration file to enable the x.509 authentication

Note: When you use x.509 authentication with LDAP authorization, you don't need to create users in the **\$external** database. User management is done on the LDAP server so when a client connects to the database, they are authenticated and authorized through the LDAP server.

Create roles

At this step, create the roles in the admin database with the names that exactly match the names of the user groups on the LDAP server. These roles are used for user *LDAP authorization* in *Percona Server for MongoDB*.

In our example, we create the role *cn=otherusers,dc=percona,dc=com* that has the corresponding LDAP group.

Output:

Enable x.509 authentication

1. Stop the mongod service

```
$ sudo systemctl stop mongod
```

2. Edit the /etc/mongod.conf configuration file.

```
port: 27017
 bindIp: 127.0.0.1
 tls:
   mode: requireTLS
   certificateKeyFile: /var/lib/mongocerts/server.pem
   CAFile: /var/lib/mongocerts/ca.crt
security:
 authorization: enabled
 ldap:
    servers: "ldap.example.com"
    transportSecurity: none
    authz:
      queryTemplate: "dc=percona,dc=com??sub?(&(objectClass=groupOfNames)(member=
→{USER}))"
setParameter:
  authenticationMechanisms: PLAIN, MONGODB-X509
```

Replace ldap.example.com with the hostname of your LDAP server. In the LDAP query template, replace the domain controllers percona and com with those relevant to your organization.

3. Start the mongod service

```
$ sudo systemctl start mongod
```

16.2.4 Authenticate with the x.509 certificate

To test the authentication, connect to Percona Server for MongoDB using the following command:

```
$ mongo --host localhost --tls --tlsCAFile /var/lib/mongocerts/ca.crt --

→tlsCertificateKeyFile <path_to_client_certificate>/client.pem --

→authenticationMechanism MONGODB-X509 --authenticationDatabase='$external'
```

The result should look like the following:

(continues on next page)

(continued from previous page)

```
],
             "authenticatedUserRoles" : [
                     {
                              "role" : "cn=otherreaders,dc=percona,dc=com",
                             "db" : "admin"
                     },
                     {
                             "role" : "clusterAdmin",
                             "db" : "admin"
                     },
                     {
                             "role" : "userAdminAnyDatabase",
                             "db" : "admin"
                     },
                     {
                             "role" : "clusterManager",
                             "db" : "admin"
                     },
                     {
                             "role" : "clusterMonitor",
                              "db" : "admin"
                     }
             ]
     },
     "ok" : 1
}
```

Percona Server for MongoDB 4.4 Documentation, Release 4.4.17-17	

CHAPTER

SEVENTEEN

SETTING UP KERBEROS AUTHENTICATION

This document provides configuration steps for setting up Kerberos Authentication in Percona Server for MongoDB.

17.1 Assumptions

The setup of the Kerberos server itself is out of scope of this document. Please refer to the Kerberos documentation for the installation and configuration steps relevant to your operation system.

We assume that you have successfully completed the following steps:

- · Installed and configured the Kerberos server
- · Added necessary realms
- · Added service, admin and user principals
- Configured the A and PTR DNS records for every host running mongod instance to resolve the hostnames onto Kerberos realm.

See also:

MongoDB Documentation: Kerberos Authentication

17.2 Add user principals to Percona Server for MongoDB

To get authenticated, users must exist both in the Kerberos and *Percona Server for MongoDB* servers with exactly matching names.

After you defined the user principals in the Kerberos server, add them to the \$external database in *Percona Server* for *MongoDB* and assigned required roles:

```
use $external
db.createUser({user: "demo@PERCONATEST.COM",roles: [{role: "read", db: "admin"}]})
```

Replace demo@PERCONATEST.COM with your username and Kerberos realm.

17.3 Configure Kerberos keytab files

A keytab file stores the authentication keys for a service principal representing a mongod instance to access the Kerberos admin server.

After you have added the service principal to the Kerberos admin server, the entry for this principal is added to the /etc/krb5.keytab keytab file.

The mongod server must have access to the keytab file to authenticate. To keep the keytab file secure, restrict the access to it only for the user running the mongod process.

1. Stop the mongod service

\$ sudo systemctl stop mongod

2. Generate the keytab file or get a copy of it if you generated the keytab file on another host. Save the keyfile under a separate path (e.g. /etc/mongodb.keytab)

\$ cp /etc/krb5.keytab /etc/mongodb.keytab

3. Change the ownership to the keytab file

\$ sudo chown mongod:mongod /etc/mongodb.keytab

4. Set the KRB5_KTNAME variable in the environment file for the mongod process.

On Debian and Ubuntu

Edit the environment file at the path /etc/default/mongod and specify the KRB5_KTNAME variable:

KRB5_KTNAME=/etc/mongodb.keytab

If you have a different path to the keytab file, specify it accordingly.

On RHEL and derivatives

Edit the environment file at the path /etc/sysconfig/mongod and specify the KRB5_KTNAME variable:

KRB5_KTNAME=/etc/mongodb.keytab

If you have a different path to the keytab file, specify it accordingly.

5. Restart the mongod service

\$ sudo systemctl start mongod

17.4 Percona Server for MongoDB configuration

Enable external authentication in *Percona Server for MongoDB* configuration. Edit the etc/mongod.conf configuration file and specify the following configuration:

```
security:
   authorization: "enabled"

setParameter:
   authenticationMechanisms: GSSAPI
```

Restart the mongod service to apply the configuration:

```
$ sudo systemctl start mongod
```

17.5 Test the access to Percona Server for MongoDB

1. Obtain the Kerberos ticket for the user using the kinit command and specify the user password:

```
$ kinit demo
Password for demo@PERCONATEST.COM:
```

2. Check the user ticket:

3. Connect to Percona Server for MongoDB:

The result should look like the following:

(continues on next page)

(continued from previous page)

```
"ok" : 1
}
```

CHAPTER

EIGHTEEN

PERCONA SERVER FOR MONGODB PARAMETER TUNING GUIDE

Percona Server for MongoDB includes several parameters that can be changed in one of the following ways:

• The setParameter admonitions in the configuration file for persistent changes in production:

```
setParameter:
   cursorTimeoutMillis: <int>
   failIndexKeyTooLong: <boolean>
   internalQueryPlannerEnableIndexIntersection: <boolean>
   ttlMonitorEnabled: <boolean>
   ttlMonitorSleepSecs: <int>
```

• The --setParameter option arguments when running the mongod process for development or testing purposes:

```
$ mongod \
   --setParameter cursorTimeoutMillis=<int> \
   --setParameter failIndexKeyTooLong=<boolean> \
   --setParameter internalQueryPlannerEnableIndexIntersection=<boolean> \
   --setParameter ttlMonitorEnabled=<boolean> \
   --setParameter ttlMonitorSleepSecs=<int>
```

• The setParameter command on the admin database to make changes at runtime:

18.1 Parameters

18.1.1 cursorTimeoutMillis

```
Value Type integer

Default 600000 (ten minutes)
```

Sets the duration of time after which idle query cursors are removed from memory.

18.1.2 failIndexKeyTooLong

Value Type boolean

Default true

Versions of MongoDB prior to 2.6 would insert and update documents even if an index key was too long. The documents would not be included in the index. Newer versions of MongoDB ignore documents with long index key. By setting this value to false, the old behavior is enabled.

18.1.3 internalQueryPlannerEnableIndexIntersection

Value Type boolean

Default true

Due to changes introduced in MongoDB 2.6.4, some queries that reference multiple indexed fields, where one field matches no documents, may choose a non-optimal single-index plan. Setting this value to false will enable the old behavior and select the index intersection plan.

18.1.4 ttlMonitorEnabled

Value Type boolean

Default true

If this option is set to false, the worker thread that monitors TTL Indexes and removes old documents will be disabled.

18.1.5 ttlMonitorSleepSecs

Value Type integer

Default 60 (one minute)

Defines the number of seconds to wait between checking TTL Indexes for old documents and removing them.

UPGRADING PERCONA SERVER FOR MONGODB

An in-place upgrade is done by keeping the existing data in the server. It involves changing out the MongoDB binaries. Generally speaking, the upgrade steps include:

- 1. Stopping the mongod service
- 2. Removing the old binaries
- 3. Installing the new server version binaries
- 4. Restarting the mongod service with the same dbpath data directory.

An in-place upgrade is suitable for most environments except the ones that use ephemeral storage and/or host addresses.

This document provides upgrade instructions for the following use cases:

- Upgrading from MongoDB 4.4 Community Edition;
- Minor upgrade of Percona Server for MongoDB

19.1 Upgrading from MongoDB 4.4 Community Edition

Note: MongoDB creates a user that belongs to two groups, which is a potential security risk. This is fixed in *Percona Server for MongoDB*: the user is included only in the mongod group. To avoid problems with current MongoDB setups, existing user group membership is not changed when you migrate to *Percona Server for MongoDB*. Instead, a new mongod user is created during installation, and it belongs to the mongod group.

This section describes an in-place upgrade of a mongod instance. If you are using data at rest encryption, refer to the *Upgrading to Percona Server for MongoDB with data at rest encryption enabled* section.

Prerequisites

19.1.1 Prerequisites

Before you start the upgrade, update the MongoDB configuration file (/etc/mongod.conf) to contain the following settings.

```
processManagement:
   fork: true
   pidFilePath: /var/run/mongod.pid
```

Troubleshooting tip: The pidFilePath setting in mongod.conf must match the PIDFile option in the systemd mongod service unit. Otherwise, the service will kill the mongod process after a timeout.

Warning: Before starting the upgrade, we recommend to perform a full backup of your data.

Upgrading on Debian or Ubuntu

1. Stop the mongod service:

```
$ sudo systemctl stop mongod
```

2. Check for installed packages:

```
$ sudo dpkg -1 | grep mongod
```

Output

ii	mongodb-org	4.4.0	amd64	MongoDB document-oriented_				
⊶d	→database system (metapackage)							
ii	mongodb-org-mongos	4.4.0	amd64	MongoDB sharded cluster query∟				
∽r	-→router							
ii	mongodb-org-server	4.4.0	amd64	MongoDB database server				
ii	mongodb-org-shell	4.4.0	amd64	MongoDB shell client				
ii	mongodb-org-tools	4.4.0	amd64	MongoDB tools				

3. Remove the installed packages:

```
$ apt remove mongodb-org mongodb-org-mongos mongodb-org-server \
$ mongodb-org-shell mongodb-org-tools
```

4. Remove log files:

```
$ sudo rm -r /var/log/mongodb
```

- 5. Install Percona Server for MongoDB using apt.
- 6. Verify that the configuration file includes the correct options. For example, *Percona Server for MongoDB* stores data files in /var/lib/mongodb by default. If you used another dbPath data directory, edit the configuration file accordingly
- 7. Start the mongod service:

```
$ sudo systemctl mongod start
```

Upgrading on Red Hat Enterprise Linux or CentOS

1. Stop the mongod service:

```
$ sudo systemctl stop mongod
```

2. Check for installed packages:

```
$ sudo rpm -qa | grep mongo
```

Output

```
mongodb-org-mongos-4.4.0-1.el6.x86_64

mongodb-org-shell-4.4.0-1.el6.x86_64

mongodb-org-server-4.4.0-1.el6.x86_64

mongodb-org-tools-4.4.0-1.el6.x86_64

mongodb-org-4.4.0-1.el6.x86_64
```

3. Remove the installed packages:

```
$ yum remove \
mongodb-org-mongos-4.4.0-1.el6.x86_64 \
mongodb-org-shell-4.4.0-1.el6.x86_64 \
mongodb-org-server-4.4.0-1.el6.x86_64 \
mongodb-org-tools-4.4.0-1.el6.x86_64 \
mongodb-org-4.4.0-1.el6.x86_64 \
```

4. Remove log files:

```
$ sudo rm -r /var/log/mongodb
```

5. Install Percona Server for MongoDB using yum.

Note: When you remove old packages, your existing configuration file is saved as /etc/mongod.conf.rpmsave. If you want to use this configuration with the new version, replace the default /etc/mongod.conf file. For example, existing data may not be compatible with the default WiredTiger storage engine.

Start the mongod service:

```
$ sudo systemctl start mongod
```

To upgrade a replica set or a sharded cluster, use the *rolling restart* method. It allows you to perform the upgrade with minimum downtime. You upgrade the nodes one by one, while the whole cluster / replica set remains operational.

See also:

MongoDB Documentation:

- Upgrade a Replica Set
- Upgrade a Sharded Cluster

19.2 Minor upgrade of Percona Server for MongoDB

To upgrade *Percona Server for MongoDB* to the latest version, follow these steps:

1. Stop the *mongod* service:

```
$ sudo systemctl stop mongod
```

2. Install the latest version packages. Use the command relevant to your operating system.

On Debian and Ubuntu: \$ sudo apt install percona-server-mongodb On Red Hat Enterprise Linux or CentOS: \$ sudo yum install percona-server-mongodb

3. Start the *mongod* service:

```
$ sudo systemctl start mongod
```

To upgrade a replica set or a sharded cluster, use the *rolling restart* method. It allows you to perform the upgrade with minimum downtime. You upgrade the nodes one by one, while the whole cluster / replica set remains operational.

19.3 Upgrading to *Percona Server for MongoDB* with data at rest encryption enabled

Steps to upgrade from MongoDB 4.4 Community Edition with data encryption enabled to *Percona Server for MongoDB* are different. mongod requires an empty dbPath data directory because it cannot encrypt data files in place. It must receive data from other replica set members during the initial sync. Please refer to the *Switching storage engines* for more information on migration of encrypted data. Contact us for working at the detailed migration steps, if further assistance is needed.

UPGRADING FROM PERCONA SERVER FOR MONGODB 4.2 TO 4.4

To upgrade *Percona Server for MongoDB* to version 4.4, you must be running version 4.2. Upgrades from earlier versions are not supported.

Before upgrading your production *Percona Server for MongoDB* deployments, test all your applications in a testing environment to make sure they are compatible with the new version. For more information, see Compatibility Changes in MongoDB 4.4

The general procedure for performing an in-place upgrade (where your existing data and configuration files are preserved) includes the following steps:

- 1. Stop the mongod instance
- 2. Enable Percona repository for Percona Server for MongoDB 4.4
- 3. Install new packages. Old packages are considered obsolete and automatically removed
- 4. Start the mongod instance

\$ sudo systemctl start mongod

It is recommended to upgrade *Percona Server for MongoDB* from official Percona repositories using the corresponding package manager for your system. For more information, see *Installing Percona Server for MongoDB*.

Warning: Perform a full backup of your data and configuration files before upgrading.

Upgrading on Debian or Ubuntu

1. Stop the mongod instance:

\$ sudo systemctl stop mongod

2. Enable Percona repository for Percona Server for MongoDB 4.4:

\$ sudo percona-release enable psmdb-44

3. Update the local cache:

\$ sudo apt update

4. Install Percona Server for MongoDB 4.4 packages:

\$ sudo apt install percona-server-mongodb

5. Start the mongod instance:

For more information, see Installing Percona Server for MongoDB on Debian and Ubuntu.

Upgrading on RHEL and CentOS

1. Stop the mongod instance:

```
$ sudo systemctl stop mongod
```

2. Enable Percona repository for *Percona Server for MongoDB* 4.4:

```
$ sudo percona-release enable psmdb-44
```

- 3. Install *Percona Server for MongoDB* 4.4 packages:
- 4. Start the mongod instance:

```
$ sudo systemctl start mongod
```

For more information, see Installing Percona Server for MongoDB on Red Hat Enterprise Linux and CentOS.

After the upgrade, *Percona Server for MongoDB* is started with the feature set of 4.2 version. Assuming that your applications are compatible with the new version, enable 4.4 version features. Run the following command against the admin database:

```
db.adminCommand( { setFeatureCompatibilityVersion: "4.4" } )
```

See also:

MongoDB Documentation:

- Upgrade a Standalone
- Upgrade a Replica Set
- Upgrade a Sharded Cluster

UNINSTALLING PERCONA SERVER FOR MONGODB

To completely remove *Percona Server for MongoDB* you need to remove all the installed packages, data and configuration files. If you need the data, consider making a backup before uninstalling Percona Server for MongoDB.

Follow the instructions, relevant to your operating system:

Uninstall on Debian and Ubuntu

You can remove *Percona Server for MongoDB* packages with one of the following commands:

- apt remove will only remove the packages and leave the configuration and data files.
- apt purge will remove all the packages with configuration files and data.

Choose which command better suits you depending on your needs.

1. Stop the **mongod** server:

```
$ sudo systemctl stop mongod
```

- 2. Remove the packages. There are two options.
 - To keep the configuration and data files, run:

```
$ sudo apt remove percona-server-mongodb*
```

• To delete both the configuration and data files and the packages, run:

```
$ sudo apt purge percona-server-mongodb*
```

Uninstall on Red Hat Enterprise Linux and CentOS

 $1. \ \, Stop \ the \ Percona \ Server \ for \ MongoDB \ service:$

```
$ sudo systemctl stop mongod
```

2. Remove the packages:

```
$ sudo yum remove percona-server-mongodb*
```

3. Remove the data and configuration files:

```
$ sudo rm -rf /var/lib/mongodb
$ sudo rm -f /etc/mongod.conf
```

Warning: This will remove all the packages and delete all the data files (databases, tables, logs, etc.). You might want to back up your data before doing this in case you need the data later.

Part V Release Notes

PERCONA SERVER FOR MONGODB 4.4 RELEASE NOTES

22.1 Percona Server for MongoDB 4.4.17-17 (2022-11-10)

Date November 10, 2022

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.17-17 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.17 Community Edition. It supports MongoDB 4.4.17 protocols and drivers.

22.1.1 Release Highlights

- Data-at-rest encryption using the Key Management Interoperability Protocol (KMIP) is generally available enabling you to use it in your production environment
- \$backupCursor and \$backupCursorExtend aggregation stages functionality is generally available, enabling your application developers to use it for building custom backup solutions.

Note: Percona provides Percona Backup for MongoDB - the open source tool for consistent backups and restores in MongoDB sharded clusters.

• Fixed security vulnerability CVE-2022-3602 for *Percona Server for MongoDB* 4.4.15-15 and higher installed from tarballs on Ubuntu 22.04.

The bug fixes, provided by MongoDB and included in Percona Server for MongoDB, are the following:

- SERVER-68925 Detect and resolve table logging inconsistencies for WiredTiger tables at startup
- SERVER-56127 Fixed retryable writes on update and delete commands to not execute more than once if chunk is migrated and shard key pattern uses nested fields
- SERVER-64142 Verify that any unique indexes are prefixed by the new shard key pattern
- SERVER-65382 Prevent the use of clientReadable function in AutoSplitVector when reordering shard key fields
- WT-9870 Fixed the global time window state before performing the rollback to stable operation by updating the pinned timestamp as part of the transaction setup.

Find the full list of changes in the MongoDB 4.4.17 Community Edition release notes

22.1.2 New Features

• PSMDB-776: Align Docker container with upstream by adding missing mongodb-tools utilities (Thanks to Denys Holius for reporting this issue)

22.1.3 Improvements

• PSMDB-1116: Use proper exit code and logging severity for successful master key rotation

22.1.4 Bugs Fixed

- PSMDB-1172: Fixed CVE-2022-3602 by updating libssl for Ubuntu 22.04 tarball
- PSMDB-1134: Prevent the server crash by ensuring the backup cursor is closed before the server shutdown
- PSMDB-1130: Improve handling of the missing encryption key during KMIP key rotation
- PSMDB-1129: Prevent *Percona Server for MongoDB* from starting if the configured encryption key doesn't match the one used for data encryption
- PSMDB-1082: Improve error handling for *Percona Server for MongoDB* when the wrong encryption key is used

22.2 Percona Server for MongoDB 4.4.16-16 (2022-08-30)

Date August 30, 2022

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.16-16 is an enhanced, source-available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.16 Community Edition. It supports MongoDB 4.4.16 protocols and drivers.

Warning: Take caution when upgrading from earlier versions of v4.4.x to later versions of 4.4 or on to v5.0. See SERVER-68511 for more details.

22.2.1 Release Highlights

- SERVER-67302 Fixed the server crash with the CLOCK_REALTIME set to forward by making the linearizable reads robust to primary catch-up and simultaneous stepdown.
- SERVER-61321, SERVER-60607 Improved handling of large/NaN (Not a Number) values for text index and geo index version.
- SERVER-66418 Fixed the issue with bad projection created during dependency analysis due to string order assumption. It resulted in the PathCollision error. The issue is fixed by improving dependency analysis for projections by folding dependencies into ancestor dependencies where possible.
- WT-9096 Fixed the wrong key/value returning during search near when the key doesn't exist.
- SERVER-63243 This bug fix adjusts the functioning of the range-deleter to prevent the balancer from getting blocked, hung, or ranges being scheduled behind other ranges.
- SERVER-67492 Failed chunk migrations can lead to recipient shard having different config.transactions records between primaries and secondaries inconsistent data.

SERVER-60958 - This fix avoids server hang in chunk migration when a step-down occurs.

Find the full list of changes in the MongoDB 4.4.16 Community Edition release notes.

22.2.2 Improvements

• PSMDB-1046: Make the kmipKeyIdentifier option not mandatory

Note: If you have configured data at rest encryption using the KMIP server and wish to upgrade *Percona Server for MongoDB*, go through the encrypting existing data steps during the upgrade as follows:

- 1. Prepare the server
- 2. Upgrade Percona Server for MongoDB
- 3. Enable encryption and initiate the data synchronization.

22.2.3 Bugs Fixed

• PSMDB-1119: Fixed the issue with backup cursor not opening if data-at-rest encryption is enabled

22.2.4 Packaging Notes

Debian 9 ("Stretch") is no longer supported.

See also:

Percona Blog: OS Platform End of Life (EOL) Announcement for Debian Linux 9

22.3 Percona Server for MongoDB 4.4.15-15 (2022-07-19)

Date July 19, 2022

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.15-15 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.15 Community Edition. It supports MongoDB 4.4.15 protocols and drivers.

22.3.1 Release Highlights

- Support of *multiple KMIP servers* adds failover to your data-at-rest encryption setup.
- Allow users to set KMIP client certificate password through a flag to simplify the migration from MongoDB Enterprise to *Percona Server for MongoDB*.

Other improvements and bug fixes introduced by MongoDB and included in Percona Server for MongoDB are the following:

• SERVER-66433 - Backported the check for user errors in case deadline on the migration destination manager is hit while waiting for a range to be cleared up. This prevents the balancer from getting blocked.

- SERVER-65821 Fixed the deadlock situation in cross shard transactions that could occur when the FCV (Feature Compatibility Version) was set after the "prepared" state of the transactions. That ended up with both the the setFCV thread and the *TransactionCoordinator* hung.
- SERVER-65131 This is a v6.0 backport fix to v4.4 that disables opportunistic read targeting (except for specified hedged reads) in order to prevent possible performance problems associated with uneven read distribution across the secondaries.
- SERVER-54900 Fixed an issue where competing/blocking network calls to the sync source could prevent selecting a new sync-source. This is resolved by canceling the ASIO session when SSL handshake times out.

Find the full list of changes in the MongoDB 4.4.15 Community Edition Release notes.

22.3.2 Supported versions

Percona Server for MongoDB is now available on Ubuntu 22.04 (Jammy Jellyfish).

22.3.3 Improvements

- PSMDB-1045: Add support for several KMIP servers
- PSMDB-1054: Add the ability to specify the password for the KMIP client keys and certificates to simplify migration from MongoDB Enterprise.

22.4 Percona Server for MongoDB 4.4.14-14 (2022-05-25)

Date May 25, 2022

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.14-14 is an enhanced, source-available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.14 Community Edition. It supports MongoDB 4.4.14 protocols and drivers.

22.4.1 Release Highlights

Percona Server for MongoDB now supports the master key rotation for data encrypted using the *Keys Management Interoperability Protocol (KMIP)* protocol (tech preview feature). This improvement allows users to comply with regulatory standards for data security.

Other improvements and bug fixes introduced by MongoDB and included in *Percona Server for MongoDB* are the following:

• WT-8924 - Fixed a bug that causes replication to stall on secondary replica set members in a sharded cluster handling cross-shard transactions. It is caused by WiredTger to erroneously return a write conflict when deciding if an update to a record is allowed. If MongoDB decides to retry the operation that caused the conflict in WiredTiger, it will enter an indefinite retry loop, and oplog application will stall on secondary nodes.

If this bug is hit, the secondary nodes will experience indefinite growth in replication lag. Restart the secondary nodes to resume replication.

This bug affects MongoDB 4.4.10 through 4.4.13 and 5.0.4 to 5.0.7.

Update to the latest version to avoid the secondary replication stall and lag issues.

• SERVER-60412 - Check if the host has cgroups v2 enabled and read the memory limits according to that.

- SERVER-62229 Fix invariant by allowing applying index build abort entry when in recoverFromOplogAsStandalone mode
- SERVER-55429 Fixed the issue with blocked migrations by adding a timeout to migrations when waiting for range deletions on intersecting ranges

Find the full list of changes in the MongoDB 4.4.14 Community Edition Release notes.

22.4.2 Improvements

- PSMDB-1011: Add KMIP master key rotation
- PSMDB-1043: The kmipClientCertificateFile option now includes both the client private key and public certificate
- PSMDB-1044: Make the kmipPort option not mandatory and assign the default value

22.4.3 Bugs Fixed

- PSMDB-979: Rotate audit logs in the mode as defined in the configuration.
- PSMDB-1030: Fix descriptions and mutual dependencies of KMIP related options for mongod and perconadecrypt

22.5 Percona Server for MongoDB 4.4.13-13

Date March 23, 2022

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.13-13 is an enhanced, source-available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.13 Community Edition. It supports MongoDB 4.4.13 protocols and drivers.

Warning: Inconsistent data is observed after the upgrade from MongoDB 4.4.3 and 4.4.4 to versions 4.4.8+ and 5.0.2+. This issue is fixed upstream in versions 4.4.11+ and 5.0.6+. *Percona Server for MongoDB* also includes the fix starting from versions 4.4.12-12 and 5.0.6-5.

See the upgrade recommendations below:

- Clusters on versions 4.4.0 and 4.4.1 are safe to upgrade to 4.4.8+ or 5.0.2+ but should upgrade to recommended versions 4.4.11+ or 5.0.5+.
- Clusters on versions 4.4.2, 4.4.3, or 4.4.4 should **downgrade** to 4.4.1 and then upgrade to versions 4.4.11+ or 5.0.5+.
- Clusters running versions 4.4.5 4.4.7 can and should upgrade to versions 4.4.11+ or 5.0.5+.

Note that clusters running versions 4.4.2 - 4.4.8 are affected by the bug WT-7995. See WT-7995 for specific explanation and instructions on running the validate command to check for data inconsistencies. These data inconsistencies can lead to data loss if not identified and repaired at this point between versions 4.4.8 and 4.4.9.

If the validate command output reports any failures, resync the impacted node from an unaffected node. The validate command must be run against all collections in the database. This process can be resource intensive and can negatively impact performance.

22.5.1 Release Highlights

Percona Server for MongoDB now supports *Keys Management Interoperability Protocol (KMIP)* so that users can store encryption keys in their favorite KMIP-compatible key manager to set up encryption at rest. This is a tech preview feature.

The list of bug fixes introduced by MongoDB and included in *Percona Server for MongoDB* is the following:

- SERVER-63203 Fixed the issue where having a large number of split points causes the chunk splitter to not function correctly and huge chunks would not be split without manual intervention. This can be caused when having small shard key ranges and a very high number of documents and where more than 8192 split points would be needed.
- SERVER-62065 Added the repairShardedCollectionChunksHistory command to restore history fields for some chunks. This aims to fix broken snapshot reads and distributed transactions.
- SERVER-59754 Fixed incorrect logging of queryHash/planCacheKey for operations that share the same \$lookup shape
- SERVER-55483 Added a new startup parameter that skips verifying the table logging settings on restarting as a replica set node from the standalone mode during the restore. This speeds up the restore process.

Find the full list of changes in the MongoDB 4.4.13 Community Edition Release notes.

22.5.2 New Features

• PSMDB-971: Added support for KMIP (Keys Management Interoperability Protocol) encryption. Now users can store encryption keys in their favorite KMIP-compatible key manager to set up encryption at rest.

22.5.3 Bug Fixes

- PSMDB-1010: Fixed the parameters order in the LOGV2_DEBUG statement for LDAP logging.
- PSMDB-957: Fixed server crash caused by LDAP misconfiguration. Now the server logs an error message and exits.

22.6 Percona Server for MongoDB 4.4.12-12

Date February 7, 2022

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.12-12 is an enhanced, source-available and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB Community Edition. It is based on MongoDB 4.4.11 and 4.4.12 and supports MongoDB 4.4.11 - 4.4.12 protocols and drivers.

Warning: Inconsistent data is observed after the upgrade from MongoDB 4.4.3 and 4.4.4 to versions 4.4.8+ and 5.0.2+. This issue is fixed upstream in versions 4.4.11 and 5.0.6. *Percona Server for MongoDB* also includes the fix in versions 4.4.12-12 and 5.0.6-5

See the upgrade recommendations below:

• Clusters on versions 4.4.0 and 4.4.1 are safe to upgrade to 4.4.8+ or 5.0.2+ but should upgrade to recommended versions 4.4.11+ or 5.0.5+

- Clusters on versions 4.4.2, 4.4.3, or 4.4.4 should **downgrade** to 4.4.1 and then upgrade to versions 4.4.11+ or 5.0.5+.
- Clusters running versions 4.4.5 4.4.7 can and should upgrade to versions 4.4.11+ or 5.0.5+.

Note that clusters running versions 4.4.2 - 4.4.8 are affected by the bug WT-7995. See WT-7995 for specific explanation and instructions on running the validate command to check for data inconsistencies. These data inconsistencies can lead to data loss if not identified and repaired at this point between versions 4.4.8 and 4.4.9.

If the validate command output reports any failures, resync the impacted node from an unaffected node. The validate command must be run against all collections in the database. This process can be resource intensive and can negatively impact performance.

22.6.1 Release Highlights

The bug fixes and improvements, provided by MongoDB and included in Percona Server for MongoDB, are the following:

- WT-8395 Fixed an issue with inconsistent data observed during the direct upgrade from from 4.4.3 and 4.4.4 to 4.4.8+ and 5.0.2+. Data inconsistency was caused by the incorrect checkpoint metadata to sometimes be recorded by MongoDB versions 4.4.3 and 4.4.4. WiredTiger used this metadata during node startup that could lead to data corruption and could cause the DuplicateKey error. The fix requires the upgrade to versions 4.4.11+ or 5.0.5+.
- SERVER-61930 Defined a timeout for a health check process and throw an error when the process fails to complete within a timeout. This prevents health check to hang.
- SERVER-61637 Changed the rangeDeleterBatchSize value to unlimited to avoid the balancer starvation during batched deletes.
- SERVER-59362 Added the ability to transition through the valid states of the fault manager, and the interface to observer and log its state transitions.
- SERVER-62147 Fixed broken OP_QUERY exhaust cursor implementation
- SERVER-62065 Added the repairShardedCollectionChunksHistory command to restore history fields for some chunks. This aims to fix broken snapshot reads and distributed transactions.

Find the full list of changes in the MongoDB 4.4.11 Community Edition and MongoDB 4.4.12 Community Edition release notes

22.6.2 Bugs Fixed

- PSMDB-756: Fixed an issue with unmet dependencies for installing MongoDB on Debian (Thanks to Stefan Schlesi for reporting this issue)
- PSMDB-950: Fixed LDAP authentication using mongo CLI for Percona Server for MongoDB installed from a tarball.

22.7 Percona Server for MongoDB 4.4.10-11

Date November 10, 2021

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.10-11 is an enhanced, source-available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.10 Community Edition.

It is rebased on MongoDB 4.4.10 Community Edition and supports MongoDB 4.4.10 protocols and drivers.

22.7.1 Release Highlights

The changes and bug fixes introduced by MongoDB include the following:

• Fixed delays in establishing egress connections on mongos due to delayed responses from libcrypto.so

Find the full list of changes in the MongoDB 4.4.10 Community Edition release notes.

22.8 Percona Server for MongoDB 4.4.9-10

Date October 7, 2021

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.9-10 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.9 Community Edition. It supports MongoDB 4.4.9 protocols and drivers.

Warning: Beginning with MongoDB 4.4.2, several data impacting or corrupting bugs were introduced. Details are listed below.

These bugs are fixed in MongoDB 4.4.9. Percona Server for MongoDB 4.4.9-10 includes the upstream fixes of these bugs.

Please upgrade to MongoDB 4.4.9 or Percona Server for MongoDB 4.4.9-10 as soon as possible.

Additional upgrade planning note

If you are running MongoDB version 4.4.4 / Percona Server for MongoDB 4.4.4-5 or below, please skip upgrading to version 4.4.8 as that has been found to trigger the Duplicate Key error most consistently. Two WiredTiger bugs (WT-7984 and WT-7995) are found in all versions of MongoDB 4.4.x except 4.4.1. Ideally, upgrade directly from version 4.4.1 to 4.4.9 to attempt to avoid those data impacting or corrupting bugs.

22.8.1 Release Highlights

The bug fixes, provided by MongoDB and included in Percona Server for MongoDB, are the following:

- WT-7426 After upgrade to v4.4.5, startups or restarts can trigger WiredTigers RTS bug which can corrupt page metadata causing documents on affected pages to become invisible to MongoDB. This can lead to temporary query incorrectness, or more likely a fatal error and inability to restart. Affects only MongoDB 4.4.5 and Percona Server for MongoDB 4.4.5-7.
- SERVER-58936 Unique Index constraint violations possible can cause duplicate data fixed in version 4.4.8.
- WT-7995 Checkpoint thread can read and persist inconsistent version of data to disk. Can cause Duplicate Key error on startup and prevent the node from starting. Unclean shutdowns can cause data inconsistency within documents, deleted documents to still exist, incomplete query results due to lost or inaccurate index entries, and/or missing documents. Affects MongoDB versions 4.4.2 through 4.4.8 and Percona Server for MongoDB 4.4.9-4 4.4.8-9 as well as MongoDB 5.0.0 through 5.0.2. Upgrade to fixed version of MongoDB 4.4.9-10 as soon as possible.
- WT-7984 and associated Server Bug SERVER-60371.
- WT-7984 Bug that could cause Checkpoint thread to omit a page of data. If the server experiences an unclean shutdown, an inconsistent checkpoint is used for recovery and causes data corruption. Fixed in version 4.4.9.
 Requires the validate command to be run and possible data remediation via complete initial sync.
- SERVER-60371 If previously upgraded to version 4.4.8 then upgrade to 4.4.9, could still experience Duplicate Key error and Fatal assertion. Related to the two previous WiredTiger bugs.

Requires the validate command to be run and possible data remediation via complete initial sync. Currently under review.

Find the full list of changes in the MongoDB 4.4.9 Community Edition release notes.

22.8.2 Improvements

• PSMDB-918: Disable the ability to delete the *mongod* user in RPM packages - This preserves the permissions to the MongoDB data directory for the mongod user as its user ID and group ID remain unchanged.

22.9 Percona Server for MongoDB 4.4.8-9

Date August 16, 2021

Installation Installing Percona Server for MongoDB

Warning: This version is not recommended for production use due to the following critical issues: WT-7984 and WT-7995. They are fixed in MongoDB 4.4.9 Community Edition and *Percona Server for MongoDB 4.4.9-10*.

We recommend you to upgrade to Percona Server for MongoDB 4.4.9-10 and run the validate command on every collection on every replica set node.

Read more about the post-upgrade steps in WT-7984 and WT-7995.

Percona Server for MongoDB 4.4.8-9 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.8 Community Edition. It supports MongoDB 4.4.8 protocols and drivers.

22.9.1 Improvements

- PSMDB-211: Add the ability to view the status of *hot backup* using the mongo shell
- PSMDB-824, PSMDB-892, PSMDB-807: Remove excessive log messages and improve error messages for various backup cases

22.9.2 Bugs Fixed

- PSMDB-210: Add the ability to stop a running hot backup with the killop() method
- PSMDB-902: The rateLimit field can now be used to filter audit logs
- PSMDB-876: Fix limiting of the *database Profiler* with the rateLimit option
- PSMDB-873: Add missing runtime dependencies for LDAP authentication against active directory in RPM packages

22.10 Percona Server for MongoDB 4.4.6-8

Date June 2, 2021

Installation Installing Percona Server for MongoDB

Warning: This version is not recommended for production use due to the following critical issues: WT-7984 and WT-7995. They are fixed in MongoDB 4.4.9 Community Edition and *Percona Server for MongoDB 4.4.9-10*.

We recommend you to upgrade to Percona Server for MongoDB 4.4.9-10 as soon as possible and run the validate command on every collection on every replica set node.

Read more about the issues and post-upgrade steps in WT-7984 and WT-7995.

Percona Server for MongoDB 4.4.6-8 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.6 Community Edition. It supports MongoDB 4.4.6 protocols and drivers.

22.10.1 New Features

• PSMDB-802: Create \$backupCursor and \$backupCursorExtend aggregation stages. (Tech Preview Feature¹)

¹ Tech Preview Features are not yet ready for enterprise use and are not included in support via SLA (Service License Agreement). They are included in this release so that users can provide feedback prior to the full release of the feature in a future release (or removal of the feature if it is deemed not useful). This functionality can change (APIs, CLIs, etc.) from tech preview to GA.

22.11 Percona Server for MongoDB 4.4.5-7

Date April 19, 2021

Installation Installing Percona Server for MongoDB

Warning: This version is not recommended for production use due to the following critical issues:

- WT-7426.
- WT-7984 and
- WT-7995.

The issue WT-7426 is fixed in MongoDB 4.4.6 Community Edition and Percona Server for MongoDB 4.4.6-8.

WT-7984 and WT-7995 are fixed in MongoDB 4.4.9 Community Edition and *Percona Server for MongoDB 4.4.9-10*.

We recommend you to upgrade to Percona Server for MongoDB 4.4.9-10 as soon as possible and run the validate command on every collection on every replica set node.

Read more about the issues and post-upgrade steps in WT-7984 and WT-7995.

Percona Server for MongoDB 4.4.5-7 is based on MongoDB 4.4.5 Community Edition and does not include any additional changes.

22.12 Percona Server for MongoDB 4.4.4-6

Date February 25, 2021

Installation Installing Percona Server for MongoDB

Warning: This version is not recommended for production use due to the following critical issues: WT-7984 and WT-7995. They are fixed in MongoDB 4.4.9 Community Edition and *Percona Server for MongoDB 4.4.9-10*.

We recommend you to upgrade to Percona Server for MongoDB 4.4.9-10 as soon as possible and run the validate command on every collection on every replica set node.

Read more about the issues and post-upgrade steps in WT-7984 and WT-7995.

Percona Server for MongoDB 4.4.4-6 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.4 Community Edition. It supports MongoDB 4.4.4 protocols and drivers.

22.12.1 Bugs Fixed

 PSMDB-817: LDAP ConnectionPoller always uses up CPU of one core (Thanks to user cleiton.domazak for reporting this issue)

22.13 Percona Server for MongoDB 4.4.3-5

Date January 27, 2021

Installation Installing Percona Server for MongoDB

Warning: This version is not recommended for production use due to the following critical issues: WT-7984 and WT-7995. They are fixed in MongoDB 4.4.9 Community Edition and *Percona Server for MongoDB 4.4.9-10*.

We recommend you to upgrade to Percona Server for MongoDB 4.4.9-10 as soon as possible and run the validate command on every collection on every replica set node.

Read more about the issues and post-upgrade steps in WT-7984 and WT-7995.

Percona Server for MongoDB 4.4.3-5 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.3 Community Edition. It supports MongoDB 4.4.3 protocols and drivers.

22.13.1 Improvements

- PSMDB-745: Add support for multiple LDAP servers for authentication
- PSMDB-761: Add validateLDAPServerConfig config option

22.13.2 Bugs Fixed

• PSMDB-788: Fix LDAP rebind procedure to allow LDAP referrals to work with ldapBindMethod==sasl

22.14 Percona Server for MongoDB 4.4.2-4

Date December 1, 2020

Installation Installing Percona Server for MongoDB

Warning: This version is not recommended for production use due to the following critical issues: WT-7984 and WT-7995. They are fixed in MongoDB 4.4.9 Community Edition and *Percona Server for MongoDB 4.4.9-10*.

We recommend you to upgrade to Percona Server for MongoDB 4.4.9-10 as soon as possible and run the validate command on every collection on every replica set node.

Read more about the issues and post-upgrade steps in WT-7984 and WT-7995.

Percona Server for MongoDB 4.4.2-4 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.2 Community Edition. It supports MongoDB 4.4.2 protocols and drivers.

22.14.1 Improvements

- PSMDB-758: Add mongobridge as a part of percona-server-mongodb-server package
- PSMDB-755: Add IdapDebug, IdapFollowReferrals and IdapConnectionPoolSizePerHost server parameters
- PSMDB-711: Improve audit log performance

22.14.2 Bugs Fixed

- PSMDB-718: Audit log messages include datatype output
- PSMDB-712: User can't be authorized via LDAP due to 'LDAP search failed with error: Referral'
- PSMDB-766: Redirect openIdap debug messages to mongodb log
- PSMDB-715: createBackup using AWS remote location fails with "EntityTooLarge"
- PSMDB-544: Binaries perconadecrypt and mongobridge do not have a version

22.15 Percona Server for MongoDB 4.4.1-3

Date October 9, 2020

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.1-3 is an enhanced, source-available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.1 Community Edition. It supports MongoDB 4.4.1 protocols and drivers.

This release fixes security vulnerability CVE-2020-26542.

22.16 Percona Server for MongoDB 4.4.1-2

Date September 24, 2020

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.1-2 is an enhanced, source available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.1 Community Edition. It supports MongoDB 4.4.1 protocols and drivers.

22.16.1 Bugs Fixed

- PSMDB-707: LDAP authentication randomly fails with the "Bad parameter to an Idap routine" message in the log
- PSMDB-677: mongosh cannot authenticate LDAP user
- PSMDB-674: Provide binary tarball with shared libs and glibc suffix

22.17 Percona Server for MongoDB 4.4.0-1

Date August 26, 2020

Installation Installing Percona Server for MongoDB

Percona Server for MongoDB 4.4.0-1 is an enhanced, source-available, and highly-scalable database that is a fully-compatible, drop-in replacement for MongoDB 4.4.0 Community Edition. It supports MongoDB 4.4.0 protocols and drivers.

This release includes all features of MongoDB 4.4.0 Community Edition and provides Enterprise-level enhancements for free.

See also:

Percona Blog Post

• MongoDB 4.4 Is Coming Out Soon - What Does the Code Tell Us?

Percona Server for MongoDB requires no changes to MongoDB applications or code and is available for download from Percona website.

Part VI

Reference

TWENTYTHREE

CONTACTING, CONTRIBUTING, REPORTING BUGS

If you want to contact developers, use the community forum.

Note: Please search the forum for similar questions and discussions before openning a new thread.

You will need to sign up for an account to post in the forum.

If you want to explore source code and contribute to the project use the GitHub repo and the Contributing guide.

Note: Search existing pull requests and recent commits for code that may fix what you are planning to suggest.

You will need a public GitHub account and request contributor access to the repo.

If you want to report a bug or feature request, use the PSMDB project in JIRA.

Note: Search JIRA for existing tickets before submitting a bug or feature request.

You will need a JIRA account to report bugs.

Percona Server for MongoDB 4.4 Documentation, F	Release 4.4.17-17

TWENTYFOUR

GLOSSARY

ACID Set of properties that guarantee database transactions are processed reliably. Stands for *Atomicity*, *Consistency*, *Isolation*, *Durability*.

Atomicity Atomicity means that database operations are applied following a "all or nothing" rule. A transaction is either fully applied or not at all.

Consistency Consistency means that each transaction that modifies the database takes it from one consistent state to another.

Durability Once a transaction is committed, it will remain so.

Foreign Key A referential constraint between two tables. Example: A purchase order in the purchase_orders table must have been made by a customer that exists in the customers table.

Isolation The Isolation requirement means that no transaction can interfere with another.

Jenkins Jenkins is a continuous integration system that we use to help ensure the continued quality of the software we produce. It helps us achieve the aims of:

- no failed tests in trunk on any platform,
- aid developers in ensuring merge requests build and test on all platforms,
- no known performance regressions (without a damn good explanation).

Kerberos Kerberos is an authentication protocol for client/server authentication without sending the passwords over an insecure network. Kerberos uses symmetric encryption in the form of tickets - small pieces of encrypted data used for authentication. A ticket is issued for the client and validated by the server.

Rolling restart A rolling restart (rolling upgrade) is shutting down and upgrading nodes one by one. The whole cluster remains operational. There is no interruption to clients assuming the elections are short and all writes directed to the old primary use the retryWrite mechanism.

TWENTYFIVE

COPYRIGHT AND LICENSING INFORMATION

25.1 Documentation Licensing

This software documentation is (C)2016-2022 Percona LLC and/or its affiliates and is distributed under the Creative Commons Attribution 4.0 International License.

25.2 Software License

Percona Server for MongoDB is source-available software.

Percona Server for MongoDB 4.4 Documentation, Release 4.4.17-17					

TWENTYSIX

TRADEMARK POLICY

This Trademark Policy is to ensure that users of Percona-branded products or services know that what they receive has really been developed, approved, tested and maintained by Percona. Trademarks help to prevent confusion in the marketplace, by distinguishing one company's or person's products and services from another's.

Percona owns a number of marks, including but not limited to Percona, XtraDB, Percona XtraDB, XtraBackup, Percona XtraBackup, Percona Server, and Percona Live, plus the distinctive visual icons and logos associated with these marks. Both the unregistered and registered marks of Percona are protected.

Use of any Percona trademark in the name, URL, or other identifying characteristic of any product, service, website, or other use is not permitted without Percona's written permission with the following three limited exceptions.

First, you may use the appropriate Percona mark when making a nominative fair use reference to a bona fide Percona product.

Second, when Percona has released a product under a version of the GNU General Public License ("GPL"), you may use the appropriate Percona mark when distributing a verbatim copy of that product in accordance with the terms and conditions of the GPL.

Third, you may use the appropriate Percona mark to refer to a distribution of GPL-released Percona software that has been modified with minor changes for the sole purpose of allowing the software to operate on an operating system or hardware platform for which Percona has not yet released the software, provided that those third party changes do not affect the behavior, functionality, features, design or performance of the software. Users who acquire this Perconabranded software receive substantially exact implementations of the Percona software.

Percona reserves the right to revoke this authorization at any time in its sole discretion. For example, if Percona believes that your modification is beyond the scope of the limited license granted in this Policy or that your use of the Percona mark is detrimental to Percona, Percona will revoke this authorization. Upon revocation, you must immediately cease using the applicable Percona mark. If you do not immediately cease using the Percona mark upon revocation, Percona may take action to protect its rights and interests in the Percona mark. Percona does not grant any license to use any Percona mark for any other modified versions of Percona software; such use will require our prior written permission.

Neither trademark law nor any of the exceptions set forth in this Trademark Policy permit you to truncate, modify or otherwise use any Percona mark as part of your own brand. For example, if XYZ creates a modified version of the Percona Server, XYZ may not brand that modification as "XYZ Percona Server" or "Percona XYZ Server", even if that modification otherwise complies with the third exception noted above.

In all cases, you must comply with applicable law, the underlying license, and this Trademark Policy, as amended from time to time. For instance, any mention of Percona trademarks should include the full trademarked name, with proper spelling and capitalization, along with attribution of ownership to Percona Inc. For example, the full proper name for XtraBackup is Percona XtraBackup. However, it is acceptable to omit the word "Percona" for brevity on the second and subsequent uses, where such omission does not cause confusion.

In the event of doubt as to any of the conditions or exceptions outlined in this Trademark Policy, please contact trademarks@percona.com for assistance and we will do our very best to be helpful.

INDEX

Symbols --auditDestination Rolling restart, 123 command line option, 44 --auditFilter command line option, 44 --auditFormat command line option, 44 --auditPath command line option, 44 --inMemorySizeGB command line option, 23 --inMemoryStatisticsLogDelaySecs command line option, 24 Α ACID, 123 Atomicity, 123 command line option --auditDestination, 44 --auditFilter, 44 --auditFormat, 44 --auditPath, 44 --inMemorySizeGB, 23 --inMemoryStatisticsLogDelaySecs, 24 Consistency, 123 D Durability, 123 F Foreign Key, 123 Isolation, 123 Jenkins, 123 K Kerberos, 123

R