


Braze sGTM Proxy Client — Setup Documentation

Thank you for purchasing the sGTM Client Template for Braze™ Proxying!

This document contains the step-by-step documentation to successfully import, configure, and integrate the template into your server-side Google Tag Manager setup and frontend environment.

Step 1 — Import the Template into sGTM


- In your Google Tag Manager Server Container, navigate to Templates on the left-hand menu.
- In the Client Templates section, click the New button.
- Click the three vertical dots (top-right contextual menu) and select Import.
- Choose the downloaded file: **custom-client-braze-proxy.tpl**
- Click Save in the top right corner and close the template editor panel.



The screenshot displays the 'Template Editor' interface. On the left, the 'Info' tab is selected, showing input fields for 'Name' (labeled 'Untitled Template'), 'Description' (labeled 'Enter a description'), and 'Icon'. Below these is a 'Choose image' button and a checkbox for 'Agree to Community Template Gallery Terms of Service'. The right pane, 'Template Preview', shows the 'Client Configuration' section with 'Client Type' set to 'Untitled Template Custom Template' and 'Priority' set to 0. A contextual menu is open in the top right corner, listing options: Import, Export, Show advanced settings, Show test page, Send Feedback, and Help.

Step 2 — Create and Configure the Client

- Navigate to Clients in the left-hand menu and click New.
- Click on Client Configuration and select your newly imported Braze Proxy Client.



- API Endpoint: Enter your project-specific Braze SDK endpoint (e.g., <https://sdk.ex-01.braze.eu>). You can locate this string in your Braze Dashboard under *Settings > App Settings > SDK Endpoint*.
- Allowed API Keys (Recommended): Enter your authorized Braze Web API key(s) to strictly secure your infrastructure endpoint against unauthorized proxy use. You can locate this string in your Braze Dashboard under *Settings > App Settings > API Key*.
- Allowed Origins: Specify your allowed website domains (e.g., <https://www.yourdomain.com>). Note: Ensure there is no trailing slash at the end of the URL string.
- Assign a recognizable name to the client (e.g., Braze Proxy) and click Save.

The screenshot shows the 'Client Configuration' modal for a 'Braze Proxy Client' in the Google Tag Manager interface. The left sidebar shows the 'Clients' section under 'Workspace'. The modal contains the following fields and options:

- Client Type:** Braze Proxy Client (datapip.de) with a 'Client permissions' link showing 5 permissions.
- Priority:** 100
- API Endpoint:** https://sdk.ex-01.braze.eu
- Allowed API Keys (recommended):**
 - API Key: a1b2c34d-5e6f7g8h-10i11j12k13l
 - Buttons: Add API Key
- Allowed Origins (recommended):**
 - Origin: https://www.yourdomain.com
 - Buttons: Add Origin
- Additional Settings:** (expandable section)

A 'Save' button is located at the top right of the modal.

Step 3 — Update your Website Integration

To actively route your frontend tracking traffic completely through your server-side container infrastructure, apply the following two code alterations to your codebase:

1. Load the Web SDK

Follow the documentation on how to install the Braze library via Braze CDN as described here: https://www.braze.com/docs/developer_guide/sdk_integration. Adjust the script `src` attribute to pull the minified library file straight from your own sGTM tracking instance domain wrapper instead of the standard public vendor CDN asset:

```
<script type="text/javascript">
  +function(a,p,P,b,y){a.braze={};a.brazeQueue=[] ... // Note: this code is shortened
    y.src='https://data.yourdomain.com/web-sdk/6.7/braze.min.js';
    y.async=1;(b=p.getElementsByTagName(P)[0]).parentNode.insertBefore(y,b)
  }(window,document,'script');
</script>
```

2. Initialize the Braze Web SDK

Point the baseline URL property directly to your custom sGTM domain environment:

```
braze.initialize("YOUR-API-KEY", {  
  baseUrl: "https://data.yourdomain.com",  
  // All other initialization options remain completely unchanged  
});
```

License, Support & Conditions

- **License Scope:** Single-company license. This commercial transaction grants operational deployment rights exclusively to the purchasing business entity/organization for internal domain infrastructures.
- **Product State & Warranty:** This asset is sold strictly as-is based on its current stable development release state. No automated future compatibility updates or maintenance lifecycles are guaranteed following potential breaking changes to internal Braze structural API layers.