# Further investigation of harmonic vibration

#### Math 352 Differential Equations

The College of Idaho

17 April 2013

#### Last time: free harmonic oscillations

Recall the equation of motion for an unforced spring-mass system:

$$mu'' + \gamma u' + ku = 0,$$

where m, k > 0 and  $\gamma \ge 0$ .

If  $\gamma=0$ , then our system is a simple harmonic oscillator, vibrating subject to the displacement function

$$u = c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t).$$

Such a system's motion persists indefinitely. The energy added by the initial conditions stays in the system forever.

#### Reduction to standard form

Every linear combination of sines and cosines with like frequency can be written as a single sinusoidal function. A sinusoidal function is one of the form  $R\cos\left(\omega t - \delta\right)$ , where R is the amplitude,  $\omega$  is the common frequency, and  $\delta$  is the phase shift.

### **Getting the new parameters**

Suppose that we have already obtained  $c_1$  and  $c_2$  from the initial conditions and wish to find R and  $\delta$  with

$$c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t) = R \cos(\omega_0 t - \delta).$$

Using the cosine subtraction identity, we find this entails that

$$c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t) = R \cos \delta \cos(\omega_0 t) + R \sin \delta \sin(\omega_0 t).$$

Hence  $c_1 = R\cos\delta$ ,  $c_2 = R\sin\delta$ , and the usual polar-coordinate equations give us

$$R = \sqrt{c_1^2 + c_2^2}, \tan \delta = c_2/c_1.$$

The arctangent function must be used with due care.

# Classification of damping; overdamped

If  $\gamma>0$ , we refer to the system as "damped". The type of damping corresponds to the discriminant  $D=\sqrt{\gamma^2-4km}$  of the characteristic polynomial.

When D > 0, the roots of the characteristic polynomial are real and negative. This is the overdamped case, and the displacement function is a linear combination of two exponentials  $e^{r_1t}$  and  $e^{r_2t}$ . Since  $r_1$ ,  $r_2 < 0$ , the vibration decays as t increases.

# **Underdamped**; critically damped

When D<0, the roots are complex with negative real part, so the oscillation again decays. Write  $\lambda \pm i\mu$  for the roots: then the displacement function is a linear combination of the functions  $e^{\lambda t}\cos(\mu t)$  and  $e^{\lambda t}\sin(\mu t)$ .

# Underdamped; critically damped

When D<0, the roots are complex with negative real part, so the oscillation again decays. Write  $\lambda \pm i\mu$  for the roots: then the displacement function is a linear combination of the functions  $e^{\lambda t}\cos(\mu t)$  and  $e^{\lambda t}\sin(\mu t)$ .

When D=0, the system is *critically damped*. Then, there is only one root r of the characteristic polynomial. The displacement function is a linear combination of  $e^{rt}$  and  $te^{rt}$ . The graphs of critically damped displacement functions look a lot like those of overdamped ones.

# The damped cases: three regimes

If  $\gamma > 0$ , then the initial energy is eventually (and in practice, quickly) dissipated in resisting the damping force of the surrounding fluid. Clearly, greater values of  $\gamma$  mean "more" damping is occurring. The correct way to measure the "size" of the damping is not via  $\gamma$  alone, but with a dimensionless coefficient involving all three constants m,  $\gamma$ , and k.

Let  $Q=\gamma^2/4km$ . If you compare the dimensions of the three coefficients, you will see that Q is dimensionless: all the units cancel out of it. Dimensionless coefficients are important, because they don't depend on our scale of measurement. It turns out that Q is a nice code for the damping type of our system.

▶ Trivially, Q = 0 when  $\gamma = 0$ .

Let  $Q=\gamma^2/4km$ . If you compare the dimensions of the three coefficients, you will see that Q is dimensionless: all the units cancel out of it. Dimensionless coefficients are important, because they don't depend on our scale of measurement. It turns out that Q is a nice code for the damping type of our system.

- ▶ Trivially, Q = 0 when  $\gamma = 0$ .
- ▶ Our system is underdamped when 0 < Q < 1.

Let  $Q=\gamma^2/4km$ . If you compare the dimensions of the three coefficients, you will see that Q is dimensionless: all the units cancel out of it. Dimensionless coefficients are important, because they don't depend on our scale of measurement. It turns out that Q is a nice code for the damping type of our system.

- ▶ Trivially, Q = 0 when  $\gamma = 0$ .
- ▶ Our system is underdamped when 0 < Q < 1.
- Critical damping obtains when Q = 1.

Let  $Q=\gamma^2/4km$ . If you compare the dimensions of the three coefficients, you will see that Q is dimensionless: all the units cancel out of it. Dimensionless coefficients are important, because they don't depend on our scale of measurement. It turns out that Q is a nice code for the damping type of our system.

- ▶ Trivially, Q = 0 when  $\gamma = 0$ .
- ▶ Our system is underdamped when 0 < Q < 1.
- Critical damping obtains when Q = 1.
- ▶ Overdamping is the case Q > 1.

# Quasiperiod and quasifrequency

The parameter  $\mu$  determines the quasifrequency of a damped oscillation (since it is not periodic, it doesn't have an honest "frequency"). Some algebra shows that

$$\frac{\mu}{\omega_0} = \frac{\sqrt{4km - \gamma^2}}{2m\sqrt{k/m}} = (1 - Q)^{1/2} \approx 1 - \frac{Q}{2}.$$

The last approximation is valid, as usual, when Q is small. These calculations will be of great utility for us in the next section, which concerns *forced vibrations*. Thus, small damping slightly reduces the frequency of the oscillation.