Further investigation of harmonic vibration

Math 352 Differential Equations

7 April 2014

Last time: free harmonic oscillations

The equation of motion for an unforced spring-mass system:

$$mu'' + \gamma u' + ku = 0,$$

where m, k > 0 and $\gamma \ge 0$.

Here u is the displacement of the mass from equilibrium.

Determining the spring constant

In practice, the spring constant is obtained via the relation

$$mg = kL$$
.

Here L is the marginal length added when the mass m is attached.

No damping

▶ If $\gamma = 0$, our system is a *simple harmonic oscillator*, vibrating subject to the displacement function

$$u = c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t).$$

- ▶ Here $\omega_0 = \sqrt{k/m}$ is the natural frequency of the oscillator.
- ▶ If either of c_1 or c_2 is nonzero, then either u(0) or u'(0) is nonzero. Thus either the potential energy or kinetic energy of the mass is nonzero.
- Such a system's motion persists indefinitely.
- The energy added by the initial conditions stays in the system forever.



Reduction to standard form

- Every linear combination of sines and cosines with like frequency can be written as a single sinusoidal function.
- ▶ A sinusoidal function is one of the form $R\cos{(\omega t \delta)}$, where R is the amplitude, ω is the common frequency, and δ is the phase shift.
- If we know c_1 and c_2 from the initial conditions, we can find R and δ with

$$c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t) = R \cos(\omega_0 t - \delta).$$



Getting the new parameters

Using the cosine subtraction identity, we find this entails that

$$c_1 \cos(\omega_0 t) + c_2 \sin(\omega_0 t) = R \cos \delta \cos(\omega_0 t) + R \sin \delta \sin(\omega_0 t).$$

Hence $c_1 = R \cos \delta$, $c_2 = R \sin \delta$, and the usual polar-coordinate equations give us

$$R = \sqrt{c_1^2 + c_2^2}, \quad \tan \delta = c_2/c_1.$$

The arctangent function must be used with due care.



Reminder on arctangent; atan2

- ▶ Recall: $tan^{-1}x \in (-\pi/2, \pi/2)$ for all x
- You may need to adjust the value from a calculator.
- ▶ Adjustments must be made when the desired value of δ is in the left half-plane: namely, when $c_1 < 0$.
- Sage and many other programming languages include the useful function atan2.
- This is a function of two variables that makes this adjustment automatically.
- ▶ atan2(y, x) returns the unique angle δ with $\sin(\delta) = y$ and $\cos(\delta) = x$
 - (and of course $tan(\delta) = y/x$)



Classification of damping; overdamped

- $\gamma > 0$: the system is "damped".
- ► The type of damping corresponds to the sign of $D = \gamma^2 4km$.
- ▶ When D > 0, the system is *overdamped*.
 - ▶ The displacement function is a linear combination of two exponentials e^{r_1t} and e^{r_2t} , with r_1 , $r_2 < 0$.
 - ▶ The vibration decays as *t* increases—in practice, very quickly.

Underdamped; critically damped

- ▶ When D < 0, the displacement function is a linear combination of the functions $e^{\lambda t} \cos(\mu t)$ and $e^{\lambda t} \sin(\mu t)$.
- ▶ The coefficients λ and μ , as always, are determined by the characteristic polynomial: its roots are $\lambda \pm i\mu$ in this case.
- ▶ Here λ < 0, so the oscillation again decays with time.
- This is called underdamped.
- ▶ When D = 0, the system is *critically damped*.
- ► The displacement function is a linear combination of e^{rt} and te^{rt}. Here r is the unique root of the characteristic polynomial.
- ► The graphs of critically damped displacement functions look a lot like those of overdamped ones.



The damped cases: three regimes

- If $\gamma > 0$, then the initial energy is dissipated
 - (and in practice, quickly)
 - in resisting the damping force of the surrounding fluid.
- \blacktriangleright Clearly, greater values of γ mean "more" damping is occurring.
- ▶ The "size" of the damping is measured by a dimensionless coefficient involving all three constants m, γ , and k.

Dimensional analysis: work together

- ▶ Find a dimensionless combination of m, γ , and k.
- ▶ Hint: mg = kL.

Damping and the discriminant

- ▶ Let $Q = \gamma^2/4km$.
- Q is dimensionless: all the units cancel out of it.
- Dimensionless coefficients are important, because they don't depend on our scale of measurement.
- ▶ Trivially, Q = 0 when $\gamma = 0$.
- ▶ Our system is underdamped when 0 < Q < 1.
- Critical damping obtains when Q = 1.
- ▶ Overdamping is the case Q > 1.

Quasiperiod and quasifrequency

The parameter μ determines the quasifrequency of a damped oscillation (since it is not periodic, it doesn't have an honest "frequency"). Some algebra shows that

$$\frac{\mu}{\omega_0} = \frac{\sqrt{4km - \gamma^2}}{2m\sqrt{k/m}} = (1 - Q)^{1/2} \approx 1 - \frac{Q}{2}.$$

The last approximation is a tangent line approximation, valid when Q is small.

Thus, small damping slightly reduces the frequency of the oscillation. These calculations will be of great utility for us in the next section, which concerns *forced vibrations*.