ROP

CS-UY 3943-G / CS-GY 9223-H

Motivation

- Consider a situation where we have:
 - A buffer overflow or other vulnerability that gives us control over the return address and values on the stack
- But:
 - No executable stack (NX)
 - No handy shell-like functions (give_shell, run_cmd, system)
- How can we still get code execution?

Return-Oriented Programing

- Solution: use code that's already in the program!
- x86 code is variable length (each instruction can be 1 to 15 bytes long) and dense (most random byte sequences are valid instructions)
- This means that you can jump to the middle of an instruction and usually get a valid instruction

Pop, pop, ret

- The core idea is to find sequences of instructions (called gadgets) in the binary that end in ret
- Each of these does a little bit of work and then transfers control to the next gadget via ret

Simple Example: execve("/bin/sh")

- Let's give ourselves some gadgets, and assume the string "/bin/sh" is in memory at 0x600000
- The full call to execve is execve("/bin/sh", NULL, NULL)
- In assembly, we roughly want mov rdi, 0x600000 mov rsi, 0 mov rdx, 0 mov rax, 59 syscall


Simple Example: execve("/bin/sh")

Our gadgets:

A B C D syscall pop rdi pop rsi pop rdx ret ret ret

E pop rax ret

What should our stack look like?




Simple Example: execve("/bin/sh")

Our gadgets:

A B C D syscall pop rdi pop rsi pop rdx ret ret ret

E pop rax ret

What should our stack look like?



RetAddr

How do we find gadgets?

- Reminder: there are utilities that can do this for you!
- One that comes with pwntools is ROPgadget

```
(pwn) moyix@lorenzo:~/offsec/week_9/rop$ ROPgadget --binary ./rop
Gadgets information
0x0000000000400564 : adc byte ptr [rax], ah ; jmp rax
0x00000000004005a4 : adc byte ptr [rax], ah ; jmp rdx
0 \times 0000000000040062d: add al, ch; retf -1
0x00000000004006bf : add bl, dh ; ret
0x000000000040062b : add byte ptr [rax], al ; add al, ch ; retf -1
0x00000000004006bd : add byte ptr [rax], al ; add bl, dh ; ret
0x00000000004006bb : add byte ptr [rax], al ; add byte ptr [rax], al ; add bl, dh ; ret
0x00000000004006bc : add byte ptr [rax], al ; add byte ptr [rax], al ; ret
0x00000000004004a3 : add byte ptr [rax], al ; add rsp, 8 ; ret
0x00000000004006be : add byte ptr [rax], al ; ret
0x00000000004005c8 : add byte ptr [rcx], al ; ret
0x00000000004005c4 : add eax, 0x200a8e ; add ebx, esi ; ret
0x000000000040058b : add eax, edx ; sar rax, 1 ; jne 0x40059c ; pop rbp ; ret
0 \times 000000000004005c9 : add ebx, esi ; ret
```

Dealing With LibC

- Many binaries don't have a lot of gadgets available
- You may want to call interesting functions in libc that aren't imported by the target binary (so they're not in the PLT/GOT)
- Unfortunately, the address of libc is randomized

Finding LibC

- The trick is to notice that we have the address of several libc functions in the GOT already
- For example, after we call puts, the linker puts the address of puts in libc into the GOT for us:

```
(gdb) x/i 0x400715

0x400715 <main+31>: call 0x400580 <puts@plt>

(gdb) x/i 0x400580

0x400580 <puts@plt>: jmp QWORD PTR [rip+0x200a92] # 0x601018

(gdb) x/xg 0x601018

0x601018: 0x00007ffff7a7c690
```

This address is in libc!

Leaking a LibC address

- We can do the equivalent of puts(puts@GOT) to leak an address from libc
- Why does this help us?
- Once we know the address of puts, we can look up where puts is in libc
- Then just subtract off the offset of puts, and we have the base address of libc in memory
- From here we can get address of any other function in libc!

Calculating libc Addresses

In pwntools:

```
In [1]: from pwn import *
In [2]: # Suppose we know the address of puts is 0x00007ffff7a7c690
In [3]: puts_addr = 0 \times 00007 ffff7a7c690
In [4]: libc = ELF('libc-2.19.so')
[*] '/home/moyix/offsec/week 9/rop/libc-2.19.so'
    Arch: amd64-64-little
   RELRO: Partial RELRO
Stack: Canary found
   NX: NX enabled
    PIE: PIE enabled
In [5]: libc_base = puts_addr - libc.symbols['puts']
In [6]: print hex(libc_base)
0x7fffff7a0c930
In [7]: system_addr = libc_base + libc.symbols['system']
In [8]: print hex(system_addr)
0x7ffff7a52ec0
```

Bonus of having libc: More Gadgets!

Main Binary

libc

libc also has lots of useful strings!


```
In [2]: libc = ELF('libc-2.19.so')
In [3]: libc.data.find('/bin/sh\x00')
Out[3]: 1574147
```

Leaking puts

Suppose we have a gadget
 A
 pop rdi
 ret

 The PLT entry for puts is at 0x400580, and the GOT entry for puts is at 0x601018

What should our ROP chain look like?




Leaking puts

Suppose we have a gadget
 A
 pop rdi
 ret

 The PLT entry for puts is at 0x400580, and the GOT entry for puts is at 0x601018

What should our ROP chain look like?



Proposed Exploit

- Last time we proposed this exploit:
 - We have full control of the stack
 - The program did gets(buf), or something similarly vulnerable
- We start our ROP...
 - puts(puts_got_address) to leak it => obtain address of puts in libc
 - We subtract the offset of puts in libc from that address to get the base address of libc
 - Then we add the offset of system in libc to get the real address of system
 - We jump there, with an argument of "/bin/sh", and get a shell

Problem!

- The exploit described on the last slide has a fatal flaw
- Do you see what it is?

Problem!

- The exploit described on the last slide has a fatal flaw
- Do you see what it is?
 - After we return from puts(puts_got_address) the program crashes!
 - So although we can find out the address of libc, we can't do anything with it
 - Next time we run the program, the address of libc will be different – so our knowledge is useless!

Solution: Return to main

- After our initial ROP chain that leaks the address of puts, we add the address of the main() function
- When the program finishes printing out the address, it will jump to the beginning of main... effectively restarting the program (but without changing where libc is)
- Now we can re-exploit the program
 - And we can make use of the libc addresses we learned the first time around!

Advanced ROP

- You can't always get what you want
- Sometimes your binary won't have all the gadgets you need
- Example: need to do a 3 argument syscall, but we only have

```
pop rdi; ret
pop rsi; ret
syscall; ret
```

How can we get something into rdx?

Some Ways to Set RDX

- Is there a mov rdx, ___ and a way to set ___ ?
 - E.g. mov rdx, rsi since we already have a pop rsi
- What is rdx at the point where our ROP chain starts?
 - Can we influence it?
- Can we do arithmetic in the ROP chain?
 - add, xor, inc, etc gadgets
 - Last resort, but possible for "nice" numbers or numbers near rdx

Getting Useful Strings and Constants

- We often need to get some useful string or constant into a known location (classic example: "/bin/sh\x00")
 - May not have a libc leak
 - May not have a stack leak
- Is there some way we can put our own data into a place that has some writable memory at a fixed address?

The .bss and .data Sections

- Every program will have a section of the executable dedicated to storing global variables
- Initialized data goes into .data, uninitialized data goes into .bss
- Recall: operating systems allocate memory in units of a page (4096 bytes on x86)
- This means there is often "slack" space at the end of one of these sections!

.bss Example

```
.data (PROGBITS) section started {0x601050-0x601060}
00601050 __data_start:
00601050 00 00 00 00 00 00 00 00
00601058 __dso_handle:
                             00 00 00 00 00 00 00 00
00601058
.data (PROGBITS) section ended \{0x601050-0x601060\}
.bss (NOBITS) section started \{0x601060-0x601090\}
00601060 stdout:
00601070 stdin:
00601070 00 00 00 00 00 00 00 00
00601078 completed.7585:
00601078
                              00 00 00 00 00 00 00 00
00601080 buf:
00601080 00 00 00 00 00 00 00
00601088 \quad int64_t \quad data_601088 = 0x0
.bss (NOBITS) section ended \{0x601060-0x601090\}
```

- Section "ends" at 0x601090
- ...but the rest of the page is mapped and writable
- So we have 0x601090-0x602000 for our own data

Reading Data

- How do we actually put data there?
- ROP, of course!
- Assuming the program takes input, it must have a function imported like fgets, gets, or read
- So we can create a ROP chain that calls that function to read data into some space in the .bss
- Since the .bss is at a fixed location, this lets us put whatever data we want and know where it is

Stack Pivots

- We saw one way (return to main) that you can make use of information you got from a ROP chain to continue your exploit
- Another way is a stack pivot:
 - We can call read() or similar to write a second ROP chain somewhere in the .bss
 - Then find a stack pivot gadget that allows us to set the value of rsp to point to our new ROP chain 0x4006ad: pop rsp; pop r13; pop r14; pop r15; ret
 - Everything after the pop rsp will happen on our new stack

Stack Pivot Warning

- The .bss section is not that large
- And it's where your stack is now
- As a result, calling complicated functions that use a lot of stack space could make your program crash
 - Or start overwriting your ROP chain
- Best to keep things simple and avoid using the stack too much!

One Last Trick

- If you have figured out where libc is but don't want to (or can't) construct a ROP chain to call system("/bin/sh")
- It turns out there are places within libc that if you jump to them will do the work of executing a shell for you!
 - In particular, partway through the system() function
- There are tools to find these locations, like one_gadget https://github.com/david942j/one_gadget

one_gadget

```
david942j at ~/one_gadget on master via ♥ v2.5.3
→ one_gadget /lib/x86_64-linux-gnu/libc.so.6
0x4f2c5 execve("/bin/sh", rsp+0x40, environ)
constraints:
  rcx == NULL
0x4f322 execve("/bin/sh", rsp+0x40, environ)
constraints:
  [rsp+0x40] == NULL
0x10a38c execve("/bin/sh", rsp+0x70, environ)
constraints:
  [rsp+0x70] == NULL
david942j at ~/one_gadget on master via ♥ v2.5.3
```