# Virtualization

- Virtualization
  - Preface
  - Getting QEMU ready
    - Check KVM support
    - Install Qemu dependencies
    - Install Qemu from source
  - Getting VM ready
    - Install CentOS8
      - Command args explained
    - SSH to CentOS8 virtual machine
  - OpenVSwitch DPDK
    - Get DPDK
    - OpenVSwitch configuration
    - Creating OpenVSwitch port and bridge
    - Relaunch QEMU with vhost-user support
  - Network Profiling
    - iperf result
      - virtio
      - vhost
    - ping test result
      - virtio
      - vhost
    - Summary of experiment result
  - Multi-Queue
  - Live Migration
  - Appendix convenient setup script

## **Preface**

The experiment is carried out on a host with Ubuntu 20.04 LTS (x86\_64), i7-9700K, 32GB RAM, bare metal.

We first build QEMU from source, then install DPDK and OpenVSwitch with DPDK enabled. Then we carry out our experiment.

## **Getting QEMU ready**

### **Check KVM support**

We should first check the KVM support. KVM is a Linux kernel feature.

If their is no KVM device, you should consider enable hardware virtualization support in BIOS/UEFI Firmware

### **Install Qemu dependencies**

QEMU require several dependencies.

```
$ sudo apt-get install ninja-build libmount-dev libpixman-1-dev libusb-1.0 libeproxy-dev
```

#### Install Qemu from source

First, install QEMU from source

```
$ wget https://download.qemu.org/qemu-6.1.0.tar.xz
$ tar xvJf qemu-6.1.0.tar.xz
$ cd qemu-6.1.0
$ ./configure --enable-vhost-user --enable-vhost-net --enable-kvm --enable-libusb --enable-opengl
$ make -j8
```

After Installation, we add qemu to PATH so that we can execute qemu-system-\* in shell.

```
$ export PATH=$(pwd)/build:$PATH
```

Then, use the following command to verify the installation is successful

```
$ qemu-system-x86_64
```

A window will pop out indicating that a virtual machine has been created

```
See setup-qemu.sh
```

## **Getting VM ready**

In this section, we will create and launch a CentOS8 VM with qemu.

### **Install CentOS8**

The CentOS installation image can be downloaded from Internet.

To run centos8, we need to create a image using <code>qemu-img</code> command.

```
$ cd $WORKING_DIR
$ qemu-img create -f qcow2 centos_disk_0 10G
Formatting 'centos_disk_0.img', fmt=qcow2 cluster_size=65536 ...
```

\$WORKING\_DIR the place to store VM disk image

This command:

- creates an IMG formatted virtual disk centos\_disk\_0.img
- limits the size of disk to 10GB
- sets the format of virtual disk to qcow2

We can exam the created image using file command

```
$ file centos_disk_0.img
centos_disk_0.img: QEMU QCOW2 Image (v3), 10737418240 bytes
```

The file command tells the size image is 10G. However, the image does not really consume 10G of storage space in host systeme:

```
$ ls centos_disk_0.img
-rw-r--r-- 1 liyutong staff 192K 9 18 21:04 centos_disk_0.img
```

This is because qcow2 virtual disks automatically expands when written.

With the virtual disk image and the installation image, we can then launch our virtual machine:

```
$ qemu-system-x86_64 -serial stdio \
  -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
  -device virtio-gpu-pci \
  -display default,show-cursor=on \
```


```
-device qemu-xhci -device usb-kbd \
-device usb-tablet -device intel-hda \
-device hda-duplex \
-drive file=centos_disk_0.img,if=virtio,cache=writethrough \
-cdrom CentOS-Stream-8-x86_64-latest-boot.iso \
-nic user,model=virtio
```

See qemu-install-os.sh

### Command args explained

Argument	Explanation
-serial stdio	Forwarding stdio to serial emulator
-smp 4,sockets=1,cores=4,threads=1	The system has 1 virtual CPU with 4 cores, each core has 1 thread
-m 4096	Available memory is 4096 MB
-device virtio-gpu-pci	Create a virtual GPU device
-display default,show-cursor=on	Configure display interface as default
-device qemu-xhci -device usb-kbd	USB bus
-device usb-tablet -device intel-hda	Tablet driver and Intel High Definition Audio
-device hda-duplex	HDA dubplex
-drive file=centos_disk_0.img,if=virtio,cache=writethrough	Mount centos_disk_0.img as a virtio disk, cache policy is writethrough
-cdrom centos8.iso	Mound the installation media as a CD drive
-nic user,model=virtio	Create a virtual nic using virtio

We finish installation steps in the GUI:



After installation, we remove the CD drive from virtual machine:

```
$ qemu-system-x86_64 -serial stdio \
    -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
    -device virtio-gpu-pci \
    -display default,show-cursor=on \
    -device qemu-xhci -device usb-kbd \
    -device usb-tablet -device intel-hda \
    -device hda-duplex \
    -drive file=centos_disk_0.img,if=virtio,cache=writethrough \
    -nic user,model=virtio,hostfwd=tcp::10122-:22
```

See gemu-simple-start.sh

### SSH to CentOS8 virtual machine

We have already mapped port 22 of VM to localhost:10122. To SSH to VM, simply execute the following SSH command on host

```
$ ssh -p 10122 localhost
```

On guest, we test internet connection with wget

```
(guest) $ mkdir Downloads && cd Downloads
(guest) $ wget www.sjtu.edu.cn
--2021-09-26 01:32:15-- http://www.sjtu.edu.cn/
Resolving www.sjtu.edu.cn (www.sjtu.edu.cn)... 202.120.2.119, 2001:da8:8000:6fc0:102:1200:2:48
Connecting to www.sjtu.edu.cn (www.sjtu.edu.cn)|202.120.2.119|:80... connected.
HTTP request sent, awaiting response... 302 Found: Moved Temporarily
```

On guest, we test CPU performance with

```
(guest) $ time echo "scale=5000; 4*a(1)" | bc -l -q # On CentOS VM
... 1m3.173s
```

On host:

```
(host) $ time echo "scale=5000; 4*a(1)" | bc -1 -q # On Ubuntu host ... 11.78s
```

The CPU performance of VM is significantly poorer than Host. This is because we disabled KVM in VM. To enable KVM, append enable-kvm argument at the end of launch command:

```
$ sudo usermod -a -G kvm $USER

$ sudo -E $(which qemu-system-x86_64) -serial stdio \
    -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
    -device virtio-gpu-pci \
    -display default,show-cursor=on \
    -device qemu-xhci -device usb-kbd \
    -device usb-tablet -device intel-hda \
    -device hda-duplex \
    -drive file=centos_disk_0.img,if=virtio,cache=writethrough \
    -nic user,model=virtio,hostfwd=tcp::10122-:22 \
    -enable-kvm
```

See qemu-kvm-start.sh

```
(guest) $ time echo "scale=5000; 4*a(1)" | bc -l -q # On CentOS VM
... 0m15.059s
```

The performance of KVM is acceptable

# OpenVSwitch DPDK

In this section, we install and configure OpenVSwitch and DPDK on Host

### Get DPDK

We install meson and clang:

In our case (Ubuntu 20.04, Intel Core i7 1165G7, gcc 9.3.0 cannot enable SSE4.2 support), therefore we use clang to build DPDK

```
$ sudo apt-get install meson clang
```

Install dpdk

```
$ wget https://fast.dpdk.org/rel/dpdk-20.11.1.tar.xz && tar xf dpdk-20.11.1.tar.xz
$ export DPDK_DIR=$(pwd)/dpdk-stable-20.11.1
$ cd $DPDK_DIR
$ export DPDK_BUILD=$DPDK_DIR/build
```

```
$ export CC=clang
$ meson build
$ ninja -C build
$ sudo ninja -C build install
$ sudo ldconfig
```

Check version

```
$ pkg-config --modversion libdpdk
```

## **OpenVSwitch configuration**

```
$ git clone https://github.com/openvswitch/ovs.git
$ cd ovs
$ git checkout v2.16.0
$ ./boot.sh
$ ./configure --with-dpdk=yes
$ make
$ make
$ make install
export PATH=$PATH:/usr/local/share/openvswitch/scripts
```

Some platfrom might need to enable iommu support. This include modification on /etc/default/grub

```
# In /etc/default/grub, add
GRUB_CMDLINE_LINUX="iommu=pt intel_iommu=on"
```

Run update-grub2 to make changes effective

```
$ update-grub2
```

See setup-dpdk.sh

Start OpenVSwitch with this original bash script

```
#!/bin/bash
# ovs-simple-start.sh
set -e
# ----- BEGIN CONFIGURATION ----- #
ETH_INTERFACE=enp1s0 # Name of ethernet interface
MEM_HUGEPAGE=4096 # Hugepage size
OVSDEV_PCIID=0000:06:00.0
DPDK_DIR=/home/liyutong/Src/dpdk/dpdk-stable-20.11.1 # DPDK installation
OVS_RUN_DIR=/usr/local/var/run/openvswitch # DPDK run dir
OVS_SCRIPT_PATH=/usr/local/share/openvswitch/scripts # OVS script path
# ----- END CONFIGURATION ----- #
DB SOCK=$OVS RUN DIR/db.sock # Place to create db sock
OVSDB_PID=$OVS_RUN_DIR/ovs-vswitchd.pid # Place to store OBSDB pid
if [ ! -d "$OVS_RUN_DIR" ]; then
echo "making dir $OVS_RUN_DIR" && sudo mkdir -p "$OVS_RUN_DIR"
fi
# Kill all ovs process
set +e
sudo killall -9 ovsdb-server
sudo killall -9 ovs-vswitchd
set -e
# Init service
# Dont need on Ubuntu 18.04
# sudo service openvswitch-switch start
# Configure hugepage
echo ">>> Configuring hugepage"
```

```
sudo sysctl -w vm.nr_hugepages=$MEM_HUGEPAGE
 echo $MEM_HUGEPAGE | sudo tee /sys/kernel/mm/hugepages/hugepages-2048kB/nr_hugepages
 grep HugePages_ /proc/meminfo
 sudo mount -t hugetlbfs none /dev/hugepages
 # Set vifo permission
 echo ">>> Configuring vfio-pci"
 dmesg | grep -e DMAR -e IOMMU
 modprobe vfio-pci
 sudo /bin/chmod a+x /dev/vfio
 sudo /bin/chmod 0666 /dev/vfio/*
 # Configure DPDK
 echo ">>> Configuring DPDK"
 sudo $DPDK_DIR/usertools/dpdk-devbind.py --status
 sudo $DPDK_DIR/usertools/dpdk-devbind.py --bind=vfio-pci $ETH_INTERFACE
 sudo $DPDK_DIR/usertools/dpdk-devbind.py --status
 # Create ovsdb
 if [ ! -f "/usr/local/etc/openvswitch/conf.db" ];then
 echo ">>> Creating db"
 sudo ovsdb-tool create /usr/local/etc/openvswitch/conf.db /usr/local/share/openvswitch/vswitch.ovsschema
 fi
 # Start ovsdb
 set +e
 echo ">>> Starting ovsdb"
 sudo ovsdb-server --remote=punix:/usr/local/var/run/openvswitch/db.sock \
              --remote=db:Open_vSwitch,Open_vSwitch,manager_options \
              --private-key=db:Open_vSwitch,SSL,private_key \
              --certificate=db:Open_vSwitch,SSL,certificate \
              --bootstrap-ca-cert=db:Open_vSwitch,SSL,ca_cert \
              --pidfile --detach
 set -e
 # Configure ovs
 echo ">>> Configuring ovs"
 sudo ovs-vsctl --no-wait set Open_vSwitch . other_config:dpdk-init=true
 \#0x06 = 0b110 will use core 2 and core 1
 sudo ovs-vsctl set Open_vSwitch . other_config:pmd-cpu-mask=0x6
 sudo ovs-vsctl set Open_vSwitch . other_config:dpdk-lcore-mask=0x1
 # sudo ovs-vsctl set Open_vSwitch . other_config:dpdk-socket-mem=512
 # Start ovs
 set +e
 echo ">>> Starting ovs"
 sudo $0VS_SCRIPT_PATH/ovs-ctl --no-ovsdb-server --db-sock="$DB_SOCK" start
 set -e
 # Validating
 sudo ovs-vsctl get Open_vSwitch . dpdk_initialized
 sudo ovs-vswitchd --version
The command sudo ovs-vsctl set Open_vSwitch . other_config:dpdk-lcore-mask=0x1 bind dpdk to core O
The command sudo ovs-vsctl set Open_vSwitch . other_config:pmd-cpu-mask=0x6 bind ovs to core 1 and core 2 (0x06 = 0b00110)
  See ovs-simple-start.sh
```

### Creating OpenVSwitch port and bridge

\$ bash ./ovs-simple-start.sh

After the OVS has stated, we create OVS bridges and ports so that our VM can link to OVS

```
$ ovs-vsctl del-port vhost-user-0
$ ovs-vsctl del-br br0
```

vhost-user-0 is the port for VM

We can verify OVS datapath structure with ovs-vsctl

```
$ sudo ovs-vsctl show
21306a7e-21cb-46d8-9e7c-d00575428e6c
    Bridge br0
        datapath_type: netdev
        Port br0
            Interface br0
                type: internal
        Port vhost-user-1
            Interface vhost-user-1
                type: dpdkvhostuserclient
                options: {vhost-server-path="/tmp/sock1"}
        Port vhost-user-0
            Interface vhost-user-0
                type: dpdkvhostuserclient
                options: {vhost-server-path="/tmp/sock0"}
   ovs_version: "2.16.0"
```

## Relaunch QEMU with vhost-user support

```
# Must match -object, size= with -m and less than /sys/kernel/mm/hugepages/hugepages-2048kB/nr_hugepages
$ sudo -E $(which qemu-system-x86_64) -serial stdio \
   -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
   -device virtio-gpu-pci \
   -display default,show-cursor=on \
   -device qemu-xhci -device usb-kbd \
   -device usb-tablet -device intel-hda \
   -device hda-duplex \
   -drive file=centos_disk_0.img,if=virtio,cache=writethrough \
   -nic user,model=virtio,hostfwd=tcp::10122-:22 \
   -enable-kvm \
   -object memory-backend-file,id=mem,size=4096M,mem-path=/dev/hugepages,share=on \
   -mem-prealloc -numa node,memdev=mem \
   -chardev socket,id=char0,path=/tmp/sock0,server=on \
   -netdev type=vhost-user,id=mynet0,chardev=char0,vhostforce=on \
   -device virtio-net-pci, netdev=mynet0, id=net0, mac=00:00:00:00:00:01
```

Since DPDK and OVS use Core 0,1,2. We bind our QEMU VM to Core 3,4,5,6. taskset can bind a process to selected cores

```
$ ps -eLo ruser,pid,ppid,lwp,psr,args | grep qemu|grep -v grep
$ sudo taskset -cp 0x78 $PID # Mask 0b01111000
```

## **Network Profiling**

In this section, we use iperf3 and ping to perform network profiling.

For example:

```
(host) $ iperf3 -s -i 1 -p 1314
(guest) $ iperf3 -c 192.168.1.207 -i 1 -P 30 -t 10 -p 1314
```

By default, qemu guest will be assigned with IP address 10.0.2.15 and host will be assigned with 10.0.2.2

## iperf result

#### virtio

#### 192.168.1.207 (VM-Host) Multiprocess

[SUM]	0.00-10.00	sec	2.33 GBytes	2.00 Gbits/sec	0	sender
[SUM]	0.00-10.00	sec	2.32 GBytes	1.99 Gbits/sec		receiver

#### 192.168.1.131 (VM-LAN) Multiprocess

[SUM]	0.00-10.00	sec	142 MBytes	119 Mbits/sec	0	sender
[SUM]	0.00-10.00	sec	112 MBytes	93.6 Mbits/sec		receiver

#### vhost

#### 192.168.1.207 (VM-Host) Multiprocess

[SUM]	0.00-10.00	sec	2.58 GBytes	2.22 Gbits/sec	0	sender
[SUM]	0.00-10.00	sec	2.57 GBytes	2.21 Gbits/sec		receiver

#### 192.168.1.131 (VM-LAN) Multiprocess

[SUM]	0.00-10.00	sec	134 MBytes	112 Mbits/sec	0	sender
[SUM]	0.00-10.00	sec	113 MBytes	93.9 Mbits/sec		receiver

## ping test result

#### virtio

192.168.1.207 (VM-Host)

```
--- 192.168.1.207 ping statistics ---
10 packets transmitted, 10 received, 0% packet loss, time 9212ms
rtt min/avg/max/mdev = 0.140/0.162/0.183/0.020 ms
```

#### 192.168.1.131 (VM-LAN)

```
packets transmitted, 10 received, 0% packet loss, time 9247ms
rtt min/avg/max/mdev = 0.579/0.718/0.848/0.100 ms
```

#### vhost

192.168.1.207 (VM-Host)

```
--- 192.168.1.207 ping statistics ---
10 packets transmitted, 100 received, 0% packet loss, time 101381ms
rtt min/avg/max/mdev = 0.127/0.154/0.223/0.033 ms
```

### 192.168.1.131 (VM-LAN)

```
10 packets transmitted, 10 received, 0% packet loss, time 9218ms rtt min/avg/max/mdev = 0.535/0.616/0.781/0.075 ms`
```

## **Summary of experiment result**

Network	Iperf (VM-Host)	Iperf (VM-Lan)	Ping (VM-Host)	Ping (VM-LAN)
virtio	1.99GB/s	93.6MB/s	0.020	0.100

vhost	2.21GB/s	93.9MB/s	0.033	0.075
111000	2.2.02/0	00.01112/0	0.000	0.070

We can see that vhost network outperforms virtio network in terms of bandwidth. Their ping results are close

## Multi-Queue

According to the documents, assuming we have M queues. We should set 2M + 2 device vectors and use ethtool to create 2M length processes.

```
# Must match -object, size= with -m and less than /sys/kernel/mm/hugepages/hugepages-2048kB/nr_hugepages
`` sudo -E ``(which qemu-system-x86_64) -serial stdio \
   -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
   -device virtio-gpu-pci \
   -display default,show-cursor=on \
   -device qemu-xhci -device usb-kbd \
   -device usb-tablet -device intel-hda \
   -device hda-duplex \
   -drive file=centos_disk_0.img,if=virtio,cache=writethrough \
   -nic user,model=virtio,hostfwd=tcp::10122-:22 \
   -enable-kvm \
   -object memory-backend-file,id=mem0,size=4096M,mem-path=/dev/hugepages,share=on \
   -mem-prealloc -numa node,memdev=mem0 \
   -chardev socket,id=char0,path=/tmp/sock0,server=on \
   -netdev tap,type=vhost-user,id=vhost-user-0,chardev=char0,vhostforce=on,queues=4 \
   -device virtio-net-pci, netdev=vhost-user-0, mq=on, vectors=
   ,id=net0,mac=00:00:00:00:00:01
 See qemu-multiqueue-start.sh
```

On guest OS, check the interrupts with following command

```
(guest) $ ethtool -L ens7 combined 8
(guest) $ cat /proc/interrupts | grep virtio
29:
             0
                        0
                                    0
                                                                            virtio2-config
                                               0 PCI-MSI 114688-edge
30:
             0
                        0
                                                  PCI-MSI 114689-edge
                                                                            virtio2-input.0
             7
                        1
                                   0
                                                  PCI-MSI 114690-edge
                                                                            virtio2-output.0
31:
                        0
32:
             0
                                   0
                                                  PCI-MSI 114691-edge
                                                                            virtio2-input.1
                        0
33:
             0
                                   0
                                                  PCI-MSI 114692-edge
                                                                            virtio2-output.1
34:
             0
                        0
                                   0
                                                  PCI-MSI 114693-edge
                                                                            virtio2-input.2
             0
                       18
                                  11
                                               0
                                                  PCI-MSI 114694-edge
                                                                            virtio2-output.2
35:
36:
             0
                        0
                                    0
                                                  PCI-MSI 114695-edge
                                                                            virtio2-input.3
37:
                                                  PCI-MSI 114696-edge
                                                                            virtio2-output.3
```

ens7 is the dpdk nic

We can find 8 interrrupts of virtio2-input and virtio2-output.

# Live Migration

We want to migrate VM1 to VM2, so VM2 listen for incoming "PUSH" operation.

In real-world scenario, the virtual disk is stored at a NFS shared path \$SHARED\_PATH/centos\_disk\_0.img, which is accessible for two hosts.

First, we launch VM1(source) with monitor enabled

```
$ SHARED_PATH=.

`` sudo -E ``(which qemu-system-x86_64) \
   -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
   -device virtio-gpu-pci \
   -display default,show-cursor=on \
   -device qemu-xhci -device usb-kbd \
   -device usb-tablet -device intel-hda \
   -device hda-duplex \
```

```
-drive file=$SHARED_PATH/centos_disk_0.img,if=virtio,cache=writethrough \
-nic user,model=virtio,hostfwd=tcp::10122-:22 \
-enable-kvm \
-object memory-backend-file,id=mem,size=4096M,mem-path=/dev/hugepages,share=on \
-mem-prealloc -numa node,memdev=mem \
-chardev socket,id=char0,path=/tmp/sock0,server=on \
-netdev tap,type=vhost-user,id=mynet-0,chardev=char0,vhostforce=on,queues=4 \
-device virtio-net-pci,netdev=mynet-0,mq=on,vectors=10,id=net0,mac=00:00:00:00:00:00:00
-monitor stdio
```

See qemu-migrate-1-start.sh

Second, we create ovs port for VM2 with ovs-vsctl

```
$ ovs-vsctl add-port br0 vhost-user-1 -- set Interface vhost-user-1 \
            type=dpdkvhostuserclient \
            options:vhost-server-path="/tmp/sock1"
$ sudo ovs-vsctl show
21306a7e-21cb-46d8-9e7c-d00575428e6c
    Bridge br0
        datapath_type: netdev
        Port vhost-user-1
            Interface vhost-user-1
                type: dpdkvhostuserclient
                options: {vhost-server-path="/tmp/sock1"}
        Port br0
            Interface br0
                type: internal
        Port vhost-user-0
            Interface vhost-user-0
                type: dpdkvhostuserclient
                options: {vhost-server-path="/tmp/sock0"}
   ovs_version: "2.16.0"
```

We also increase hugeage size:

```
$ echo 8192 > /sys/kernel/mm/hugepages/hugepages-2048kB/nr_hugepages
```

This might not be neccessary since only 1 VM is running at any time, the other one is paused.

Start VM2 with -incoming option:

```
$ SHARED_PATH=.
`` sudo -E ``(which qemu-system-x86_64) \
   -smp 2,sockets=1,cores=2,threads=1 -m 4096 \
   -device virtio-gpu-pci \
   -display default,show-cursor=on \
   -device qemu-xhci -device usb-kbd \
   -device usb-tablet -device intel-hda \
   -device hda-duplex \
   -drive file=$SHARED_PATH/centos_disk_dummy.img,if=virtio,cache=writethrough \
   -nic user,model=virtio,hostfwd=tcp::10123-:22 \
   -enable-kvm \
   -object memory-backend-file,id=mem,size=4096M,mem-path=/dev/hugepages,share=on \
   -mem-prealloc -numa node,memdev=mem \
   -chardev socket,id=char1,path=/tmp/sock1,server=on \
   -netdev tap,type=vhost-user,id=mynet-1,chardev=char1,vhostforce=on,queues=4 \
   -device virtio-net-pci, netdev=mynet-1, mq=on, vectors=10, id=net1, mac=00:00:00:00:00:00:00
   -monitor stdio \
   -incoming tcp:0:16666
```

See qemu-migrate-2-start.sh

When running experiment on a single machine, we cannot mount one qemu disk image to multiple qemu processes. Therefore a dummy disk image centos\_disk\_dummy.img is created. The disk is empty so VM2 will not boot at this point. In real-world

scenario, NFS storage should be used

VM2 will pause. In VM1's monitor, run:

```
(qemu) migrate tcp:$IP:16666
```

After a while, we should be able to connect to VM2 via ssh -p 10123 localhost. The system is migrated

In VM's monitor, run info migrate to fetch migration details

```
(qemu) info migrate
globals:
store-global-state: on
only-migratable: off
send-configuration: on
send-section-footer: on
decompress-error-check: on
clear-bitmap-shift: 18
Migration status: completed
total time: 5503 ms
downtime: 99 ms
setup: 1 ms
transferred ram: 717909 kbytes
throughput: 1074.03 mbps
remaining ram: 0 kbytes
total ram: 4211784 kbytes
duplicate: 876668 pages
skipped: 0 pages
normal: 177205 pages
normal bytes: 708820 kbytes
dirty sync count: 3
page size: 4 kbytes
multifd bytes: 0 kbytes
pages-per-second: 32720
```

The total migrate time is 5503 ms and the downtime is 99ms.

# Appendix - convenient setup script

see ICE6405P-260-M01