Lecture 5

System Calls

Obtaining System Services

 Any application requiring a resource under OS care must request for it using the proper API

Security an issue: how to ensure the OS boundary is crossed safely?

Typical OS services

- File services: create, open, read, write, close
- Terminal I/O
- Network processing
- Memory allocation, protection etc.

syscall()

• Typically, system calls wrapped in library API (such as file I/O)

• To call directly, need to use syscall () library function

syscall() example

```
#define _GNU_SOURCE
#include <unistd.h>
#include <sys/syscall.h>
#include <sys/types.h>
int
main(int argc, char *argv[])
{
    pid_t tid;
    tid = syscall(SYS_gettid);
}
```

System calls in Linux

System calls in Linux is identified by its number

- Example: To read from an opened file requires the read system call. It is **NR read**
 - 3 in /usr/include/asm/unistd 32.h (32 bit systems)
 - 0 in /usr/include/asm/unistd_64.h (64 bit systems)

x86 system calls – the old way

- Uses a software interrupt
 - int 0x80

- Uses the interrupt servicing mechanism to elevate privileges to Ring 0
- But found to be slow
 - There are more things that need to be done to service interrupts in general

The new x86 way

• Uses the **SYSENTER/SYSEXIT** instructions

Executes a fast call to a level 0 system procedure or routine. SYSENTER is a companion instruction to SYSEXIT. The instruction is optimized to provide the maximum performance for system calls from user code running at privilege level 3 to operating system or executive procedures running at privilege level 0.

When executed in IA-32e mode, the SYSENTER instruction transitions the logical processor to 64-bit mode; otherwise, the logical processor remains in protected mode.

Prior to executing the SYSENTER instruction, software must specify the privilege level 0 code segment and code entry point, and the privilege level 0 stack segment and stack pointer by writing values to the following MSRs:

- IA32_SYSENTER_CS (MSR address 174H) The lower 16 bits of this MSR are the segment selector for the privilege level 0 code segment. This value is also used to determine the segment selector of the privilege level 0 stack segment (see the Operation section). This value cannot indicate a null selector.
- IA32_SYSENTER_EIP (MSR address 176H) The value of this MSR is loaded into RIP (thus, this value references the first instruction of the selected operating procedure or routine). In protected mode, only bits 31:0 are loaded.
- IA32_SYSENTER_ESP (MSR address 175H) The value of this MSR is loaded into RSP (thus, this value contains the stack pointer for the privilege level 0 stack). This value cannot represent a non-canonical address. In protected mode, only bits 31:0 are loaded.

In 64 bits: SYSCALL/SYSRET

Introduced by AMD but now also supported in Intel64

Description

SYSCALL invokes an OS system-call handler at privilege level 0. It does so by loading RIP from the IA32_LSTAR MSR (after saving the address of the instruction following SYSCALL into RCX). (The WRMSR instruction ensures that the IA32_LSTAR MSR always contain a canonical address.)

- Both SYSENTER and SYSCALL allows for a disciplined transition from Ring 3 to Ring 0
 - Just how to set up the context is done differently

In Linux

• In arch/x86/kernel/cpu/common.c

```
void syscall_init(void)
{
     wrmsr(MSR_STAR, 0, (__USER32_CS << 16) | __KERNEL_CS);
     wrmsrl(MSR_LSTAR, (unsigned long)entry_SYSCALL_64);</pre>
```

A small digression: x86 Model Specific Registers

 Special control "registers" in the x86 instruction set used for debugging, execution tracing, computer performance monitoring, and operating certain CPU features

- They may or may not be implemented in the processor you have at hand
 - Need to check the model


Using the MSR

- Use **rdmsr** to read a MSR
 - EDX:EAX = MSR[ECX]

- Use wrmsr to write a MSR
 - MSR[ECX] = EDX:EAX
- Must first confirm a particular MSR's existence using the (complicated) **cpuid** instruction

Digression of a digression: CPUID

- Bit 21 (ID bit) of EFLAGS must be 1 to indicate support for CPUID
- Put a value in EAX for a query code
- Values returned in various registers (read the manual)



Linux system calls

- A table of system call service routines is maintained by the kernel
 - sys_call_table[] in arch/x86/entry
 - Note: it is autogenerated at kernel build time from arch/x86/entry/syscalls/syscall_{32|64}.tbl
- The index to the table is the assigned system call number
- arch/x86/entry/common.c contains the dispatch code after SYSENTER/SYSCALL
 - Wrapped in a bit of assembly code in entry {32 | 64 } . S

Summary

- There are only two ways to enter the kernel
 - Via interrupt
 - Using SYSCALL/SYSENTER
 - Important difference: a system call always transits from user to kernel mode, while an interrupt/exception/trap can happen even inside Ring 0

• In 64-bit, Linux expects user to enter the kernel only by the use SYSCALL/SYSENTER instructions

Important digressions

Stacks everywhere

- The modern Linux kernel is multithreaded
 - Need stacks to operate
 - No stack, no procedure call
 - If use user stack, security risk

Interrupts and stacks can happen any time

The stacks used by the kernel


- Per thread kernel stack
- Entry trampoline stack
- Interrupt Stack
- Hard IRQ Stack
- Soft IRQ Stack

Per thread kernel stack

• 16KB

• It is in the task_struct of each process

Grows towards the thread_info structure



Task State Segment

- Intel architecture provisions for OS tasks
 - Hardware task switching not supported in 64 bit mode
- Consists of pointers to stacks
 - 7 IST stacks for interrupt service routine usage
 - One for each protection ring
 - RSPO start of kernel stack. Use for quick access to thread_info
 - RSP1 current top of kernel stack
 - RSP2 scratch to contain user stack pointer on SYSCALL

Although hardware task-switching is not supported in 64-bit mode, a 64-bit task state segment (TSS) must exist. Figure 7-11 shows the format of a 64-bit TSS. The TSS holds information important to 64-bit mode and that is not directly related to the task-switch mechanism. This information includes:

- RSPn The full 64-bit canonical forms of the stack pointers (RSP) for privilege levels 0-2
- ISTn The full 64-bit canonical forms of the interrupt stack table (IST) pointers.
- I/O map base address The 16-bit offset to the I/O permission bit map from the 64-bit TSS base.

The operating system must create at least one 64-bit TSS after activating IA-32e mode. It must execute the LTR instruction (in 64-bit mode) to load the TR register with a pointer to the 64-bit TSS responsible for both 64-bit-mode programs and compatibility-mode programs.

I/O Map Base Address	s Reserved	10
	Reserved	9
	Reserved	
	IST7 (upper 32 bits)	8
	IST7 (lower 32 bits)	8
	IST6 (upper 32 bits)	8
	IST6 (lower 32 bits)	7
	IST5 (upper 32 bits)	7
	IST5 (lower 32 bits)	6
	IST4 (upper 32 bits)	6
	IST4 (lower 32 bits)	6
	IST3 (upper 32 bits)	5
	IST3 (lower 32 bits)	5
	IST2 (upper 32 bits)	4
	IST2 (lower 32 bits)	4
	IST1 (upper 32 bits)	4
	IST1 (lower 32 bits)	3
	Reserved	3
	Reserved	2
	RSP2 (upper 32 bits)	2
	RSP2 (lower 32 bits)	2
	RSP1 (upper 32 bits)	1
	RSP1 (lower 32 bits)	1
	RSP0 (upper 32 bits)	8
	RSP0 (lower 32 bits)	4
	Reserved	0

Figure 7-11. 64-Bit TSS Format

Page Table Isolation

- Full set of kernel page tables use to coexist with user page tables
- Potential security loophole!
- Two separate sets (duplicates) of kernel page tables
 - The full one
 - A minimal one in the user space just sufficient to transit to the kernel
- Implemented on Linux 4.15 onwards

Details of SYSCALL

Hardware execution

What the Intel manual says:

```
Operation
                IF (CS.L \neq 1) or (IA32_EFER.LMA \neq 1) or (IA32_EFER.SCE \neq 1)
                (* Not in 64-Bit Mode or SYSCALL/SYSRET not enabled in IA32_EFER *)
                   THEN #UD:
                 FI;
                RCX := RIP;
                                                     (* Will contain address of next instruction *)
                RIP := IA32_LSTAR;
                R11 := RFLAGS:
                RFLAGS := RFLAGS AND NOT(IA32_FMASK);
                CS.Selector := IA32_STAR[47:32] AND FFFCH (* Operating system provides C5; RPL forced to 0 *)
                (* Set rest of CS to a fixed value *)
                 CS.Base := 0;
                                                         (* Flat segment *)
                 4-680 Vol. 2B
                                                                                                                 SYSCALL—Fast System Call
arch/x86/kernel/cpu/common.c:1752
             void syscall init(void)
                           wrmsr(MSR_STAR, 0, (__USER32_CS << 16) | __KERNEL_CS);
wrmsrl(MSR_LSTAR, (unsigned long)entry_SYSCALL_64);
```

arch/x86/entry/entry 64.S

```
64-bit SYSCALL instruction entry. Up to 6 arguments in registers.
 This is the only entry point used for 64-bit system calls. The
st hardware interface is reasonably well designed and the register to
* argument mapping Linux uses fits well with the registers that are
 available when SYSCALL is used.
* SYSCALL instructions can be found inlined in libc implementations as
^st well as some other programs and libraries. There are also a handful
* of SYSCALL instructions in the vDSO used, for example, as a
* clock gettimeofday fallback.
st 64-bit SYSCALL saves rip to <code>rcx</code>, <code>clears</code> <code>rflags.RF</code>, <code>then</code> <code>saves</code> <code>rflags</code> <code>to</code> <code>rll</code>
st then loads new ss, cs, and rip from previously programmed MSRs.
* rflags gets masked by a value from another MSR (so CLD and CLAC
* are not needed). SYSCALL does not save anything on the stack
* and does not change rsp.
* Registers on entry:
 rax system call number
 rcx return address
* rll saved rflags (note: rll is callee-clobbered register in C ABI)
* rsi arg1
 rdx ara2
 r10 arg3 (needs to be moved to rcx to conform to C_ABI)
     arg4
 r9 arg5
 (note: r12-r15, rbp, rbx are callee-preserved in C ABI)
Only called from user space.
 When user can change pt_regs->foo always force IRET. That is because
* it deals with uncanonical addresses better. SYSRET has trouble
 with them due to bugs in both AMD and Intel CPUs.
```

Pt_regs is the structure for saving all registers.

Defined in

arch/x86/include/uapi/asm/ ptrace.h

arch/x86/entry/entry 64.S

```
SYM CODE START(entry SYSCALL 64)
        UNWIND HINT EMPTY
        swapgs
        /* tss.sp2 is scratch space. */
                %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
        SWITCH TO KERNEL CR3 scratch reg=%rsp
                PER CPU VAR(cpu current top of stack), %rsp
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
        /* Construct struct pt regs on stack */
               $ USER DS
                                                         /* pt regs->ss */
        pushq
               PER CPU VAR(cpu tss rw + TSS sp2)
                                                           pt regs->sp */
        pushq
                                                         /* pt regs->flags */
                %r11
        pushq
                $ USER CS
                                                         /* pt regs->cs */
        pushq
                                                         /* pt regs->ip */
        pushq
                %rcx
SYM INNER LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
        pushq
                                                         /* pt regs->orig ax */
        PUSH AND CLEAR REGS rax=$-ENOSYS
        /* IRQs are off. */
                %rax, %rdi
        movq
                %rsp, %rsi
        movq
        call
                                        /* returns with IRQs disabled */
                do syscall 64
```

Code written in asembly can do funky things to the stack. This makes it hard for debugging tools to follow the stack frame properly as they don't follow the proper calling convention. This is a macro that gives "hints" to such debuggers.

arch/x86/entry/entry_64.S

```
SYM CODE START(entry SYSCALL 64)
       UNWIND HINT EMPTY
       swapgs
       /* tss.sp2 is scratch space. */
               %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
       SWITCH TO KERNEL CR3 scratch reg=%rsp
                PER CPU VAR(cpu current top of stack), %rsp
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
       /* Construct struct pt regs on stack */
               $ USER DS
                                                        /* pt regs->ss */
        pushq
               PER CPU VAR(cpu tss rw + TSS sp2)
        pushq
                                                           pt regs->sp */
                                                         /* pt regs->flags */
        pushq
                %r11
               $ USER CS
                                                        /* pt regs->cs */
        pushq
                                                        /* pt regs->ip */
        pushq
SYM INNER LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
       pushq
                                                        /* pt regs->orig ax */
                %rax
       PUSH AND CLEAR REGS rax=$-ENOSYS
       /* IRQs are off. */
       movq
                %rax, %rdi
               %rsp, %rsi
       movq
       call
                                        /* returns with IRQs disabled */
               do syscall 64
```

GS segment register is used for quick access to the per CPU region so as to get the per-CPU variables quickly.

arch/x86/entry/entry_64.S

```
SYM CODE START(entry SYSCALL 64)
       UNWIND HINT EMPTY
       swapqs
       /* tss.sp2 is scratch space. */
             %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
       SWITCH TO KERNEL CR3 scratch reg=%rsp
               PER CPU VAR(cpu current top of stack), %rsp
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
       /* Construct struct pt regs on stack */
               $ USER DS
                                                        /* pt regs->ss */
        pushq
               PER CPU VAR(cpu tss rw + TSS sp2)
        pushq
                                                           pt regs->sp */
                                                        /* pt_regs->flags */
        pushq
                %r11
               $ USER CS
                                                        /* pt regs->cs */
        pushq
                                                        /* pt regs->ip */
        pushq
SYM INNER LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
       pushq
                                                        /* pt regs->orig ax */
       PUSH AND CLEAR REGS rax=$-ENOSYS
       /* IRQs are off. */
       movq
                %rax, %rdi
               %rsp, %rsi
       movq
       call
                                        /* returns with IRQs disabled */
               do syscall 64
```

saves the user mode stack pointer into a scratch location, namely the **sp2** of the TSS which is also not used since Ring 2 is not used.

arch/x86/entry/entry 64.S

```
SYM CODE START(entry SYSCALL 64)
       UNWIND HINT EMPTY
        swapgs
       /* tss.sp2 is scratch space. */
             %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
       SWITCH TO KERNEL CR3 scratch reg=%rsp
               PER CPU VAR(cpu current top of stack), %rsp
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
       /* Construct struct pt regs on stack */
               $ USER DS
                                                        /* pt regs->ss */
        pushq
               PER CPU VAR(cpu tss rw + TSS sp2)
        pushq
                                                        /* pt regs->sp */
                                                        /* pt regs->flags */
        pushq
                %r11
       pushq
               $ USER CS
                                                        /* pt regs->cs */
                                                        /* pt regs->ip */
        pushq
                %rcx
SYM INNER LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
       pushq
                                                        /* pt regs->orig ax */
                %rax
       PUSH AND CLEAR REGS rax=$-ENOSYS
       /* IRQs are off. */
       movq
               %rax, %rdi
               %rsp, %rsi
       movq
       call
               do syscall 64
                                        /* returns with IRQs disabled */
```

Restore the full kernel page table. Use %rsp as a scratch since it was already saved up.

arch/x86/entry/entry_64.S

```
SYM CODE START(entry SYSCALL 64)
       UNWIND HINT EMPTY
        swapgs
       /* tss.sp2 is scratch space. */
               %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
       SWITCH TO KERNEL CR3 scratch reg=%rsp
               PER CPU VAR(cpu current top of stack), %rsp
       movq
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
       /* Construct struct pt regs on stack */
       pushq
              $ USER DS
                                                        /* pt regs->ss */
               PER CPU VAR(cpu tss rw + TSS sp2)
                                                        /* pt_regs->sp */
       pushq
                                                        /* pt regs->flags */
       pushq
               %r11
       pushq
               $ USER CS
                                                        /* pt regs->cs */
                                                        /* pt regs->ip */
        pushq
                %rcx
SYM INNER LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
       pushq
                                                        /* pt regs->orig ax */
               %rax
       PUSH AND CLEAR REGS rax=$-ENOSYS
       /* IRQs are off. */
       movq
               %rax, %rdi
               %rsp, %rsi
       movq
       call
               do syscall 64
                                        /* returns with IRQs disabled */
```

Switch to true kernel stack.

arch/x86/entry/entry 64.S

```
SYM CODE START(entry SYSCALL 64)
        UNWIND HINT EMPTY
        swapgs
        /* tss.sp2 is scratch space. */
                %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
        SWITCH TO KERNEL CR3 scratch reg=%rsp
                PER CPU VAR(cpu current top of stack), %rsp
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
        /* Construct struct pt regs on stack */
        pushq
               $ USER DS
                                                          /* pt regs->ss */
                PER CPU VAR(cpu tss rw + TSS sp2)
                                                          /* pt_regs->sp */
        pushq
                                                          /* pt regs->flags */
        pushq
                %r11
        pushq
                $ USER CS
                                                         /* pt regs->cs */
                                                         /* pt regs->ip */
        pushq
                %rcx
SYM INN<mark>E</mark>R LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
        pushq
                                                         /* pt regs->orig ax *,
                %rax
        PUSH AND CLEAR REGS rax=$-ENOSYS
        /* IRQs are off. */
        movq
                %rax, %rdi
                %rsp, %rsi
        movq
        call
                do syscall 64
                                         /* returns with IRQs disabled */
```

Saves (some) registers to pt_regs.

arch/x86/entry/entry 64.S

```
SYM CODE START(entry SYSCALL 64)
       UNWIND HINT EMPTY
        swapgs
       /* tss.sp2 is scratch space. */
               %rsp, PER CPU VAR(cpu tss rw + TSS sp2)
       SWITCH TO KERNEL CR3 scratch reg=%rsp
               PER CPU VAR(cpu current top of stack), %rsp
SYM INNER LABEL(entry SYSCALL 64 safe stack, SYM L GLOBAL)
       /* Construct struct pt regs on stack */
       pushq
              $ USER DS
                                                        /* pt regs->ss */
               PER CPU VAR(cpu tss rw + TSS sp2)
                                                        /* pt_regs->sp */
       pushq
                                                        /* pt regs->flags */
       pushq
               %r11
       pushq
               $ USER CS
                                                        /* pt regs->cs */
                                                        /* pt regs->ip */
        pushq
                %rcx
SYM INNER LABEL(entry SYSCALL 64 after hwframe, SYM L GLOBAL)
       pushq
                                                        /* pt regs->orig ax */
               %rax
       PUSH AND CLEAR REGS rax=$-ENOSYS
       /* IRQs are off. */
       movq
                %rax, %rdi
               %rsp, %rsi
       movq
        call
               do syscall 64
                                        /* returns with IRQs disabled */
```

Call the service dispatcher.

arch/x86/entry/common.c

Speeding up system calls (1)

vsyscall

vsyscall

Certain system calls can get called very often

- How to speed it up even faster?
 - Key: do not actually enter the kernel

Executing system call in userspace

- Linux kernel maps a page containing some kernel variables and implementation of some system calls into the user space
 - Key: read only!

Nuts and bolts

Mapping of the vsyscall page occurs in the map_vsyscall function that is defined in the arch/x86/entry/vsyscall/vsyscall_64.c

This is called during kernel initialization

Read only

- Used to be done for gettimeofday(), time() and getcpu()
 - All read only functions
- The vsyscall page contains the variables involved and the small amount of (kernel) code to read them
 - Page is readable, executable but not writable

Deprecated!

- Now deemed too dangerous!
 - Exposing a kernel physical page to the all user processes at a fixed known address

Speeding up system calls (2)

Virtual Dynamic Shared Object

vDSO

 Also same idea as vsyscall but allow linker to do address space randomization (ASR) and place the page anywhere in the virtual space

• Example from two different processes:

Kernel-GLIBC

- Kernel provide the dynamic shared object to the loader
 - vdso{32|64}.so in arch/x86/entry/vdso
- Kernel detects loading of shared executable, will then provide the shared object in the process image

Final setup done by glibc ELF startup code

END