

RMAN CONFIGURATION PARAMETERS

1: CONFIGURE RETENTION POLICY TO REDUNDANCY 1; # default

To set this parameter type --->>>CONFIGURE RETENTION POLICY TO REDUNDANCY 7; This parameter kept save 7 days old to current backup mean's. Assume

the current backup is 25thMay the rman kept save backup till 18thMAy. To set default value type:

CONFIGURE RETENTION POLICY clear;

2: CONFIGURE BACKUP OPTIMIZATION OFF; # default

To set this parameter type--->>>> CONFIGURE BACKUP OPTIMIZATION ON; This parameter check whether the backup is already exist are not if yes its check (dbid, checkpoint, and reset logs data) IF not It takes the backup. To set default value type:

CONFIGURE BACKUP OPTIMIZATION CLEAR;

3: CONFIGURE CHANNEL DEVICE TYPE DISK.

TO set this parameter type ---->>> CONFIGURE CHANNEL DEVICE TYPE DISK FORMAT '/u01/backup/%U'; this parameter takes backup on your choice destination but for this u must have to make directory manually on your location. (%U means the RMAN make backup file with unique name's). To set default value type

4: CONFIGURE CONTROLFILE AUTOBACKUP OFF; # default

To set this parameter type --->>> CONFIGURE CONTROLFILE AUTOBACKUP ON; This parameter take's auto backup of control file when u take backup of control file Rman takes controlfile backup in your backup destination but also takes control file backup in this destination automatically /u01/app/oracle/flash_recovery_area/PRIMARY/autobackup/; To set default value type:

CONFIGURE CONTROLFILE AUTOBACKUP clear;

5: CONFIGURE CONTROLFILE AUTOBACKUP FORMAT FOR DEVICE TYPE DISK TO '%F'; # default

To set this parameter type---->>>> CONFIGURE CONTROLFILE AUTOBACKUP FORMAT FOR DEVICE TYPE DISK TO '/u01/control/%F'; To set this parameter u should make to your own choice destination AND must set this parameter CONFIGURE CONTROLFILE AUTOBACKUP ON for auto backup of control file. To set default value type:

CONFIGURE CONTROLFILE AUTOBACKUP FORMAT FOR DEVICE TYPE DISK clear;

6: CONFIGURE DEVICE TYPE DISK PARALLELISM 1 BACKUP TYPE TO BACKUPSET; # default



consultant.mubashir@gmail.com

To set this parameter type ---->>> CONFIGURE DEVICE TYPE DISK PARALLELISM 4 BACKUP TYPE TO BACKUPSET; This parameter increase the number workers to take backup fast with 4 worker's which u set.

7: CONFIGURE DATAFILE BACKUP COPIES FOR DEVICE TYPE DISK TO 1; # default

To set this parameter type ---->>> CONFIGURE DATAFILE BACKUP COPIES FOR DEVICE TYPE DISK TO 4; now This parameter can take 4 backup copy of single backup FOR example: if u type RMAN>> backup current control file it takes 4 backup of controlfile; To set default value type:

CONFIGURE DATAFILE BACKUP COPIES FOR DEVICE TYPE DISK clear;

backup spfile format '/u01/rman/%U','/u01/bbc/%U','/u01/pak/%U','/u01/abc/%U'; <--four backup at a time.

8: CONFIGURE ARCHIVELOG BACKUP COPIES FOR DEVICE TYPE DISK TO 1; # default

To set this parameter type CONFIGURE ARCHIVELOG BACKUP COPIES FOR DEVICE TYPE DISK TO 4; now this parameter can take backup of single archive 4 time;

To set default value type:

CONFIGURE DATAFILE BACKUP COPIES FOR DEVICE TYPE DISK clear;

9: CONFIGURE CHANNEL DEVICE TYPE DISK MAXPIECESIZE UNLIMITED;

To set this parameter---->>> CONFIGURE CHANNEL DEVICE TYPE DISK MAXPIECESIZE 500M; This parameter can make's your backup files in 500mb chunks.

To set default value type:

CONFIGURE MAXSETSIZE CLEAR;

10: For speed up the performance of rman backup; depends upon your core

```
ALLOCATE CHANNEL c1 DEVICE TYPE DISK; ALLOCATE CHANNEL c2 DEVICE TYPE DISK; ALLOCATE CHANNEL c3 DEVICE TYPE DISK; ALLOCATE CHANNEL c4 DEVICE TYPE DISK;
```

11: CONFIGURE DEFAULT DEVICE TYPE TO DISK; # default

To run this command type:

CONFIGURE DEVICE TYPE DISK BACKUP TYPE TO COMPRESSED BACKUPSET.

To clear type:

CONFIGURE DEVICE TYPE DISK clear;



consultant.mubashir@gmail.com

12: FOR COMPRRESSED AND UNCOMPREESED BACKUP;

CONFIGURE DEVICE TYPE DISK BACKUP TYPE TO BACKUPSET; # uncompressed CONFIGURE DEVICE TYPE DISK BACKUP TYPE TO COMPRESSED BACKUPSET; CONFIGURE DEVICE TYPE sbt BACKUP TYPE TO COMPRESSED BACKUPSET;

- 13: CONFIGURE CHANNEL DEVICE TYPE DISK MAXPIECESIZE 50M; <-----for making chunks CONFIGURE CHANNEL DEVICE TYPE DISK MAXPIECESIZE clear;
- 14: CONFIGURE ENCRYPTION FOR DATABASE OFF; # default for encryption
- 15: CONFIGURE ENCRYPTION ALGORITHM 'AES128'; # default for encrypted algorithm
- 16: CONFIGURE ARCHIVELOG DELETION POLICY TO NONE; # default for archive log deletion
- 17: CONFIGURE ARCHIVELOG DELETION POLICY TO BACKED UP 1 TIMES TO DISK; archive log deletion policy