





Priority Ceiling Protocol - Resource Access Protocols

A study of concurrency control mechanisms in real-time systems — from basic semaphores to advanced protocols that bound priority inversion and guarantee schedulability.

PREPARED BY CHIMEZIE DANIEL CHIDI 1230515



Resources, Critical Sections & Semaphores

Private Resource

Dedicated to a single process.

Shared Resource


Accessible by multiple tasks.

Exclusive Resource

Shared but protected against concurrent access.

A **critical section** is code executed under mutual exclusion. Tasks use **semaphores** via *wait/signal* primitives. Blocked tasks enter a **WAIT** state, then return to **READY** (not RUN) when signaled.

The Priority Inversion Phenomenon



What Is It?

A high-priority task is forced to wait for lower-priority tasks holding a shared resource — potentially **unboundedly**.

Classic Scenario

τ_3 holds a resource $\rightarrow \tau_1$ preempts and blocks $\rightarrow \tau_2$ (medium priority) preempts τ_3 , extending τ_1 's wait beyond τ_3 's critical section.



Any intermediate-priority task can prolong blocking, causing critical deadlines to be missed.

Five Resource Access Protocols

01

Non-Preemptive Protocol (NPP)

Disables preemption inside all critical sections.

02

Highest Locker Priority (HLP)

Raises priority to the resource's *ceiling* on entry.

03

Priority Inheritance Protocol (PIP)

Blocking tasks inherit the highest blocked priority.

04

Priority Ceiling Protocol (PCP)

Denies lock if priority $\leq$ any locked semaphore's ceiling.

05

Stack Resource Policy (SRP)

Blocks at preemption time; supports EDF and stack sharing.

Non-Preemptive & Highest Locker Priority

NPP

Raises task priority to the system maximum inside any critical section. Simple, but causes **unnecessary blocking** — even high-priority tasks not sharing the resource are blocked.

Max blocking: longest critical section of any lower-priority task.

HLP / IPC

Raises priority to the **resource ceiling** — the highest priority of tasks sharing that resource.

Bounds blocking to **one critical section**. More precise than NPP, but may block before the resource is actually needed.

Priority Inheritance Protocol (PIP)

Direct Blocking

High-priority task waits for a lower-priority task holding a needed resource.


Push-Through Blocking

Medium-priority task blocked by a low-priority task that inherited a higher priority.

Transitive Inheritance

If τ_3 blocks τ_2 and τ_2 blocks τ_1 , then τ_3 inherits τ_1 's priority via τ_2 .

Under PIP, τ_i can be blocked at most $\alpha_i = \min(l_i, s_i)$ critical sections, where l_i = lower-priority tasks that can block, s_i = distinct blocking semaphores.



PIP: Chained Blocking & Deadlock


Chained Blocking

If τ_1 accesses n semaphores each locked by a different lower-priority task, it can be blocked for **n critical sections** — still bounded, but potentially substantial.

Deadlock

PIP does **not** prevent deadlocks. Two tasks nesting semaphores in reverse order can deadlock. Solution: impose a **total ordering** on semaphore accesses.

Priority Ceiling Protocol (PCP)



Core Rule

A task may enter a critical section only if its priority is **higher** than the ceiling of all semaphores currently locked by other tasks.

Key Properties

- Blocks at most **one** critical section
- **Prevents deadlocks** by construction
- **Prevents chained blocking**
- Introduces **ceiling blocking** as a third form

Stack Resource Policy (SRP)

Preemption Test

Task τ may run only if $\pi(\tau) > \Pi_s$ (system ceiling). Blocks at **preemption time**, not access time.

Dynamic Priorities


Supports both fixed-priority (RM) and dynamic (EDF) scheduling natively.

Stack Sharing

Tasks share a single stack — saves up to **90%** memory with many tasks across few preemption levels.

Multi-Unit Resources

Generalizes PCP to resources with multiple concurrent units.



PCP_UPPAAL Analysis

PCP_Submission_Ready.xml - UPPAAL

File Edit View Tools Options Help

Editor Symbolic Simulator Concrete Simulator Verifier

Overview

A[] not deadlock
A[] not (T1.Critical and T2.Critical and owner[R1] = owner[R2])
A[] not (T1.Critical and T3.Critical)
A[] T1.Critical imply owner[R1] = 1
A[] T2.Critical imply owner[R2] = 2
A[] T3.Critical imply owner[R1] = 3
E<> T1.Critical
E<> T2.Critical
E<> T3.Critical
A[] locked[R1] imply owner[R1] ≠ FREE
A[] locked[R2] imply owner[R2] ≠ FREE

Protocol	Definition	Blocking	Deadlock Free	Priority Type	Complexity
NPP (Non-Preemptive Protocol)	Disables preemption while inside a critical section.	1 CS	✓	Any	Easy
HLP (Highest Locker Priority)	Task inherits the ceiling priority of the resource it locks.	1 CS	✓	Fixed	Easy
PIP (Priority Inheritance Protocol)	Resource holder inherits the priority of the highest blocked task.	α_i	✗	Fixed	Hard
PCP (Priority Ceiling Protocol)	Task can lock a resource only if its priority exceeds the current system ceiling.	1 CS	✓	Fixed	Medium
SRP (Stack Resource Policy)	Blocks tasks at preemption time using a system ceiling; supports stack sharing.	1 CS	✓	Any (RM/EDF)	Easy

THANK YOU !

EXTRA – FOR MY PERSONAL REFERENCE