cpu-hotplug.txt CPU hotplug Support in Linux(tm) Kernel

Maintainers:

CPU Hotplug Core:

Rusty Russell <rusty@rustycorp.com.au> Srivatsa Vaddagiri <vatsa@in.ibm.com>

i386:

Zwane Mwaikambo <zwane@arm.linux.org.uk>

ppc64:

Nathan Lynch <nathanl@austin.ibm.com> Joel Schopp <jschopp@austin.ibm.com>

ia64/x86 64:

Āshok Raj ⟨ashok.raj@intel.com⟩

s390:

Heiko Carstens <a heiko.carstens@de.ibm.com>

Authors: Ashok Raj <ashok.raj@intel.com>

Lots of feedback: Nathan Lynch <nathanl@austin.ibm.com>,

Joel Schopp <jschopp@austin.ibm.com>

Introduction

Modern advances in system architectures have introduced advanced error reporting and correction capabilities in processors. CPU architectures permit partitioning support, where compute resources of a single CPU could be made available to virtual machine environments. There are couple OEMS that support NUMA hardware which are hot pluggable as well, where physical node insertion and removal require support for CPU hotplug.

Such advances require CPUs available to a kernel to be removed either for provisioning reasons, or for RAS purposes to keep an offending CPU off system execution path. Hence the need for CPU hotplug support in the Linux kernel.

A more novel use of CPU-hotplug support is its use today in suspend resume support for SMP. Dual-core and HT support makes even a laptop run SMP kernels which didn't support these methods. SMP support for suspend/resume is a work in progress.

General Stuff about CPU Hotplug

Command Line Switches

maxcous=n

Restrict boot time cpus to n. Say if you have 4 cpus, using maxcpus=2 will only boot 2. You can choose to bring the other cpus later online, read FAQ's for more info.

additional_cpus=n (*) Use this to limit hotpluggable cpus. This option sets cpu_possible_map = cpu_present_map + additional_cpus

cede_offline={"off","on"}
Use this option to disable/enable putting offlined processors to an extended H_CEDE state on supported pseries platforms.

If nothing is specified, cede_offline is set to "on".

第 1 页

(*) Option valid only for following architectures - ia64

ia64 uses the number of disabled local apics in ACPI tables MADT to determine the number of potentially hot-pluggable cpus. The implementation should only rely on this to count the # of cpus, but *MUST* not rely on the apicid values in those tables for disabled apics. In the event BIOS doesn't mark such hot-pluggable cpus as disabled entries, one could use this parameter "additional_cpus=x" to represent those cpus in the cpu possible map.

possible_cpus=n

[s390, x86_64] use this to set hotpluggable cpus. This option sets possible_cpus bits in cpu_possible_map. Thus keeping the numbers of bits set constant even if the machine gets rebooted.

CPU maps and such

[More on cpumaps and primitive to manipulate, please check include/linux/cpumask.h that has more descriptive text.]

cpu_possible_map: Bitmap of possible CPUs that can ever be available in the system. This is used to allocate some boot time memory for per_cpu variables that aren't designed to grow/shrink as CPUs are made available or removed. Once set during boot time discovery phase, the map is static, i.e no bits are added or removed anytime. Trimming it accurately for your system needs upfront can save some boot time memory. See below for how we use heuristics in x86_64 case to keep this under check.

cpu_online_map: Bitmap of all CPUs currently online. Its set in __cpu_up() after a cpu is available for kernel scheduling and ready to receive interrupts from devices. Its cleared when a cpu is brought down using __cpu_disable(), before which all OS services including interrupts are migrated to another target CPU.

cpu_present_map: Bitmap of CPUs currently present in the system. Not all of them may be online. When physical hotplug is processed by the relevant subsystem (e.g ACPI) can change and new bit either be added or removed from the map depending on the event is hot-add/hot-remove. There are currently no locking rules as of now. Typical usage is to init topology during boot, at which time hotplug is disabled.

You really dont need to manipulate any of the system cpu maps. They should be read-only for most use. When setting up per-cpu resources almost always use cpu possible map/for each possible cpu() to iterate.

Never use anything other than cpumask t to represent bitmap of CPUs.

#include linux/cpumask.h>

for_each_possible_cpu - Iterate over cpu_possible_map for_each_online_cpu - Iterate over cpu_online_map for_each_present_cpu - Iterate over cpu_present_map for each cpu mask(x, mask) - Iterate over some random collection of cpu

mask.

```
#include linux/cpu.h>
get online cpus() and put online cpus():
```

The above calls are used to inhibit cpu hotplug operations. While the cpu_hotplug.refcount is non zero, the cpu_online_map will not change. If you merely need to avoid cpus going away, you could also use preempt_disable() and preempt_enable() for those sections. Just remember the critical section cannot call any function that can sleep or schedule this process away. The preempt_disable() will work as long as stop_machine_run() is used to take a cpu down.

CPU Hotplug - Frequently Asked Questions.

Q: How to enable my kernel to support CPU hotplug?

A: When doing make defconfig, Enable CPU hotplug support

"Processor type and Features" -> Support for Hotpluggable CPUs

Make sure that you have CONFIG HOTPLUG, and CONFIG SMP turned on as well.

You would need to enable ${\tt CONFIG_HOTPLUG_CPU}$ for ${\tt SMP}$ suspend/resume support as well.

Q: What architectures support CPU hotplug?

A: As of 2.6.14, the following architectures support CPU hotplug.

i386 (Intel), ppc, ppc64, parisc, s390, ia64 and x86 64

Q: How to test if hotplug is supported on the newly built kernel?

A: You should now notice an entry in sysfs.

Check if sysfs is mounted, using the "mount" command. You should notice an entry as shown below in the output.

```
none on /sys type sysfs (rw) \dots
```

If this is not mounted, do the following.

```
#mkdir /sysfs
#mount -t sysfs sys /sys
```

Now you should see entries for all present cpu, the following is an example in a 8-way system.

```
#pwd
#/sys/devices/system/cpu
#1s -1
total 0
drwxr-xr-x 10 root root 0 Sep 19 07:44.
drwxr-xr-x 13 root root 0 Sep 19 07:45..
drwxr-xr-x 3 root root 0 Sep 19 07:44 cpu0
drwxr-xr-x 3 root root 0 Sep 19 07:44 cpu1
drwxr-xr-x 3 root root 0 Sep 19 07:44 cpu1
gryph 3 页
```

```
      drwxr-xr-x
      3 root root 0 Sep 19 07:44 cpu3

      drwxr-xr-x
      3 root root 0 Sep 19 07:44 cpu4

      drwxr-xr-x
      3 root root 0 Sep 19 07:44 cpu5

      drwxr-xr-x
      3 root root 0 Sep 19 07:44 cpu6

      drwxr-xr-x
      3 root root 0 Sep 19 07:48 cpu7
```

Under each directory you would find an "online" file which is the control file to logically online/offline a processor.

Q: Does hot-add/hot-remove refer to physical add/remove of cpus?
A: The usage of hot-add/remove may not be very consistently used in the code.
CONFIG_HOTPLUG_CPU enables logical online/offline capability in the kernel.
To support physical addition/removal, one would need some BIOS hooks and the platform should have something like an attention button in PCI hotplug.
CONFIG ACPI HOTPLUG CPU enables ACPI support for physical add/remove of CPUs.

Q: How do i logically offline a CPU?

A: Do the following.

#echo 0 > /sys/devices/system/cpu/cpuX/online

Once the logical offline is successful, check

#cat /proc/interrupts

You should now not see the CPU that you removed. Also online file will report the state as 0 when a cpu if offline and 1 when its online.

#To display the current cpu state.
#cat /sys/devices/system/cpu/cpuX/online

Q: Why cant i remove CPUO on some systems?

A: Some architectures may have some special dependency on a certain CPU.

For e.g in IA64 platforms we have ability to sent platform interrupts to the OS. a.k.a Corrected Platform Error Interrupts (CPEI). In current ACPI specifications, we didn't have a way to change the target CPU. Hence if the current ACPI version doesn't support such re-direction, we disable that CPU by making it not-removable.

In such cases you will also notice that the online file is missing under cpu0.

Q: How do i find out if a particular CPU is not removable? A: Depending on the implementation, some architectures may show this by the absence of the "online" file. This is done if it can be determined ahead of time that this CPU cannot be removed.

In some situations, this can be a run time check, i.e if you try to remove the last CPU, this will not be permitted. You can find such failures by investigating the return value of the "echo" command.

Q: What happens when a CPU is being logically offlined? A: The following happen, listed in no particular order :-)

- A notification is sent to in-kernel registered modules by sending an event CPU_DOWN_PREPARE or CPU_DOWN_PREPARE_FROZEN, depending on whether or not the 第 4 页

CPU is being offlined while tasks are frozen due to a suspend operation in progress

- All processes are migrated away from this outgoing CPU to new CPUs. The new CPU is chosen from each process' current cpuset, which may be a subset of all online CPUs.
- All interrupts targeted to this CPU is migrated to a new CPU
- timers/bottom half/task lets are also migrated to a new CPU
- Once all services are migrated, kernel calls an arch specific routine cpu disable() to perform arch specific cleanup.
- Once this is successful, an event for successful cleanup is sent by an event CPU_DEAD (or CPU_DEAD_FROZEN if tasks are frozen due to a suspend while the CPU is being offlined).

"It is expected that each service cleans up when the CPU_DOWN_PREPARE notifier is called, when CPU_DEAD is called its expected there is nothing running on behalf of this CPU that was offlined"

Q: If i have some kernel code that needs to be aware of CPU arrival and departure, how to i arrange for proper notification?

A: This is what you would need in your kernel code to receive notifications.

```
#include ux/cpu.h>
static int __cpuinit foobar_cpu_callback(struct notifier block *nfb,
                                     unsigned long action, void *hcpu)
        unsigned int cpu = (unsigned long)hcpu;
        switch (action) {
        case CPU_ONLINE:
        case CPU ONLINE FROZEN:
                foobar online action(cpu);
                break;
        case CPU DEAD:
        case CPU DEAD FROZEN:
                foobar dead action(cpu):
                break:
        return NOTIFY OK;
}
static struct notifier_block __cpuinitdata foobar_cpu_notifer =
   .notifier_call = foobar_cpu_callback,
};
```

You need to call register_cpu_notifier() from your init function. Init functions could be of two types:

1. early init (init function called when only the boot processor is online).

2. late init (init function called _after_ all the CPUs are online).

For the first case, you should add the following to your init function

```
register cpu notifier(&foobar cpu notifier);
```

For the second case, you should add the following to your init function

```
cpu-hotplug.txt
register_hotcpu_notifier(&foobar_cpu_notifier);
```

You can fail PREPARE notifiers if something doesn't work to prepare resources. This will stop the activity and send a following CANCELED event back.

CPU_DEAD should not be failed, its just a goodness indication, but bad things will happen if a notifier in path sent a BAD notify code.

Q: I don't see my action being called for all CPUs already up and running?
A: Yes, CPU notifiers are called only when new CPUs are on-lined or offlined.
If you need to perform some action for each cpu already in the system, then

```
for_each_online_cpu(i) {
          foobar_cpu_callback(&foobar_cpu_notifier, CPU_UP_PREPARE, i);
          foobar_cpu_callback(&foobar_cpu_notifier, CPU_ONLINE, i);
}
```

- Q: If i would like to develop cpu hotplug support for a new architecture, what do i need at a minimum?
- A: The following are what is required for CPU hotplug infrastructure to work correctly.
 - Make sure you have an entry in Kconfig to enable CONFIG_HOTPLUG_CPU
 - __cpu_up() Arch interface to bring up a CPU
 - __cpu_disable() Arch interface to shutdown a CPU, no more interrupts can be handled by the kernel after the routine returns. Including local APIC timers etc are shutdown.
 - __cpu_die()

 This actually supposed to ensure death of the CPU.

 Actually look at some example code in other arch
 that implement CPU hotplug. The processor is taken
 down from the idle() loop for that specific
 architecture. __cpu_die() typically waits for some
 per_cpu state to be set, to ensure the processor
 dead routine is called to be sure positively.
- Q: I need to ensure that a particular cpu is not removed when there is some work specific to this cpu is in progress.
- A: There are two ways. If your code can be run in interrupt context, use smp_call_function_single(), otherwise use work_on_cpu(). Note that work_on_cpu() is slow, and can fail due to out of memory:

```
int my_func_on_cpu(int cpu)
{
    int err;
        get_online_cpus();
    if (!cpu_online(cpu))
        err = -EINVAL;
    else
#if NEEDS_BLOCKING

    err = work_on_cpu(cpu, __my_func_on_cpu, NULL);
#else
        smp_call_function_single(cpu, __my_func_on_cpu, &err, true);
#endif

put online cpus();
```

return err;

}

Q: How do we determine how many CPUs are available for hotplug.

A: There is no clear spec defined way from ACPI that can give us that information today. Based on some input from Natalie of Unisys, that the ACPI MADT (Multiple APIC Description Tables) marks those possible CPUs in a system with disabled status.

Andi implemented some simple heuristics that count the number of disabled CPUs in MADT as hotpluggable CPUS. In the case there are no disabled CPUS we assume 1/2 the number of CPUs currently present can be hotplugged.

Caveat: Today's ACPI MADT can only provide 256 entries since the apicid field in MADT is only 8 bits.

User Space Notification

Hotplug support for devices is common in Linux today. Its being used today to support automatic configuration of network, usb and pci devices. A hotplug event can be used to invoke an agent script to perform the configuration task.

You can add /etc/hotplug/cpu.agent to handle hotplug notification user space scripts.

```
#!/bin/bash
# $Id: cpu.agent
# Kernel hotplug params include:
#ACTION=%s [online or offline]
#DEVPATH=%s
cd /etc/hotplug
. ./hotplug.functions
case $ACTION in
        online)
                echo `date` ":cpu.agent" add cpu >> /tmp/hotplug.txt
        offline)
                echo date ":cpu.agent" remove cpu >>/tmp/hotplug.txt
        *)
                debug mesg CPU $ACTION event not supported
exit 1
; ;
esac
```