kbuild.txt

Out	nut	fi	100
out	put	$_{\rm II}$	res

1 1	I		1
modu	Les.	orc	ler

This file records the order in which modules appear in Makefiles. This is used by modprobe to deterministically resolve aliases that match multiple modules.

modules. builtin

This file lists all modules that are built into the kernel. This is used by modprobe to not fail when trying to load something builtin.

Environment variables

KCPPFLAGS

Additional options to pass when preprocessing. The preprocessing options will be used in all cases where kbuild does preprocessing including building C files and assembler files.

KAFLAGS

Additional options to the assembler.

KCFLAGS

Additional options to the C compiler.

KBUILD VERBOSE

Set the kbuild verbosity. Can be assigned same values as "V=...".

See make help for the full list. Setting "V=..." takes precedence over KBUILD_VERBOSE.

KBUILD EXTMOD

Set the directory to look for the kernel source when building external modules.

The directory can be specified in several ways:
1) Use "M=..." on the command line
2) Environmnet variable KBUILD_EXTMOD

- 3) Environment variable SUBDIRS

The possibilities are listed in the order they take precedence.

Using "M=..." will always override the others.

KBUILD OUTPUT

Specify the output directory when building the kernel. The output directory can also be specificed using "0=...". Setting "0=..." takes precedence over KBUILD OUTPUT.

ARCH

Set ARCH to the architecture to be built.

kbuild. txt

In most cases the name of the architecture is the same as the directory name found in the arch/directory. But some architectures such as x86 and sparc have aliases. x86: i386 for 32 bit, x86 64 for 64 bit sparc: sparc for 32 bit, sparc64 for 64 bit

CROSS COMPILE

Specify an optional fixed part of the binutils filename. CROSS COMPILE can be a part of the filename or the full path.

CROSS COMPILE is also used for ccache in some setups.

CF

Additional options for sparse.

CF is often used on the command-line like this:

make CF=-Wbitwise C=2

INSTALL PATH

INSTALL PATH specifies where to place the updated kernel and system map images. Default is /boot, but you can set it to other values.

INSTALLKERNEL.

Install script called when using "make install". The default name is "installkernel".

The script will be called with the following arguments:

\$1 - kernel version

\$2 - kernel image file

\$3 - kernel map file

\$4 - default install path (use root directory if blank)

The implmentation of "make install" is architecture specific and it may differ from the above.

INSTALLKERNEL is provided to enable the possibility to specify a custom installer when cross compiling a kernel.

MODLIB

Specify where to install modules.

The default value is:

\$(INSTALL MOD PATH)/lib/modules/\$(KERNELRELEASE)

The value can be overridden in which case the default value is ignored.

INSTALL MOD PATH

INSTALL MOD PATH specifies a prefix to MODLIB for module directory

relocations required by build roots. This is not defined in the makefile but the argument can be passed to make if needed.

第 2 页

kbuild.txt

INSTALL MOD STRIP

INSTALL_MOD_STRIP, if defined, will cause modules to be stripped after they are installed. If INSTALL_MOD_STRIP is '1', then the default option --strip-debug will be used. Otherwise,

INSTALL_MOD_STRIP will used as the options to the strip command.

INSTALL FW PATH

 $\label{thm:local_to_thm} \begin{tabular}{ll} INSTALL_FW_PATH specifies where to install the firmware blobs. \\ The default value is: \end{tabular}$

\$(INSTALL_MOD_PATH)/lib/firmware

The value can be overridden in which case the default value is ignored.

INSTALL HDR PATH

INSTALL_HDR_PATH specifies where to install user space headers when executing "make headers_*". The default value is:

\$(objtree)/usr

\$(objtree) is the directory where output files are saved. The output directory is often set using "0=..." on the commandline.

The value can be overridden in which case the default value is ignored.

KBUILD MODPOST WARN

KBUILD_MODPOST_WARN can be set to avoid errors in case of undefined symbols in the final module linking stage. It changes such errors into warnings.

KBUILD MODPOST NOFINAL

KBUILD_MODPOST_NOFINAL can be set to skip the final link of modules. This is solely useful to speed up test compiles.

KBUILD EXTRA SYMBOLS

For modules that use symbols from other modules. See more details in modules.txt.

ALLSOURCE ARCHS

For tags/TAGS/cscope targets, you can specify more than one arch to be included in the databases, separated by blank space. E.g.:

\$ make ALLSOURCE_ARCHS="x86 mips arm" tags

To get all available archs you can also specify all. E.g.:

\$ make ALLSOURCE ARCHS=all tags