printk-formats.txt use printk format specifier:

If variable is of Type,

%d or %x unsigned int %u or %x long %1d or %1x unsigned long %lu or %lx %11d or %11x long long unsigned long long %11u or %11x %zu or %zx size t %zd or %zx ssize t

Raw pointer value SHOULD be printed with %p.

u64 SHOULD be printed with %11u/%11x, (unsigned long long):

printk("%11u", (unsigned long long)u64_var);

s64 SHOULD be printed with %11d/%11x, (long long):

printk("%11d", (long long)s64 var);

If \langle type \rangle is dependent on a config option for its size (e.g., sector_t, blkcnt_t, phys_addr_t, resource_size_t) or is architecture-dependent for its size (e.g., tcflag t), use a format specifier of its largest possible type and explicitly cast to it. Example:

> printk("test: sector number/total blocks: %11u/%11u\n", (unsigned long long) sector, (unsigned long long) blockcount);

Reminder: sizeof() result is of type size_t.

Thank you for your cooperation and attention.

By Randy Dunlap <rdunlap@xenotime.net>