## binfmt misc.txt

Kernel Support for miscellaneous (your favourite) Binary Formats v1.1

This Kernel feature allows you to invoke almost (for restrictions see below) every program by simply typing its name in the shell. This includes for example compiled Java(TM), Python or Emacs programs.

To achieve this you must tell binfmt\_misc which interpreter has to be invoked with which binary. Binfmt\_misc recognises the binary-type by matching some bytes at the beginning of the file with a magic byte sequence (masking out specified bits) you have supplied. Binfmt\_misc can also recognise a filename extension aka '.com' or '.exe'.

First you must mount binfmt\_misc:
 mount binfmt\_misc -t binfmt\_misc /proc/sys/fs/binfmt\_misc

To actually register a new binary type, you have to set up a string looking like :name:type:offset:magic:mask:interpreter:flags (where you can choose the ':' upon

your needs) and echo it to /proc/sys/fs/binfmt\_misc/register. Here is what the fields mean:

- 'name' is an identifier string. A new /proc file will be created with this name below /proc/sys/fs/binfmt\_misc

- 'type' is the type of recognition. Give 'M' for magic and 'E' for extension. - 'offset' is the offset of the magic/mask in the file, counted in bytes. This

defaults to 0 if you omit it (i.e. you write ':name:type::magic...')

- 'magic' is the byte sequence binfmt\_misc is matching for. The magic string may contain hex-encoded characters like \x0a or \xA4. In a shell environment you will have to write \x0a to prevent the shell from eating your \. If you chose filename extension matching, this is the extension to be recognised (without the '.', the \x0a specials are not allowed). Extension matching is case sensitive!

- 'mask' is an (optional, defaults to all Oxff) mask. You can mask out some bits from matching by supplying a string like magic and as long as magic.

The mask is anded with the byte sequence of the file.

- 'interpreter' is the program that should be invoked with the binary as first argument (specify the full path)

- 'flags' is an optional field that controls several aspects of the invocation of the interpreter. It is a string of capital letters, each controls a certain

aspect. The following flags are supported -

'P' - preserve-argv[0]. Legacy behavior of binfmt\_misc is to overwrite the

original argv[0] with the full path to the binary. When this flag

included,  ${\tt binfmt\_misc}$  will add an argument to the argument vector

this purpose, thus preserving the original argv[0].

'0' - open-binary. Legacy behavior of binfmt\_misc is to pass the full path of the binary to the interpreter as an argument. When this flag is included, binfmt\_misc will open the file for reading and pass its descriptor as an argument, instead of the full path, thus allowing the interpreter to execute non-readable binaries. This feature

should

is

for

be used with care - the interpreter has to be trusted not to emit the contents of the non-readable binary.

## binfmt misc.txt

'C' - credentials. Currently, the behavior of binfmt\_misc is to calculate the credentials and security token of the new process according to the interpreter. When this flag is included, these attributes are calculated according to the binary. It also implies the 'O' flag. This feature should be used with care as the interpreter will run with root permissions when a setuid binary owned by root is run with binfmt misc.

There are some restrictions:

- the whole register string may not exceed 255 characters
- the magic must reside in the first 128 bytes of the file, i.e. offset+size(magic) has to be less than 128
- the interpreter string may not exceed 127 characters

To use binfmt\_misc you have to mount it first. You can mount it with "mount -t binfmt\_misc none /proc/sys/fs/binfmt\_misc" command, or you can add a line "none /proc/sys/fs/binfmt\_misc binfmt\_misc defaults 0 0" to your /etc/fstab so it auto mounts on boot.

You may want to add the binary formats in one of your /etc/rc scripts during boot-up. Read the manual of your init program to figure out how to do this right.

Think about the order of adding entries! Later added entries are matched first!

A few examples (assumed you are in /proc/sys/fs/binfmt misc):

- enable support for em86 (like binfmt\_em86, for Alpha AXP only): echo

- enable support for packed DOS applications (pre-configured dosemu hdimages):
  echo ':DEXE:M::\x0eDEX::/usr/bin/dosexec:' > register
- enable support for Windows executables using wine: echo ':DOSWin:M::MZ::/usr/local/bin/wine:' > register

For java support see Documentation/java.txt

You can enable/disable binfmt\_misc or one binary type by echoing 0 (to disable) or 1 (to enable) to /proc/sys/fs/binfmt\_misc/status or /proc/.../the\_name. Catting the file tells you the current status of binfmt\_misc/the entry.

You can remove one entry or all entries by echoing -1 to /proc/.../the\_name or /proc/sys/fs/binfmt misc/status.

## binfmt misc.txt

## HINTS:

If you want to pass special arguments to your interpreter, you can write a wrapper script for it. See Documentation/java.txt for an example.

Your interpreter should NOT look in the PATH for the filename; the kernel passes it the full filename (or the file descriptor) to use. Using \$PATH can cause unexpected behaviour and can be a security hazard.

There is a web page about binfmt\_misc at http://www.tat.physik.uni-tuebingen.de/~rguenth/linux/binfmt\_misc.html

Richard Günther <rguenth@tat.physik.uni-tuebingen.de>