UTL_LMS

UTL LMS retrieves and formats error messages in different languages.

This chapter contains the following topics:

- Security Model
- Summary of UTL_LMS Subprograms

See Also:

Oracle Database Globalization Support Guide

UTL_LMS Security Model

This package must be created as the user SYS.

Summary of UTL_LMS Subprograms

This table lists the ${\tt UTL_LMS}$ subprograms and briefly describes them.

Table 294-1 UTL_LMS Package Subprograms

Function	Description
FORMAT_MESSAGE Function	Formats a retrieved error message
GET_MESSAGE Function	Retrieves an error message based on error number, product, facility, language, and message specified

FORMAT_MESSAGE Function

This function formats a message retrieved by the <code>GET_MESSAGE</code> function and returns the formatted message. If the function fails, then it returns a <code>NULL</code> result.

The following table shows special characters that can be used in the format string.

Special Character	Description
'%s'	Substitute the next string argument
'%d'	Substitute the next integer argument
1881	Represents the special character %

Syntax

```
UTL_LMS.FORMAT_MESSAGE (
   format IN VARCHAR2 CHARACTER SET ANY_CS,
   args IN VARCHAR2 CHARACTER SET ANY_CS DEFAULT NULL)
RETURN VARCHAR2 CHARACTER SET format%CHARSET;
```

Parameters

Table 294-2 FORMAT_MESSAGE Procedure Parameters

Parameter	Description
format	Specifies the string to format
args	Specifies the list of arguments

Examples

```
DECLARE
   s varchar2(200);
   i   pls_integer;
BEGIN
   i:= utl_lms.get_message(26052, 'rdbms', 'ora', 'french', s);
   dbms_output.put_line('before format, message is: '||s);
   dbms_output.put_line('formatted message is: '||utl_lms.format_message(s, 9, 'my_column_name');
END;
//
```

The following is an unformatted message:

```
Type %d non pris en charge pour l'expression SQL sur la colonne %s.
```

The following is the formatted message:

Type 9 non pris en charge pour l'expression SQL sur la colonne my_column_name.

GET_MESSAGE Function

This function retrieves an Oracle error message. The user can define user-specific error messages with the <code>lmsgen</code> utility.

It returns 0 when it is successful. It returns -1 when it fails.



Oracle Database Globalization Support Guide for more information about the lmsgen utility

Syntax

```
UTL_LMS.GET_MESSAGE (
errnum IN PLS_INTEGER,
product IN VARCHAR2,
facility IN VARCHAR2,
```



```
language IN VARCHAR2,
  message OUT NOCOPY VARCHAR2CHARCTER SET ANY_CS)
RETURN PLS_INTEGER;
```

Parameters

Table 294-3 GET_MESSAGE Function Parameters

Parameter	Description
errnum	Specifies the error number.
	Example: '972' (for ORA-00972)
product	Specifies the product to which the error message applies
	Example: 'rdbms'
facility	Specifies the error message prefix
	Example: 'ora'
language	Specifies the language of the message. The parameter is case-insensitive. The default is <code>NULL</code> , which causes <code>GET_MESSAGE</code> to use the value of the <code>NLS_LANGUAGE</code> session parameter.
message	Specifies the output buffer for the retrieved message

Usage Notes

If the language parameter is set to NULL, then the value of the ${\tt NLS_LANGUAGE}$ session parameter is used as the default.

Examples

```
DECLARE
   s varchar2(200);
   i pls_integer;
BEGIN
   i:=utl_lms.get_message(601, 'rdbms', 'oci', 'french', s);
   dbms_output.put_line('OCI--00601 is: '||s);
END
//
```

The following output results:

OCI--00601 is: Echec du processus de nettoyage.