DBMS_DBFS_HS

The Oracle Database File System Hierarchical Store is implemented in the <code>DBMS_DBFS_HS</code> package. This package provides users the ability to use tape or Amazon S3 Web service as a storage tier when doing Information Lifecycle Management for their database tables.

This chapter contains the following topics:

- Overview
- Security Model
- Constants
- Operational Notes
- Summary of DBMS_DBFS_HS Subprograms

See Also:

Oracle Database SecureFiles and Large Objects Developer's Guide

DBMS_DBFS_HS Overview

The DBMS_DBFS_HS package is a service provider underneath the DBMS_DBFS_CONTENT package that enables use of tape or Amazon S3 Web service as storage for data.

The data on tape or Amazon S3 Web service is part of the Oracle Database and can be accessed through all standard interfaces, but only through the database. The package allows users to use tape or Amazon S3 Web service as a storage tier when doing Information Lifecycle Management of their content.

The package initially stores all content files in level-1 cache. As the level-1 cache fills up, content files are moved to level-2 cache and then to an external storage device using bulk writes.

DBMS_DBFS_HS Security Model

The DBMS_DBFS_HS package runs with invoker's rights.

DBMS DBFS HS Constants

The DBMS DBFS HS package uses the constants shown in the tables in this topic.

Table 69-1 DBMS_DBFS_HS Constants - Used by the CREATESTORE Procedure

Constant	Туре	Value	Description
STORETYPE_TAPE	VARCHAR2(50)	'HS_TAPE'	Use tape as a storage tier
STORETYPE_AMAZON S3	VARCHAR2 (50)	'HS_S3'	Use Amazon S3 Web service as a storage tier

Table 69-2 DBMS_DBFS_HS Constants - Used by the SETSTOREPROPERTY Procedure and the GETSTOREPROPERTY Function

Constant	Туре	Value	Description
PROPNAME_BUCKET	VARCHAR2(50)	'BUCKET'	Specifies the AWS bucket to be used as a storage tier by the Hierarchical Store.
			Restrictions on bucket name are:
			1) Bucket names can only contain lowercase letters, numbers, periods (.) and dashes(-). Note that underscores (_) are invalid.
			2) Bucket names must start with a number or letter.
			3) Bucket names cannot be in an IP address style (192.168.5.4).
			4) Bucket names must be between 3 and 63 characters long.
			5) Bucket names should not end with a dash.
			6) Dashes cannot appear next to periods. For example, mybucket.com is invalid.
PROPNAME_CACHESI ZE	VARCHAR2(50)	'CACHE_SIZE'	Specifies the cumulative cache size used for the Hierarchical Store. This property is set by the CREATESTORE Procedure and can be modified by the RECONFIGCACHE Procedure. It cannot be modified by the SETSTOREPROPERTY Procedure, though its value can be queried by the GETSTOREPROPERTY Function.
PROPNAME_COMPRES SLEVEL	VARCHAR2(50)	'COMPRESSION_L EVEL'	Use to enable compression of files stored in the DBFS hierarchical store. It specifies the compression level to be used for compressing the files



Constant	Туре	Value	Description
PROPNAME_ENABLEC LEANUPONDELETE	VARCHAR2 (50)	'ENABLE_CLEANU P_ON_DELETE'	If this property is set to 'TRUE', whenever the user invokes the DELETEFILE Procedure in the DBMS_DBFS_CONTENT interface on a file residing in the DBMS_DBFS_HS store, the DBMS_DBFS_HS removes the file on the external storage that contains this user file, provided that the file has no other useful data.By default, the property is set to 'TRUE' for STORETYPE_AMAZONS3 and 'FALSE' for STORETYPE_TAPE.
PROPNAME_HTTPPROXY	VARCHAR2(50)	'HTTP_PROXY'	Specifies the DNS name of the HTTP proxy, if any, that is needed to access the Amazon S3 storage service
PROPNAME_LICENSE ID	VARCHAR2(50)	'LICENSE_ID'	Specifies the license ID associated with the library libosbws11.so.
PROPNAME_LOBCACH E_QUOTA	VARCHAR2(50)	'LOBCACHE_QUOT A'	Specifies fraction of the cache_size which is allocated for level 1 cache. The default value of this parameter is NULL which means that 0.8 (= 80%) of the cache_size is used for level 1 cache.
			This property cannot be modified by the SETSTOREPROPERTY Procedurethough its value can be queried by the GETSTOREPROPERTY Function. Its value is set by CREATESTORE Procedure and can be modified by the RECONFIGCACHE Procedure.
PROPNAME_MEDIAPO OL	VARCHAR2(50)	'MEDIA_POOL'	Specifies the media pool number to use for storing the content
PROPVAL_COMPLVL_NONE	VARCHAR2(50)	'NONE'	Indicates no compression
PROPVAL_COMPLVL_ LOW	VARCHAR2(50)	'LOW'	Use to set the compression level to LOW. This is expected to have the best performance while still providing a good compression ratio.
PROPVAL_COMPLVL_MEDIUM	VARCHAR2(50)	'MEDIUM'	Use to set the compression level to MEDIUM. This compression level is expected to provide better compression ratio than LOW but the time required for compression will be higher than compression level LOW.
PROPVAL_COMPLVL_ HIGH	VARCHAR2(50)	'HIGH'	Use to set the compression level to HIGH. This compression level is expected to provide the best compression ratio but compression time will in general be highest among the 3 compression levels.



Table 69-2 (Cont.) DBMS_DBFS_HS Constants - Used by the SETSTOREPROPERTY Procedure and the GETSTOREPROPERTY Function

Constant	Туре	Value	Description
PROPNAME_OPTTARB ALLSIZE	VARCHAR2(50)	'OPTIMAL_TARBA LL_SIZE'	Specifies optimal_tarball_size as the maximum possible size of an archive file.
			Multiple content files are bundled together into one archive file and then the archive file is transferred to tape or Amazon S3. This is because creating one file on tape or Amazon S3 for every content file in the store is a prohibitively expensive operation.
			This property cannot be modified by the SETSTOREPROPERTY Procedurethough its value can be queried by the GETSTOREPROPERTY Function. Its value is set by CREATESTORE Procedure and can be modified by the RECONFIGCACHE Procedure.
PROPNAME_READCHU NKSIZE	VARCHAR2(50)	'READ_CHUNK_SI ZE'	Specifies the size used by the SBT protocol to transfer data from tape or S3. This chunk is allocated in memory per transaction for retrieval of content files from an archive store, so the value of this property should be conservative. The default size of 1MB is typically good for most users.
PROPNAME_S3HOST	VARCHAR2(50)	'S3_HOST'	Specifies the HOST name of the Amazon S3 storage service. It must be s3.amazonaws.com.
PROPNAME_SBT_LIB RARY	VARCHAR2(50)	'SBT_LIBRARY'	Specifies the path of the shared library used by RMAN to communicate with Amazon S3. It is named libosbws11.so and is available in rdbms/lib directory.
PROPNAME_STREAMA BLE	VARCHAR2(50)	'STREAMABLE'	Indicates whether buffer-based PUT or GET should be done on this store. Valid values for are TRUE and FALSE. The default value of this property is TRUE.



Table 69-2 (Cont.) DBMS_DBFS_HS Constants - Used by the SETSTOREPROPERTY Procedure and the GETSTOREPROPERTY Function

Compatent	T	Valera	Description
Constant	Type	Value	Description The contract of this assessment of a cold by a f
PROPNAME_WALLET	VARCHAR2(50)	'WALLET'	The value of this property should be of the form:
			LOCATION=file: filename
			CREDENTIAL_ALIAS=access/ secret alias
			PROXY AUTH ALIAS=proxyusername/
			password alias
			Defines the Oracle Wallet which contains the credentials of the Amazon S3 account associated with the store under consideration.
			LOCATION: The directory path that contains the Oracle wallet. The format is file: directory-path
			The format of wallet_path in Windows is, for example:
			<pre>file:c:\WINNT\Profiles\username\ WALLETS</pre>
			In UNIX or Linux it is, for example:
			file:/home/username/wallets
			When the package is executed in the Oracle database server, the wallet is accessed from the database server.
			PASSWORD: Defines the wallet password. If auto-login is enabled in wallet, this parameter does not have to be specified. By default, the mkstore utility enables auto-login.
			CREDENTIAL_ALIAS: Defines the credential alias for ACCESS_KEY and SECRET_KEY
PROPNAME_WRITECH UNKSIZ	VARCHAR2(50)	'WRITE_CHUNK_S IZE'	Specifies the size used by the SBT protocol to transfer data to tape or S3.
			This chunk is allocated in memory per transaction for PUT of Content Files to an archive store so the value should be conservative.
			The default size of 1MB is typically good for most users.

Table 69-3 DBMS_DBFS_HS Constants - Used by the REGISTERSTORECOMMAND Function

Constant	Туре	Value	Description
BEFORE_PUT	NUMBER	'1'	Specified operation must be performed before writing a SECUREFILE to the remote store

Table 69-3 (Cont.) DBMS_DBFS_HS Constants - Used by the REGISTERSTORECOMMAND Function

Constant	Туре	Value	Description
BEFORE_GET	NUMBER	'2'	Specified operation must be performed before a retrieval operation such as reading a SECUREFILE from the remote device

Table 69-4 DBMS_DBFS_HS Constants - Failure/Success/Error

Constant	Туре	Value	Description
FAIL	NUMBER	'0'	Procedure or function did not execute successfully
SUCCESS	NUMBER	'1'	Procedure or function completed successfully
ERROR	NUMBER	'2'	Procedure or function returned an error

DBMS_DBFS_HS Operational Notes

When the <code>DBMS_DBFS_HS</code> package is executed in the Oracle database server, the wallet is accessed from the database server.

Summary of DBMS_DBFS_HS Subprograms

This table lists and describes the subprograms in the <code>DBMS_DBFS_HS</code> package.

Table 69-5 DBMS_DBFS_HS Package Subprograms

Subprogram	Description
CLEANUPUNUSEDBACKUPFILE S Procedure	Removes files created on the external storage device that hold no currently used data
CREATEBUCKET Procedure	Creates an AWS bucket, associated with a store of type STORETYPE_AMAZONS3 into which the Hierarchical Store can then move data
CREATESTORE Procedure	Creates a new hierarchical store
DEREGSTORECOMMAND Function	Removes a command that had been previously associated with a store through the RECONFIGCACHE Procedure
DROPSTORE Procedure	Deletes a previously created hierarchical store
FLUSHCACHE Procedure	Flushes (writes out) dirty contents from the level-1 cache.
GETSTOREPROPERTY Function	Retrieves the values of a property of a store
RECONFIGCACHE Procedure	Reconfigures the parameters of the database cache used by the store
REGISTERSTORECOMMAND Procedure	Registers commands for a store with the Hierarchical Store to be sent to the Media Manager for the external storage device associated with the store

Table 69-5 (Cont.) DBMS_DBFS_HS Package Subprograms

Subprogram	Description
SENDCOMMAND Procedures	Sends a command to be executed on the external storage device's Media Manager
SETSTOREPROPERTY Procedure	Stores properties of a store in the database
STOREPUSH Procedure	Pushes locally staged data to the remote storage

CLEANUPUNUSEDBACKUPFILES Procedure

This procedure removes files created on the external storage device that hold no currently used data in them.

Syntax

Parameters

Table 69-6 CLEANUPUNUSEDBACKUPFILES Procedure Parameters

Parameter	Description
store_name	Name of store

Usage Notes

- The action of removing files from external storage device can not be rolled back.
- This method can be executed periodically to clear space on the external storage device.
 Asynchronously deleting content from the external storage device is useful because it has minimal impact on the OLTP performance. The periodic scheduling can be accomplished using the DBMS_SCHEDULER package.

CREATEBUCKET Procedure

This procedure creates an AWS bucket, associated with a store of type STORETYPE_AMAZONS3 into which the Hierarchical Store can then move data.

Syntax

```
DBMS_DBFS_HS.CREATEBUCKET (
    store_name IN VARCHAR2);
```

Parameters

Table 69-7 CREATEBUCKET Procedure Parameters

Parameter	Description
store_name	Name of store



Usage Notes

- The PROPNAME BUCKET property of the store should be set before this subprogram is called.
- Once this procedure has successfully created a bucket in Amazon S3, the bucket can only be deleted using out-of-band methods, such as logging-in to S3 and deleting data (directories, files, and other items) for the bucket.

CREATESTORE Procedure

This procedure creates a new hierarchical store <code>store_name</code> of type <code>STORE_TYPE</code> (<code>STORETYPE_TAPE</code> or <code>STORETYPE_AMAZONS3</code>) in schema <code>schema_name</code> (defaulting to the current schema) under the ownership of the invoking session user.

Syntax

```
DBMS_DBFS_HS.CREATESTORE (

store_name IN VARCHAR2,
store_type IN VARCHAR2,
tbl_name IN VARCHAR2,
tbs_name IN VARCHAR2,
cache_size IN NUMBER,
lob_cache_quota IN NUMBER DEFAULT NULL,
optimal_tarball_size IN NUMBER DEFAULT NULL,
schema_name IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 69-8 CREATESTORE Procedure Parameters

Parameter	Description
store_name	Name of store
store_type	STORETYPE_TAPE or STORETYPE_AMAZONS3
tbl_name	Table for store entries
tbs_name	Tablespace for the store
cache_size	Amount of space used by the store to cache content in given tablespace
lob_cache_quota	Fraction of the cache_size which is allocated for level 1 cache. The default value of this parameter is \texttt{NULL} which means that 0.8 (= 80%) of the <code>cache_size</code> is used for level 1 cache.
optimal_tarball_size	Maximum possible size of the archive file.
	Multiple content files are bundled together into one archive file, and then the archive file is transferred to tape or Amazon S3. This is because creating one file on tape or Amazon S3 for every content file in the store is a prohibitively expensive operation.
	The value of is set by default to 10GB for tape and to 100MB for Amazon S3.
schema_name	Schema for the store

Usage Notes

CREATESTORE () sets certain properties of the store to default values. The user can use the methods SETSTOREPROPERTY () and RECONFIGCACHE () to appropriately change the property values and to set other properties of the store.

- Store names must be unique for an owner. The same store names can be used for different stores owned by different owners.
- Once a table space has been specified to store the store's content in a database, it cannot be changed later.
- This subprogram will execute like a DDL statement, performing an automatic COMMIT
 before and after execution.
- Stores using DBMS_DBFS_HS must not use singleton mount. This means that the singleton
 parameter should be FALSE and the store_mount parameter should have a non-NULL value
 in a call to the DBMS_DBFS_CONTENT.MOUNTSTORE procedure.

DEREGSTORECOMMAND Function

This procedure removes a command that had been previously associated with a store through the REGISTERSTORECOMMAND Procedure.

Syntax

Parameters

Table 69-9 DEREGSTORECOMMAND Procedure Parameters

Parameter	Description
store_name	Name of store
message	Message to be deregistered

Usage Notes

If this subprogram successfully executes, its actions cannot be rolled back by the user. If the user wants to restore the previous state, the user must call the REGISTERSTORECOMMAND Procedure.

Related Topics

REGISTERSTORECOMMAND Procedure

This procedure registers commands for a store with the Hierarchical Store. These commands are sent to the Media Manager for the external storage device associated with the store.

DROPSTORE Procedure

This procedure deletes a previously created hierarchical store specified by name and owned by the invoking session user.

Syntax

```
DBMS_DBFS_HS.DROPSTORE (
   store_name IN VARCHAR2,
   opt_flags IN INTEGER DEFAULT 0);
```



Parameters

Table 69-10 DROPSTORE Procedure Parameters

Parameter	Description
store_name	Name of store owned by the invoking session user
opt_flags	User can specify optional flags. If <code>DISABLE_CLEANUPBACKUPFILES</code> is specified as one of the optional flags, the call to the <code>CLEANUPUNUSEDBACKUPFILES</code> Procedure is not issued. By default, when this flag is not set, the procedure implicitly cleans-up all unused backup files.

Usage Notes

- The procedure executes like a DDL in that it auto-commits before and after its execution.
- If CLEANUPBACKUPFILES is disabled during the procedure, the user must resort to out-ofband techniques to cleanup unused backup files. No further invocations of CLEANUPBACKFILES for a dropped store are possible through hierarchical store.
- This subprogram will un-register the store from <code>DBMS_DBFS_CONTENT</code> package. All files in the given store are deleted from the store (Tape or Amazon S3 Web service). The database table holding the store's entries in the database, is also dropped by this subprogram.

FLUSHCACHE Procedure

This procedure flushes out dirty contents from level-1 cache, which can be locked, to level-2 cache, thereby freeing-up space in level 1 cache.

Syntax

```
DBMS_DBFS_HS.FLUSHCACHE (
   store name IN VARCHAR2);
```

Parameters

Table 69-11 FLUSHCACHE Procedure Parameters

Parameter	Description
store_name	Name of store

GETSTOREPROPERTY Function

This function retrieves the values of a property.

Syntax

```
DBMS_DBFS_HS.GETSTOREPROPERTY (
store_name IN VARCHAR2,
property_name IN VARCHAR2,
noexcp IN BOOLEAN DEFAULT FALSE) RETURN VARCHAR2;
```



Parameters

Table 69-12 GETSTOREPROPERTY Function Parameters

Parameter	Description
store_name	Name of store
property_name	Name of property
noexcp	If set to FALSE, raises an exception if the property does not exist in the database. If noexcp is set to TRUE, returns NULL if the property does not exist.

Return Values

The values of a property.

Usage Notes

The specified store must already have been created.

RECONFIGCACHE Procedure

This procedure reconfigures the parameters of the database cache being used by the store.

Syntax

```
DBMS_DBFS_HS.RECONFIGCACHE (
store_name IN VARCHAR2,
cache_size IN NUMBER DEFAULT NULL,
lobcache_quota IN NUMBER DEFAULT NULL,
optimal_tarball_size IN NUMBER DEFAULT NULL);
```

Parameters

Table 69-13 RECONFIGCACHE Procedure Parameters

Parameter	Description
store_name	Name of store
cache_size	Cumulative cache size used for the Hierarchical Store
lobcache_quota	Fraction of the cache size that are assigned to level 1 cache
optimal_tarball_size	Maximum possible size of an archive file. Since creating one file for every content file in the store is a prohibitively expensive operation, multiple content files are bundled together into one archive file for transfer to tape or Amazon S3.

Usage Notes

- The specified store must already have been created before reconfiguration.
- The Hierarchical Store uses a level 1 cache and a level 2 cache. The level 1 cache subsumes most of the working set and the level 2 cache is used to perform bulk writes to the backend device.

• If any of the last 3 parameters is NULL, its value specified during store creation is used. If the parameter was NULL when the call to the CREATESTORE Procedure was issued, the DBMS DBFS HS package assigns a default value.

The DBMS_DBFS_HS package optimistically tries to allocate more than 1 tarball's worth of size for level 2 cache to facilitate concurrency, though a minimum of 1 tarball size is necessary for level 2 cache.

The values for cumulative cache size and LOB cache quota decide allocation of space for the two caches. If values are not provided, a user might see an <code>INSUFFICIENT_CACHE</code> exception. In that case, it is better to revise the cache parameters in order to have a working store.

• If this subprogram successfully executes, its actions cannot be rolled back by the user. In that case, the user should call RECONFIGCACHE again with new or modified parameters.

REGISTERSTORECOMMAND Procedure

This procedure registers commands for a store with the Hierarchical Store. These commands are sent to the Media Manager for the external storage device associated with the store.

Syntax

```
DBMS_DBFS_HS.REGISTERSTORECOMMAND (
store_name IN VARCHAR2,
message IN VARCHAR2,
flags IN NUMBER);
```

Parameters

Table 69-14 REGISTERSTORECOMMAND Procedure Parameters

Parameter	Description
store_name	Name of store
message	Message to be sent to the Media Manager of the external store
flags	Valid values:
	 BEFORE_PUT CONSTANT NUMBER := 1;
	 BEFORE_GET CONSTANT NUMBER := 2;

Usage Notes

- These commands are sent before the next read or write of content. When the Hierarchical Store wants to push (or get) data to (or from) the storage device, it begins a session (to communicate with the device). After beginning the session, it sends all registered commands for the to the relevant device before writing (or getting) any data.
- If this method successfully executes, its actions cannot be rolled back by the user. To restore the previous state the user must call the DEREGSTORECOMMAND Function.

SENDCOMMAND Procedure

This procedure sends a command to be executed on the external storage device's Media Manager.

Syntax

Parameters

Table 69-15 SENDCOMMAND Procedure Parameters

Parameter	Description
store_name	Name of store
message	Message string to be executed

SETSTOREPROPERTY Procedure

This procedure stores properties of a store in the database as name-value pairs.

Syntax

```
DBMS_DBFS_HS.SETSTOREPROPERTY (
store_name IN VARCHAR2,
property_name IN VARCHAR2,
property_value IN VARCHAR2);
```

Parameters

Table 69-16 SETSTOREPROPERTY Procedure Parameters

Parameter	Description
store_name	Name of store
property_name	For a store using Tape device, there are three properties whose values must be set by the user, and four properties that have default values. Stores of type STORETYPE_AMAZONS3 have properties with default values. The various options for both types of stores are detailed under property_value.



Table 69-16 (Cont.) SETSTOREPROPERTY Procedure Parameters

Parameter

Description

property value

Stores using a Tape Device

The values for the following properties must be set by the user:

- PROPNAME_SBTLIBRARY This should point to the shared library used by RMAN to communicate with the external tape device. It is usually named libobk.so.
- PROPNAME MEDIAPOOL Media pool number for storing content
- PROPNAME_CACHE_SIZE Amount of space, in bytes, used for the cache of this store

The following properties, which have default values assigned to them when a store is created, benefit from tuning:

- PROPNAME_READCHUNKSIZE and PROPNAME_WRITECHUNKSIZE These are the sizes used by the SBT protocol to transfer data to
 and from the tapes. These chunks are allocated in memory per
 transaction, so the values should be conservative. The default size
 is 1MB.
- PROPNAME_STREAMABLE Indicates whether DBFS_LINKs can
 perform read operations (for example SELECT or DBMS_LOB.READ)
 directly from the store, or if the data must be copied back into the
 database before it can be read
- PROPNAME_ENABLECLEANUPONDELETE Indicates if DBMS_DBFS_HS should delete unused files on the external storage. Valid values for this property are 'FALSE' for STORETYPE TAPE.
- PROPNAME_COMPRESSLEVEL Describes how files written to Tape should be compressed. It can be set to PROPVAL_COMPLVL_NONE, PROPVAL_COMPLVL_LOW, PROPVAL_COMPLVL_MEDIUM or PROPVAL_COMPLVL_HIGH. By default it is set to PROPVAL_COMPLVL_NONE.



Table 69-16 (Cont.) SETSTOREPROPERTY Procedure Parameters

Parameter

Description

(cont) property value

Stores of type STORETYPE AMAZONS3

It is mandatory that the following properties have assigned values, and default values are provided:

- PROPNAME_SBTLIBRARY Specifies the path of the shared library used by RMAN to communicate with Amazon S3. It is named libosbws11.so and is available in rdbms/lib directory.
- PROPNAME_S3HOST Defines the HOST name of the Amazon S3 storage service. It must be s3.amazonaws.com.
- PROPNAME_BUCKET Defines the AWS bucket used as a storage tier by the Hierarchical Store. Restrictions on bucket names are:
 - -- Bucket names can only contain lowercase letters, numbers, periods (.) and dashes (-). Use of an underscore () is invalid.
 - -- Bucket names must start with a number or letter
 - -- Bucket names cannot be in an IP address style ("192.168.5.4")
 - -- Bucket names must be between 3 and 63 characters in length
 - -- Bucket names should not end with a dash
 - -- Dashes cannot appear next to periods. For example, "my-.bucket.com" is invalid.
- PROPNAME_LICENSEID Specifies the license ID associated with the library libosbws11.so.
- PROPNAME_WALLET Has the form: 'LOCATION=file:<filename>
 CREDENTIAL_ALIAS=<access/secret_alias>
 PROXY AUTH ALIAS=<proxyusername/password alias>'
 - -- LOCATION Directory path that contains the Oracle wallet. The format is file: directory-path. See Examples for variations in format.
 - -- PASSWORD Defines the wallet password. If auto-login is enabled in the wallet (this can be changed using the user's own utility), and does not have to be specified. By default, the mkstore utility enables auto-login.
 - -- CREDENTIAL ALIAS Defines the credential alias for ACCESS KEY and SECRET KEY
 - -- PROXY_AUTH_ALIAS Defines authentication credentials for the proxy server, if applicable.



Table 69-16 (Cont.) SETSTOREPROPERTY Procedure Parameters

Parameter	Description
(property_value (contd.)	 The following properties are optional: PROPNAME_HTTPPROXY - Defines the DNS name of the HTTP proxy, if any, that is needed to access the Amazon S3 storage service. PROPNAME_STREAMABLE - Indicates whether buffer-based PUT or GET operation should be done on this store. Valid values for this property are TRUE (default) and FALSE. PROPNAME_ENABLECLEANUPONDELETE - Indicates if DBMS_DBFS_HS should delete unused files on the external storage device. Default values for this property are FALSE for STORETYPE_TAPE and TRUE for STORETYPE_AMAZONS3. PROPNAME_COMPRESSLEVEL - Describes how files written to tape should be compressed. It can be set to PROPVAL_COMPLVL_NONE, PROPVAL_COMPLVL_HIGH. By default it is set to PROPVAL_COMPLVL NONE.

Usage Notes

- The specified store must already have been created.
- If this subprogram successfully executes, its actions cannot be rolled back by the user.
- The same property can be set multiple times to the same or different values using this subprogram
- Regarding PROPNAME_ENABLECLEANUPONDELETE behavior, a job is created for each store by the DBMS_DBFS_HS to remove the unused files from the external storage. By default, the job is enabled for STORETYPE_AMAZONS3 and is disabled for STORETYPE_TAPE. If the ENABLECLEANUPONDELETE property is set to TRUE, the job is enabled; if the property is set to FALSE, the job is disabled. If enabled, the job runs at an interval of one hour by default. The DBMS_SCHEDULER package can be used to modify the schedule. The name of the job can be obtained by querying USER DBFS_HS_FIXED_PROPERTIES for prop_name = 'DELJOB_NAME'.

Examples

Format

The format of wallet path in Windows is, for example:

file:c:\WINNT\Profiles\<username>\WALLETS

The format of wallet path in UNIX or Linux is, for example:

file:/home/username/wallets



STOREPUSH Procedure

This procedure pushes locally staged data to the remote storage.

Syntax

```
DBMS_DBFS_HS.STOREPUSH (
store_name IN VARCHAR2,
path IN VARCHAR2 DEFAULT NULL);
```

Parameters

Table 69-17 STOREPUSH Procedure Parameters

Parameter	Description
store_name	Name of store whose content the client writes from local cache to the external store
path	A non-mount qualified (without mount point) path within the store. By default, its value is \mathtt{NULL} which corresponds to the root path of the store.

Usage Notes

- The Hierarchical Store caches the content files locally in database tables. When enough
 content is amassed in the cache to make it efficient to write to the external storage device
 (or the cache is completely filled), the Hierarchical Store creates a tarball out of the local
 content and writes these tarballs as files on the external device. The size of the tarball
 created by the Hierarchical Store is controlled by the store property
 PROPNAME OPTTARBALLSIZE.
- When the amount of free space in the cache is such that the caching of a content file will push the space used above <code>cache_size</code>, the Hierarchical Store will internally call <code>STOREPUSH</code>. The <code>STOREPUSH Procedure</code> creates tarball(s) out of the existing dirty or modified content files in the cache and writes them out to the external device. A <code>STOREPUSH</code> call is not guaranteed to write all the dirty content from local cache to the external storage, since some files may be locked by other sessions.
- STOREPUSH has a built-in ability feature allowing it to automatically resume operation. If a
 STOREPUSH call is interrupted (say by a network outage) after it has transferred some
 tarballs to the external device, it can be restarted after the outage and will then resume
 transferring data from the point it was interrupted. In other words, work done before the
 outage is not lost. STOREPUSH can safely be restarted and the effect is such as if the outage
 never occurred.
- If this method successfully executes, its actions cannot be rolled back by the user.
- By default, when path is NULL, all files in the store are candidates for STOREPUSH. If path has a valid input value, all files which are under the namespace of given path are written from the local cache to the external store. If a given path is an existing file, it is pushed out again to the remote store.

