DBMS_ERRLOG

The DBMS_ERRLOG package provides a procedure that enables you to create an error logging table so that DML operations can continue after encountering errors rather than abort and roll back. This enables you to save time and system resources.

This chapter contains the following topics:

- Security Model
- Summary of DBMS_ERRLOG Subprograms

See Also:

Oracle Database Data Warehousing Guide for more information regarding how to use DBMS_ERRLOG and Oracle Database SQL Language Reference for error logging clause syntax

DBMS_ERRLOG Security Model

Security on this package can be controlled by granting EXECUTE on this package to selected users or roles. The EXECUTE privilege is granted publicly. However, to create an error logging table, you need SELECT access on the base table or view, the CREATE TABLE privilege, as well as tablespace quota for the target tablespace.

Summary of DBMS_ERRLOG Subprograms

The DBMS_ERRORLOG package includes the CREATE_ERROR_LOG procedure subprogram.

Table 85-1 DBMS_ERRLOG Package Subprograms

Subprogram	Description
CREATE_ERROR_LOG Procedure	Creates the error logging table used in DML error logging

CREATE_ERROR_LOG Procedure

This procedure creates the error logging table needed to use the DML error logging capability.

LONG, CLOB, BLOB, BFILE, and ADT datatypes are not supported in the columns.

Syntax

```
err_log_table_owner
err_log_table_space
skip_unsupported
IN VARCHAR2 := NULL,
IN VARCHAR2 := NULL,
IN BOOLEAN := FALSE);
```

Parameters

Table 85-2 CREATE_ERROR_LOG Procedure Parameters

Parameter	Description
dml_table_name	The name of the DML table or duality view to base the error logging table on. The name can be fully qualified (for example, emp, scott.emp, "EMP", "SCOTT"."EMP"). If a name component is enclosed in double quotes, it will not be upper cased. Duality views are supported as values for this parameter.
err_log_table_name	The name of the error logging table you will create.
	The default is the first 25 characters in the name of the DML table prefixed with <code>'ERR\$_'</code> . Examples are the following:
	<pre>dml_table_name: 'EMP', err_log_table_name: 'ERR\$_EMP'</pre>
	<pre>dml_table_name: '"Emp2"', err_log_table_name: 'ERR\$_Emp2'</pre>
err_log_table_owner	The name of the owner of the error logging table. You can specify the owner in dml_table_name. Otherwise, the schema of the current connected user is used.
err_log_table_space	The tablespace the error logging table will be created in. If not specified, the default tablespace for the user owning the DML error logging table will be used.
skip_unsupported	When set to TRUE, column types that are not supported by error logging will be skipped over and not added to the error logging table. When set to FALSE, an unsupported column type will cause the procedure to terminate.
	The default is FALSE.

Examples

First, create an error log table for the channels table in the SH schema, using the default name generation.

Then, see all columns of the table channels:

SQL> DESC channels		
Name	Null?	Type
CHANNEL_ID	NOT NULL	CHAR(1)
CHANNEL_DESC	NOT NULL	VARCHAR2(20)
CHANNEL CLASS		VARCHAR2 (20)

Finally, see all columns of the generated error log table. Note the mandatory control columns that are created by the package:

SQL> DESC ERR\$_CHANNELS		
Name	Null?	Type
ORA_ERR_NUMBER\$		NUMBER
ORA_ERR_MESG\$		VARCHAR2 (2000)
ORA_ERR_ROWID\$		ROWID
ORA_ERR_OPTYP\$		VARCHAR2(2)
ORA_ERR_TAG\$		VARCHAR2 (2000)



CHANNEL_ID	VARCHAR2 (4000)
CHANNEL_DESC	VARCHAR2 (4000)
CHANNEL CLASS	VARCHAR2 (4000)

See Oracle Database Administrator's Guide for more information regarding control columns.

Example Using a Duality View as the DML Table

The following code creates an error log table for a duality view named "COURSE." This example shows the procedure's flexibility in handling duality views in addition to tables.

```
EXEC DBMS_ERRLOG.CREATE_ERROR_LOG(dml_table_name => 'COURSE');
```

