Oracle® Database PL/SQL Packages and Types Reference





Oracle Database PL/SQL Packages and Types Reference, 23ai

F46980-29

Copyright © 1996, 2025, Oracle and/or its affiliates.

Primary Author: Gunjan Jain

Contributing Authors: Louise Morin, Denis Raphaely, Lance Ashdown, Drue Baker, Donna Carver, Maitreyee Chaliha, Beethoven Cheng, Rhonda Day, Steve Fogel, Bryn Llewellyn, Paul Lane, David McDermid, Tony Morales, Anne Murphy, Chuck Murray, Sue Pelski, Kathy Rich, Antonio Romero, Vivian Schupmann, Cathy Shea, Margaret Taft, Kathy Taylor, Randy Urbano, Pat Huey, Drew Adams, Sarika Surumpudi, Rodney Ward, Rajesh Bhatiya, Tanmay Choudhury, Roopesh Ashok Kumar, Atif Chaudhry, Subha Vikram

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface	
Audience	С
Documentation Accessibility	С
Related Documents	С
Conventions	cl
Changes in This Release for Oracle Database PL/SQL Packages and Types Reference	d
Changes in this Release	clii
Introduction to Oracle Supplied PL/SQL Packages & Types	
Package Overview	1-1
Package Components	1-2
Using Oracle Supplied Packages	1-2
Creating New Packages	1-2
Separating the Specification and Body	1-3
Referencing Package Contents	1-5
Summary of Oracle Supplied PL/SQL Packages and Types	1-5
Oracle Application Express Packages APEX_APPLICATION Through APEX_ZIP	า
CTX_ADM	
CTX_ANL	
GET_COMPRESSION_RATIO Procedure	4-1



CTX_DDL	
CTX_CLS	
CTX_DOC	
CTX_ENTITY	
CTX_OUTPUT	
DBMS_SAGA_ADM	
DBMS_SAGA_ADM Overview	10-2
DBMS_SAGA_ADM Security Model	10-3
Summary of DBMS_SAGA_ADM Subprograms	10-1
ADD_BROKER Procedure	10-2
DROP_BROKER Procedure	10-2
ADD_COORDINATOR Procedure	10-3
DROP_COORDINATOR Procedure	10-4
ADD_PARTICIPANT Procedure	10-4
DROP_PARTICIPANT Procedure REGISTER_SAGA_CALLBACK Procedure	10-6 10-8
CTX_QUERY	
CTX_REPORT	
CTX_THES	
CTX_ULEXER	



15 DBMS_ACTIVITY

	Using DBMS_ACTIVITY	15-1
	Summary of DBMS_ACTIVITY Subprograms	15-2
	CONFIGURE Procedure	15-2
	CREATE_SNAPSHOT Procedure	15-3
	DELETE_SNAPSHOTS Procedure	15-4
	DELETE_SNAPSHOTS Procedure	15-5
16	DBMS_ADDM	
	DBMS_ADDM Security Model	16-1
	Summary of DBMS_ADDM Subprograms	16-1
	ANALYZE_DB Procedure	16-3
	ANALYZE_INST Procedure	16-4
	ANALYZE_PARTIAL Procedure	16-5
	COMPARE_CAPTURE_REPLAY_REPORT Function	16-7
	COMPARE_DATABASES Function	16-8
	COMPARE_INSTANCES Function	16-9
	COMPARE_REPLAY_REPLAY_REPORT Function	16-10
	DELETE Procedure	16-11
	DELETE_FINDING_DIRECTIVE Procedure	16-12
	DELETE_PARAMETER_DIRECTIVE Procedure	16-12
	DELETE_SEGMENT_DIRECTIVE Procedure	16-13
	DELETE_SQL_DIRECTIVE Procedure	16-13
	FAILED_AUTO_TASKS_REPORT Function	16-14
	GET_ASH_QUERY Function	16-14
	GET_REPORT Function	16-15
	INSERT_FINDING_DIRECTIVE Procedure	16-15
	INSERT_PARAMETER_DIRECTIVE Procedure	16-16
	INSERT_SEGMENT_DIRECTIVE Procedure	16-17
	INSERT_SQL_DIRECTIVE Procedure	16-18
	REAL_TIME_ADDM_REPORT Function	16-19
	REEXECUTE_FAILED_AUTO_TASKS Procedure	16-20
17	DBMS_ADVANCED_REWRITE	
	DBMS_ADVANCED_REWRITE Security Model	17-1
	Summary of DBMS_ADVANCED_REWRITE Subprograms	17-1
	ALTER_REWRITE_EQUIVALENCE Procedure	17-2
	BUILD_SAFE_REWRITE_EQUIVALENCE Procedure	17-3
	DECLARE_REWRITE_EQUIVALENCE Procedures	17-3



	DROP_REWRITE_EQUIVALENCE Procedure	17-5
	VALIDATE_REWRITE_EQUIVALENCE Procedure	17-6
18	DBMS_ADVISOR	
	DBMS_ADVISOR Deprecated Subprograms	18-1
	DBMS_ADVISOR Security Model	18-2
	Summary of DBMS_ADVISOR Subprograms	18-2
	ADD_SQLWKLD_REF Procedure	18-5
	ADD_SQLWKLD_STATEMENT Procedure	18-6
	ADD_STS_REF Procedure	18-8
	CANCEL_TASK Procedure	18-9
	COPY_SQLWKLD_TO_STS Procedure	18-10
	CREATE_FILE Procedure	18-11
	CREATE_OBJECT Procedure	18-12
	CREATE_SQLWKLD Procedure	18-14
	CREATE_TASK Procedures	18-15
	DELETE_SQLWKLD Procedure	18-17
	DELETE_SQLWKLD_REF Procedure	18-18
	DELETE_SQLWKLD_STATEMENT Procedure	18-19
	DELETE_STS_REF Procedure	18-20
	DELETE_TASK Procedure	18-21
	EXECUTE_TASK Procedure	18-21
	GET_REC_ATTRIBUTES Procedure	18-23
	GET_TASK_REPORT Function	18-24
	GET_TASK_SCRIPT Function	18-25
	IMPLEMENT_TASK Procedure	18-26
	IMPORT_SQLWKLD_SCHEMA Procedure	18-27
	IMPORT_SQLWKLD_SQLCACHE Procedure	18-28
	IMPORT_SQLWKLD_STS Procedure	18-30
	IMPORT_SQLWKLD_SUMADV Procedure	18-31
	IMPORT_SQLWKLD_USER Procedure	18-33
	INTERRUPT_TASK Procedure	18-34
	MARK_RECOMMENDATION Procedure	18-35
	QUICK_TUNE Procedure	18-36
	RESET_SQLWKLD Procedure	18-38
	RESET_TASK Procedure	18-39
	SET_DEFAULT_SQLWKLD_PARAMETER Procedure	18-39
	SET_DEFAULT_TASK_PARAMETER Procedure	18-40
	SET_SQLWKLD_PARAMETER Procedure	18-41
	SET_TASK_PARAMETER Procedure	18-43
	TUNE_MVIEW Procedure	18-57



	OPDATE_OBJECT Procedure	18-59
	UPDATE_REC_ATTRIBUTES Procedure	18-61
	UPDATE_SQLWKLD_ATTRIBUTES Procedure	18-62
	UPDATE_SQLWKLD_STATEMENT Procedure	18-63
	UPDATE_TASK_ATTRIBUTES Procedure	18-65
19	DBMS_AUTOIM	
	Using DBMS_AUTOIM	19-1
	Summary of DBMS_AUTOIM Subprograms	19-1
	SET_PARAMETER Procedure	19-1
	ACTIVITY_REPORT Function	19-2
20	DBMS_ALERT	
	DBMS_ALERT Overview	20-1
	DBMS_ALERT Security Model	20-1
	DBMS_ALERT Constants	20-1
	DBMS_ALERT Restrictions	20-2
	DBMS_ALERT Exceptions	20-2
	DBMS_ALERT Operational Notes	20-2
	DBMS_ALERT Examples	20-3
	Summary of DBMS_ALERT Subprograms	20-4
	REGISTER Procedure	20-4
	REMOVE Procedure	20-5
	REMOVEALL Procedure	20-5
	SET_DEFAULTS Procedure	20-5
	SIGNAL Procedure	20-6
	WAITANY Procedure	20-6
	WAITONE Procedure	20-7
21	DBMS_APP_CONT	
	DBMS_APP_CONT Overview	21-1
	DBMS_APP_CONT Security Model	21-2
	Summary of DBMS_APP_CONT Subprograms	21-2
	APPLY_REPLAY_RULE Procedure	21-2
	GET_LTXID_OUTCOME Procedure	21-3
	GET_REPLAY_RULES Function	21-4
	RESET_REPLAY_RULES Procedure	21-5



22 DBMS_APP_CONT_ADMIN

	DBMS_APP_CONT_ADMIN Security Model	22-1
	Summary of DBMS_APP_CONT_ADMIN Subprograms	22-1
	ACCHK_CLEAR_FILTER Procedure	22-2
	ACCHK_PURGE Procedure	22-3
	ACCHK_SET Procedure	22-4
	ACCHK_SET_FILTER Procedure	22-6
	ACCHK_SHOW_FILTERS Procedure	22-7
	ADD_SQL_CONNECTION_TEST Procedure	22-7
	CHECK_REPLAY_RULES Procedure	22-8
	CREATE_CHILD_SERVICE Procedure	22-9
	DELETE_CHILD_SERVICE Procedure	22-9
	DELETE_SQL_CONNECTION_TEST Procedure	22-10
	DISABLE_CONNECTION_TEST Procedure	22-10
	DISABLE_FAILOVER Procedure	22-11
	DISABLE_SMART_CONNECTION Procedure	22-12
	ENABLE_AC Procedure	22-12
	ENABLE_CONNECTION_TEST Procedure	22-13
	ENABLE_RESET_STATE Procedure	22-14
	ENABLE_SMART_CONNECTION Procedure	22-15
	ENABLE_TAC Procedure	22-15
	ENABLE_TAF Procedure	22-16
	ENABLE_TG Procedure	22-17
	MODIFY_SERVICE Procedure	22-18
	RESET_REPLAY_RULES Procedure	22-21
	SET_DRAINING Procedure	22-21
	SET_LOAD_BALANCING Procedure	22-22
	SET_REPLAY_RULES Procedure	22-23
23	DBMS_APP_CONT_REPORT	
	DBMS_APP_CONT_REPORT Security Model	23-1
	Summary of DBMS_APP_CONT_REPORT Subprograms	23-1
	ACCHK_REPORT Procedure	23-1
24	DBMS_APPLICATION_INFO	
	DBMS_APPLICATION_INFO Overview	24-1
	DBMS_APPLICATION_INFO Security Model	24-1
	DBMS_APPLICATION_INFO Operational Notes	24-1
	Summary of DBMS_APPLICATION_INFO Subprograms	24-2



	READ_CLIENT_INFO Procedure	24-2
	READ_MODULE Procedure	24-2
	SET_ACTION Procedure	24-3
	SET_CLIENT_INFO Procedure	24-4
	SET_MODULE Procedure	24-5
	SET_SESSION_LONGOPS Procedure	24-5
25	DBMS_APPLY_ADM	
	DBMS_APPLY_ADM Overview	25-1
	DBMS_APPLY_ADM Security Model	25-2
	DBMS_APPLY_ADM Deprecated Subprograms	25-3
	Summary of DBMS_APPLY_ADM Subprograms	25-3
	ALTER_APPLY Procedure	25-5
	CLEAR_KEY_COLUMNS Procedure	25-10
	COMPARE_OLD_VALUES Procedure	25-11
	CREATE_APPLY Procedure	25-13
	CREATE_OBJECT_DEPENDENCY Procedure	25-19
	DELETE_ALL_ERRORS Procedure	25-20
	DELETE_ERROR Procedure	25-20
	DROP_APPLY Procedure	25-21
	DROP_OBJECT_DEPENDENCY Procedure	25-22
	EXECUTE_ALL_ERRORS Procedure	25-23
	EXECUTE_ERROR Procedure	25-24
	GET_ERROR_MESSAGE Function	25-26
	HANDLE_COLLISIONS	25-28
	SET_DML_CONFLICT_HANDLER Procedure	25-28
	SET_DML_HANDLER Procedure	25-34
	SET_ENQUEUE_DESTINATION Procedure	25-38
	SET_EXECUTE Procedure	25-40
	SET_GLOBAL_INSTANTIATION_SCN Procedure	25-41
	SET_KEY_COLUMNS Procedures	25-45
	SET_PARAMETER Procedure	25-48
	SET_REPERROR_HANDLER Procedure	25-69
	SET_SCHEMA_INSTANTIATION_SCN Procedure	25-70
	SET_TABLE_INSTANTIATION_SCN Procedure	25-73
	SET_UPDATE_CONFLICT_HANDLER Procedure	25-75
	SET_VALUE_DEPENDENCY Procedure	25-79
	START_APPLY Procedure	25-80
	STOP_APPLY Procedure	25-81



26 DBMS_AQ

	DBMS_AQ Security Model	26-1
	DBMS_AQ Constants	26-2
	DBMS_AQ Data Types	26-3
	DBMS_AQ Operational Notes	26-5
	Summary of DBMS_AQ Subprograms	26-5
	BIND_AGENT Procedure	26-6
	DEQUEUE Procedure	26-7
	DEQUEUE_ARRAY Function	26-9
	ENQUEUE Procedure	26-10
	ENQUEUE_ARRAY Function	26-11
	LISTEN Procedures	26-12
	POST Procedure	26-13
	REGISTER Procedure	26-14
	SEEK Procedure	26-15
	UNBIND_AGENT Procedure	26-16
	UNREGISTER Procedure	26-16
27	DBMS_AQADM	
	DBMS_AQADM Security Model	27-1
	DBMS_AQADM Constants	27-2
	DBMS_AQADM Subprogram Groups	27-3
	DBMS_AQADM Queue Table Subprograms	27-3
	DBMS_AQADM Privilege Subprograms	27-4
	DBMS_AQADM Queue Subprograms	27-4
	DBMS_AQADM Subscriber Subprograms	27-5
	DBMS_AQADM OKafka Subprograms	27-5
	DBMS_AQADM Propagation Subprograms	27-5
	DBMS_AQADM Miscellaneous Subprograms	27-6
	DBMS_AQADM Agent Subprograms	27-6
	DBMS_AQADM Alias Subprograms	27-7
	Summary of DBMS_AQADM Subprograms	27-7
	ADD_ALIAS_TO_LDAP Procedure	27-10
	ADD_SUBSCRIBER Procedure	27-10
	ALTER_AQ_AGENT Procedure	27-11
	ALTER_PROPAGATION_SCHEDULE Procedure	27-12
	ALTER_QUEUE Procedure	27-13
	ALTER_QUEUE_TABLE Procedure	27-14
	ALTER_SHARDED_QUEUE Procedure	27-15
	ALTER_SUBSCRIBER Procedure	27-16



ALTER_TRANSACTIONAL_EVENT_QUEUE Procedure	27-16
CREATE_AQ_AGENT Procedure	27-17
CREATE_DATABASE_KAFKA_TOPIC Procedure	27-18
CREATE_NP_QUEUE Procedure	27-19
CREATE_QUEUE Procedure	27-20
CREATE_QUEUE_TABLE Procedure	27-21
CREATE_SHARDED_QUEUE Procedure	27-24
CREATE_EXCEPTION_QUEUE Procedure	27-25
CREATE_EQ EXCEPTION_QUEUE Procedure	27-26
CREATE_TRANSACTIONAL_EVENT_QUEUE Procedure	27-26
DEL_ALIAS_FROM_LDAP Procedure	27-27
DISABLE_DB_ACCESS Procedure	27-28
DISABLE_PROPAGATION_SCHEDULE Procedure	27-28
DROP_AQ_AGENT Procedure	27-29
DROP_DATABASE_KAFKA_TOPIC Procedure	27-29
DROP_QUEUE Procedure	27-30
DROP_QUEUE_TABLE Procedure	27-30
DROP_SHARDED_QUEUE Procedure	27-31
DROP_TRANSACTIONAL_EVENT_QUEUE Procedure	27-31
ENABLE_DB_ACCESS Procedure	27-32
ENABLE_JMS_TYPES Procedure	27-32
ENABLE_PROPAGATION_SCHEDULE Procedure	27-33
GET_MAX_STREAMS_POOL Procedure	27-33
GET_MIN_STREAMS_POOL Procedure	27-34
GET_QUEUE_PARAMETER Procedure	27-34
GET_WATERMARK Procedure	27-37
GRANT_QUEUE_PRIVILEGE Procedure	27-37
GRANT_SYSTEM_PRIVILEGE Procedure	27-37
MIGRATE_QUEUE_TABLE Procedure	27-38
MOVE_QUEUE_TABLE Procedure	27-39
PURGE_QUEUE_TABLE Procedure	27-41
QUEUE_SUBSCRIBERS Function	27-42
REMOVE_SUBSCRIBER Procedure	27-42
REVOKE_QUEUE_PRIVILEGE Procedure	27-43
REVOKE_SYSTEM_PRIVILEGE Procedure	27-43
SCHEDULE_PROPAGATION Procedure	27-44
SET_QUEUE_PARAMETER Procedure	27-46
SET_MAX_STREAMS_POOL Procedure	27-49
SET_MIN_STREAMS_POOL Procedure	27-49
SET_WATERMARK Procedure	27-49
START_QUEUE Procedure	27-50
STOP QUEUE Procedure	27-50



	UNSCHEDULE_PROPAGATION Procedure	27-51
	UNSET_QUEUE_PARAMETER Procedure VERIFY_QUEUE_TYPES Procedure	27-52 27-54
	VERIFI_QUEUE_ITFES Flucedule	21-34
28	DBMS_AQELM	
	DBMS_AQELM Security Model	28-1
	Summary of DBMS_AQELM Subprograms	28-1
	SET_MAILHOST Procedure	28-1
	SET_MAILPORT Procedure	28-2
	SET_SENDFROM Procedure	28-2
29	DBMS_AQIN	
	DBMS_AQIN Security Model	29-1
30	DBMS_AQMIGTOOL	
	DBMS_AQMIGTOOL Security Model	30-1
	DBMS_AQMIGTOOL Constants	30-1
	Summary of DBMS_AQMIGTOOL Subprograms	30-2
	CANCEL_MIGRATION Procedure	30-3
	CHECK_MIGRATED_MESSAGES Procedure	30-4
	CHECK_MIGRATION_TO_TXEVENTQ Procedure	30-4
	CHECK_STATUS Procedure	30-5
	CLEAR_UNSUPPORTED_FEATURE_TABLE Procedure	30-7
	COMMIT_MIGRATION Procedure	30-8
	DISABLE_MIGRATION_CHECK Procedure	30-8
	INIT_MIGRATION Procedure	30-9
	PURGE_QUEUE_MESSAGES Procedure	30-11
	RECOVER_MIGRATION Procedure	30-12
	RENAME_QUEUE Procedure	30-13
31	DBMS_ASSERT	
	DBMS_ASSERT Operational Notes	31-1
	Summary of DBMS_ASSERT Subprograms	31-1
	ENQUOTE_LITERAL Function	31-2
	ENQUOTE_NAME Function	31-2
	NOOP Functions	31-4
	QUALIFIED_SQL_NAME Function	31-4
	SCHEMA_NAME Function	31-5



SIMPLE_SQL_NAME Function	31-5
SQL_OBJECT_NAME Function	31-6
DBMS_AUDIT_MGMT	
DBMS_AUDIT_MGMT Overview	32-1
DBMS_AUDIT_MGMT Deprecated and Desupported Subprograms	32-2
DBMS_AUDIT_MGMT Security Model	32-3
DBMS_AUDIT_MGMT Constants	32-3
DBMS_AUDIT_MGMT Views	32-5
DBMS_AUDIT_MGMT Subprogram Groups	32-5
DBMS_AUDIT_MGMT Audit Trail Management Subprograms	32-5
DBMS_AUDIT_MGMT Audit Trail Cleanup Subprograms	32-6
Summary of DBMS_AUDIT_MGMT Subprograms	32-7
ALTER_PARTITION_INTERVAL Procedure	32-8
CLEAN_AUDIT_TRAIL Procedure	32-8
CLEAR_AUDIT_TRAIL_PROPERTY Procedure	32-11
CLEAR_LAST_ARCHIVE_TIMESTAMP Procedure	32-12
CREATE_PURGE_JOB Procedure	32-14
DEINIT_CLEANUP Procedure	32-15
DROP_OLD_UNIFIED_AUDIT_TABLES Procedure	32-16
DROP_PURGE_JOB Procedure	32-17
GET_AUDIT_COMMIT_DELAY Function	32-17
GET_ AUDIT_TRAIL_PROPERTY_VALUE Function	32-18
GET_LAST_ARCHIVE_TIMESTAMP Function	32-19
INIT_CLEANUP Procedure	32-20
IS_CLEANUP_INITIALIZED Function	32-22
LOAD_UNIFIED_AUDIT_FILES Procedure	32-23
SET_AUDIT_TRAIL_LOCATION Procedure	32-24
SET_AUDIT_TRAIL_PROPERTY Procedure	32-26
SET_LAST_ARCHIVE_TIMESTAMP Procedure	32-28
SET_PURGE_JOB_INTERVAL Procedure	32-30
SET_PURGE_JOB_STATUS Procedure	32-31
TRANSFER_UNIFIED_AUDIT_RECORDS Procedure	32-32
DBMS_AUDIT_UTIL	
DBMS_AUDIT_UTIL Overview	33-1
DBMS_AUDIT_UTIL Security Model	33-1
DBMS_AUDIT_UTIL Views	33-1
Summary of DBMS_AUDIT_UTIL Subprograms	33-2
DECODE_RLS_INFO_ATRAIL_FGA Function	33-2



	DECODE_RLS_INFO_ATRAIL_STD FUNCTION	33-3
	DECODE_RLS_INFO_ATRAIL_UNI Function	33-4
	DECODE_RLS_INFO_ATRAIL_XML Function	33-5
34	DBMS_AUTO_CLUSTERING	
	DBMS_AUTO_CLUSTERING Overview	34-1
	Summary of DBMS_AUTO_CLUSTERING Subprograms	34-1
	CONFIGURE Procedure	34-2
	RECOMMEND_CLUSTERING_METHOD Function	34-4
	VERIFY_RECOMMENDATION Procedure	34-5
	APPLY_RECOMMENDATION Procedure	34-6
	GET_RECOMMENDATION Function	34-7
	REPORT ACTIVITY Function	34-7
	REPORT_LAST_ACTIVITY Function	34-8
35	DBMS_AUTO_SQLTUNE	
	DBMS_AUTO_SQLTUNE Overview	35-1
	DBMS_AUTO_SQLTUNE Security Model	35-1
	Summary of DBMS_AUTO_SQLTUNE Subprograms	35-1
	EXECUTE_AUTO_TUNING_TASK Function and Procedure	35-2
	REPORT_AUTO_TUNING_TASK Function	35-3
	SET_AUTO_TUNING_TASK_PARAMETER Procedures	35-4
36	DBMS_AUTO_INDEX	
	DBMS_AUTO_INDEX Overview	36-1
	Summary of DBMS_AUTO_INDEX Subprograms	36-1
	CONFIGURE Procedure	36-1
	DROP_AUTO_INDEXES Procedure	36-6
	DROP_SECONDARY_INDEXES Procedure	36-7
	REPORT_ACTIVITY Function	36-8
	REPORT_LAST_ACTIVITY Function	36-10
	RECOMMEND Function	36-12
37	DBMS_AUTO_MV	
	Using DBMS_AUTO_MV	37-1
	Summary of DBMS_AUTO_MV Subprograms	37-1
	CONFIGURE Procedure	37-2
	DROP_AUTO_MVS Procedure	37-4



	RECOMMEND Function	37-5
	REFRESH Procedure	37-7
	REPORT_ACTIVITY Function	37-7
	REPORT_LAST_ACTIVITY Function	37-8
38	DBMS_AUTO_REPORT	
	DBMS_AUTO_REPORT Overview	38-2
	DBMS_AUTO_REPORT Security Model	38-2
	Summary of DBMS_AUTO_REPORT Subprograms	38-2
	FINISH_REPORT_CAPTURE Procedure	38-2
	REPORT_REPOSITORY_DETAIL Function	38-2
	REPORT_REPOSITORY_DETAIL_XML Function	38-3
	REPORT_REPOSITORY_LIST_XML Function	38-3
	START_REPORT_CAPTURE Procedure	38-5
	PURGE_ALL_REPORTS Function	38-5
	PURGE_REPORTS_BY_RETENTION Function	38-5
39	DBMS_AUTO_TASK_ADMIN	
	DBMS_AUTO_TASK_ADMIN Deprecated Subprograms	39-2
	DBMS_AUTO_TASK_ADMIN Security Model	39-1
	DBMS_AUTO_TASK_ADMIN Constants	39-1
	Summary of DBMS_AUTO_TASK_ADMIN Subprograms	39-2
	DISABLE Procedures	39-2
	ENABLE Procedures	39-3
	GET_CLIENT_ATTRIBUTES Procedure	39-4
	GET_P1_RESOURCES Procedure	39-4
	OVERRIDE_PRIORITY Procedures	39-5
	SET_CLIENT_SERVICE Procedure	39-6
	SET_P1_RESOURCES Procedure	39-6
40	DBMS_AUTO_ZONEMAP	
	DBMS_AUTO_TASK_ADMIN Security Model	40-2
	Summary of DBMS_AUTO_ZONEMAP Subprograms	40-2
	ACTIVITY_REPORT Function	40-1
	CONFIGURE Procedure	40-4
41	DBMS_AVTUNE	
	DBMS_AVTUNE Overview	41-3



	DBMS_AVTUNE Security Model	41-1
	Summary of DBMS_AVTUNE Subprograms	41-1
	AUTO_CACHE_CREATE Procedure	41-2
	AUTO_CACHE_DISABLE Procedure	41-3
	AUTO_CACHE_ENABLE Procedure	41-3
	AUTO_CACHE_MODIFY Procedure	41-4
	AUTO_CACHE_REFRESH Procedure	41-4
42 DE Usi Sur	AUTO_CACHE_REMOVE Procedure	41-5
	AUTO_CACHE_TUNE Procedure	41-5
	AUTO_CACHE_STAR_DISABLE Procedure	41-6
	AUTO_CACHE_STAR_ENABLE Procedure	41-6
	AUTO_CACHE_STAR_MODIFY Procedure	41-7
	AUTO_CACHE_STAR_REFRESH Procedure	41-7
42	DBMS_AW_STATS	
	Using DBMS_AW_STATS	42-1
	Summary of DBMS_AW_STATS Subprograms	42-1
	ANALYZE Procedure	42-1
	CLEAR Procedure	42-4
43	DBMS_BLOCKCHAIN_TABLE	
	DBMS_BLOCKCHAIN_TABLE Overview	43-1
	DBMS_BLOCKCHAIN_TABLE Security Model	43-2
	Summary of DBMS_BLOCKCHAIN_TABLE Subprograms	43-2
	ADD_INTERVAL_PARTITIONING Procedure	43-4
	COUNTERSIGN_ROW Procedure	43-5
	COUNTERSIGN_ROW_SPECIFIED_BY_KEY_COLUMNS Procedure	43-6
	DELETE_EXPIRED_ROWS Procedure	43-7
	GET_BLOCKCHAIN_DIGEST Function	43-8
	GET_BLOCKCHAIN_DIGEST_FOR_SELECTED_ROWS Function	43-9
	GET_BYTES_FOR_ROW_HASH Procedure	43-10
	GET_BYTES_FOR_ROW_HASH_SPECIFIED_BY_KEY_COLUMNS Procedure	43-12
	GET_BYTES_FOR_ROW_SIGNATURE Procedure	43-13
	GET_BYTES_FOR_ROW_SIGNATURE_SPECIFIED_BY_KEY_COLUMNS Procedure	43-13
	GET_SIGNED_BLOCKCHAIN_DIGEST Function	43-14
	GET_SIGNED_BLOCKCHAIN_DIGEST_FOR_SELECTED_ROWS Function	43-16
	SIGN_ROW Procedure	43-18
	SIGN_ROW_SPECIFIED_BY_KEY_COLUMNS Procedure	43-19
	SIGN_ROW_SPECIFIED_BY_KEY_COLUMNS_WITH_COUNTERSIGNATURE Procedure	43-20



SIGN_ROW_WITH_COUNTERSIGNATURE Procedure	43-22
VERIFY_ROWS Procedure	43-24
VERIFY_TABLE_BLOCKCHAIN Procedure	43-25
VERIFY_USER_BLOCKCHAIN_ROWS Procedure	43-26
DBMS_BLOCKER_RESOLVER	
DBMS_BLOCKER_RESOLVER Overview	44-1
DBMS_BLOCKER_RESOLVER Security Model	44-1
DBMS_BLOCKER_RESOLVER Constants	44-2
DBMS_BLOCKER_RESOLVER Exceptions	44-3
Summary of DBMS_BLOCKER_RESOLVER Subprograms	44-3
SET Procedure	44-3
DBMS_CAPTURE_ADM	
DBMS_CAPTURE_ADM Overview	45-1
DBMS_CAPTURE_ADM Security Model	45-1
Summary of DBMS_CAPTURE_ADM Subprograms	45-2
ABORT_GLOBAL_INSTANTIATION Procedure	45-3
ABORT_SCHEMA_INSTANTIATION Procedure	45-4
ABORT_SYNC_INSTANTIATION Procedure	45-5
ABORT_TABLE_INSTANTIATION Procedure	45-5
ALTER_CAPTURE Procedure	45-6
ALTER_SYNC_CAPTURE Procedure	45-11
BUILD Procedure	45-12
CREATE_CAPTURE Procedure	45-13
CREATE_SYNC_CAPTURE Procedure	45-23
DROP_CAPTURE Procedure	45-25
INCLUDE_EXTRA_ATTRIBUTE Procedure	45-26
PREPARE_GLOBAL_INSTANTIATION Procedure	45-27
PREPARE_SCHEMA_INSTANTIATION Procedure	45-28
PREPARE_SYNC_INSTANTIATION Function	45-29
PREPARE_TABLE_INSTANTIATION Procedure	45-30
SET_PARAMETER Procedure	45-31
START_CAPTURE Procedure	45-46
STOP_CAPTURE Procedure	45-46
DBMS_CACHEUTIL	
DBMS_CACHEUTIL Overview	46-1
DBMS_CACHEUTIL Security Model	46-2



	Summary of DBMS_CACHEUTIL Subprograms	46-2
	DISSOLVE_AFFINITY Procedure	46-3
	DISSOLVE_READMOSTLY Procedure	46-3
	GRAB_AFFINITY Procedure	46-4
	GRAB_READMOSTLY Procedure	46-5
	LIST_READMOSTLY Procedure	46-6
	OBJECT_DOWNCONVERT Procedure	46-6
	TRUE_CACHE_KEEP Procedure	46-7
	TRUE_CACHE_UNKEEP Procedure	46-7
47	DBMS_CLOUD	
	Installing DBMS_CLOUD	47-1
	DBMS_CLOUD Endpoint Management	47-1
	DBMS_CLOUD Subprograms and REST APIs	47-2
	DBMS_CLOUD for Access Management	47-2
	CREATE_CREDENTIAL Procedure	47-2
	DROP_CREDENTIAL Procedure	47-5
	UPDATE_CREDENTIAL Procedure	47-6
	DBMS_CLOUD for Objects and Files	47-7
	COPY_COLLECTION Procedure	47-8
	COPY_DATA Procedure	47-11
	COPY_DATA Procedure for Avro or Parquet Files	47-15
	COPY_OBJECT Procedure	47-17
	CREATE_EXTERNAL_PART_TABLE Procedure	47-18
	CREATE_EXTERNAL_TABLE Procedure	47-25
	CREATE_EXTERNAL_TABLE Procedure for Apache Iceberg	47-28
	CREATE_EXTERNAL_TABLE Procedure for Avro or Parquet Files	47-30
	CREATE_HYBRID_PART_TABLE Procedure	47-33
	DELETE_ALL_OPERATIONS Procedure	47-36
	DELETE_FILE Procedure	47-36
	DELETE_OBJECT Procedure	47-37
	DELETE_OPERATION Procedure	47-38
	EXPORT_DATA Procedure	47-38
	GET_OBJECT Procedure and Function	47-43
	LIST_FILES Function	47-45
	LIST_OBJECTS Function	47-46
	MOVE_OBJECT Procedure	47-47
	PUT_OBJECT Procedure	47-48
	SYNC_EXTERNAL_PART_TABLE Procedure	47-50
	VALIDATE_EXTERNAL_PART_TABLE Procedure	47-50
	VALIDATE_EXTERNAL_TABLE Procedure	47-51



VALIDATE_HYBRID_PART_TABLE Procedure	47-52
DBMS_CLOUD for Bulk File Management	47-53
BULK_COPY Procedure	47-54
BULK_DELETE Procedure	47-56
BULK_DOWNLOAD Procedure	47-57
BULK_MOVE Procedure	47-59
BULK_UPLOAD Procedure	47-61
DBMS_CLOUD REST APIS	47-62
DBMS_CLOUD REST API Overview	47-63
DBMS_CLOUD REST API Constants	47-63
DBMS_CLOUD REST API Results Cache	47-64
GET_RESPONSE_HEADERS Function	47-64
GET_RESPONSE_RAW Function	47-65
GET_RESPONSE_STATUS_CODE Function	47-65
GET_RESPONSE_TEXT Function	47-66
GET_API_RESULT_CACHE_SIZE Function	47-66
SEND_REQUEST Function and Procedure	47-66
SET_API_RESULT_CACHE_SIZE Procedure	47-68
DBMS_CLOUD REST API Examples	47-69
DBMS_CLOUD URI Formats	47-73
Oracle Cloud Infrastructure Object Storage Native URI Format	47-73
Oracle Cloud Infrastructure Object Storage Swift URI Format	47-75
Oracle Cloud Infrastructure Object Storage URI Format Using Pre-Authenticated	
Request URL	47-76
URI Format Using Public URL	47-77
Oracle Cloud Infrastructure Object Storage Classic URI Format	47-78
Amazon S3 URI Format	47-78
Amazon S3 Compatible URI Format	47-79
GitHub Raw URL Format	47-80
Additional Customer-Managed URI Formats	47-81
DBMS_CLOUD Package Format Options	47-83
DBMS_CLOUD Package Format Options for EXPORT_DATA	47-94
DBMS_CLOUD Avro and Parquet Support	47-98
DBMS_CLOUD Package Format Options for Avro or Parquet	47-98
DBMS_CLOUD Package Avro to Oracle Data Type Mapping	47-100
DBMS_CLOUD Package ORC to Oracle Data Type Mapping	47-100
DBMS_CLOUD Package Parquet to Oracle Data Type Mapping	47-101
DBMS_CLOUD Package Oracle Data Type to Parquet Mapping	47-102
DBMS_CLOUD Package Avro and Parquet Complex Types	47-103
DBMS_CLOUD Package Avro and Parquet to Oracle Column Name Mapping	47-104
DBMS_CLOUD Exceptions	47-106



48 DBMS_CLOUD_AI

	DBMS_CLOUD_AI Overview	48-1
	Summary of DBMS_CLOUD_AI Subprograms	48-1
	CREATE_PROFILE Procedure	48-1
	DROP_PROFILE Procedure	48-2
	ENABLE_PROFILE Procedure	48-3
	DISABLE_PROFILE Procedure	48-3
	GET_PROFILE Function	48-4
	GET_PROFILE Procedure	48-4
	SET_ATTRIBUTE Procedure	48-5
	SET_PROFILE Procedure	48-6
	GENERATE Function	48-7
	Profile Attributes	48-10
49	DBMS_CLOUD_NOTIFICATION	
	DBMS_CLOUD_NOTIFICATION Overview	49-1
	Summary of DBMS_CLOUD_NOTIFICATION Subprograms	49-1
	SEND_DATA Procedure	49-1
	SEND_MESSAGE Procedure	49-5
50	DBMS_CLOUD_PIPELINE	
	Summary of DBMS_CLOUD_PIPELINE Subprograms	50-1
	CREATE_PIPELINE Procedure	50-1
	DROP_PIPELINE Procedure	50-2
	RESET_PIPELINE Procedure	50-2
	RUN_PIPELINE_ONCE Procedure	50-4
	SET_ATTRIBUTE Procedure	50-4
	START_PIPELINE Procedure	50-5
	STOP_PIPELINE Procedure	50-6
	DBMS_CLOUD_PIPELINE Attributes	50-6
	DBMS_CLOUD_PIPELINE Views	50-8
51	DBMS_CLOUD_REPO	
	DBMS_CLOUD_REPO Overview	51-1
	DBMS_CLOUD_REPO Data Structures	51-2
	DBMS_CLOUD_REPO Subprogram Groups	51-2
	DBMS_CLOUD_REPO Initialization Operations	51-2
	DBMS_CLOUD_REPO Repository Management Operations	51-2
	DBMS_CLOUD_REPO Repository Branch Management Operations	51-3



	DBMS_CLOUD_REPO File Operations	51-3
	DBMS_CLOUD_REPO SQL Install Operations	51-3
	Summary of DBMS_CLOUD_REPO Subprograms	51-4
	CREATE_BRANCH Procedure	51-4
	CREATE_REPOSITORY Procedure	51-5
	DELETE_BRANCH Procedure	51-6
	DELETE_FILE Procedure	51-6
	DELETE_REPOSITORY Procedure	51-7
	EXPORT_OBJECT Procedure	51-8
	EXPORT_SCHEMA Procedure	51-9
	GET_FILE Procedure and Function	51-11
	INIT_AWS_REPO Function	51-12
	INIT_AZURE_REPO Function	51-12
	INIT_GITHUB_REPO Function	51-13
	INIT_REPO Function	51-14
	INSTALL_FILE Procedure	51-14
	INSTALL_SQL Procedure	51-15
	LIST_BRANCHES Function	51-16
	LIST_COMMITS Function	51-17
	LIST_FILES Function	51-18
	LIST_REPOSITORIES Function	51-19
	MERGE_BRANCH Procedure	51-19
	PUT_FILE Procedure	51-20
	UPDATE_REPOSITORY Procedure	51-21
52	DBMS_COMPARISON	
	DBMS_COMPARISON Overview	52-1
	DBMS_COMPARISON Security Model	52-2
	DBMS_COMPARISON Constants	52-3
	DBMS_COMPARISON Views	52-5
	DBMS_COMPARISON Operational Notes	52-5
	DBMS_COMPARISON Data Structures	52-9
	COMPARISON_TYPE Record Type	52-10
	Summary of DBMS_COMPARISON Subprograms	52-10
	COMPARE Function	52-11
	CONVERGE Procedure	52-12
	CREATE_COMPARISON Procedure	52-13
	DROP_COMPARISON Procedure	52-17
	PURGE_COMPARISON Procedure	52-18
	RECHECK Function	52-18



53 DBMS_COMPRESSION

	DBMS_COMPRESSION Overview	53-1
	DBMS_COMPRESSION Security Model	53-1
	DBMS_COMPRESSION Constants	53-1
	DBMS_COMPRESSION Data Structures	53-3
	COMPREC Record Type	53-3
	COMPRECLIST Table Type	53-4
	Summary of DBMS_COMPRESSION Subprograms	53-4
	GET_COMPRESSION_RATIO Procedure	53-4
	GET_COMPRESSION_TYPE Function	53-12
54	DBMS_CONNECTION_POOL	
	Summary of DBMS_CONNECTION_POOL Subprograms	54-1
	ADD_POOL Procedure	54-2
	ALTER_PARAM Procedure	54-4
	CONFIGURE_POOL Procedure	54-5
	REMOVE_POOL Procedure	54-7
	RESTORE_DEFAULTS Procedure	54-8
	START_POOL Procedure	54-8
55	STOP_POOL Procedure DBMS_CQ_NOTIFICATION	54-9
33		
	DBMS_CQ_NOTIFICATION Overview	55-1
	DBMS_CQ_NOTIFICATION Security Model	55-2
	DBMS_CQ_NOTIFICATION Constants	55-2
	DBMS_CQ_NOTIFICATION Operational Notes	55-3
	DBMS_CQ_NOTIFICATION Examples	55-4
	DBMS_CQ_NOTIFICATION Data Structures	55-10
	CQ_NOTIFICATION\$_DESCRIPTOR Object Type	55-11
	CQ_NOTIFICATION\$_QUERY Object Type	55-11
	CQ_NOTIFICATION\$_QUERY_ARRAY Object (Array) Type	55-12
	CQ_NOTIFICATION\$_TABLE Object Type	55-12
	CQ_NOTIFICATION\$_TABLE_ARRAY Object (Array) Type	55-13
	CQ_NOTIFICATION\$_ROW Object Type	55-13
	CQ_NOTIFICATION\$_ROW_ARRAY Object (Array) Type	55-13
	CQ_NOTIFICATION\$_REG_INFO Object Type	55-14
	Summary of DBMS_CQ_NOTIFICATION Subprograms	55-16
	CQ_NOTIFICATION_QUERYID Function	55-17
	DEREGISTER Procedure	55-17



	ENABLE_REG Procedure NEW_REG_START Function REG_END Procedure SET_ROWID_THRESHOLD Procedure	55-18 55-19 55-19
56	DBMS_CREDENTIAL	
	DBMS_CREDENTIAL Overview	56-1
	DBMS_CREDENTIAL Security Model	56-1
	DBMS_CREDENTIAL Operational Notes	56-2
	Summary of DBMS_CREDENTIAL Subprograms	56-2
	CREATE_CREDENTIAL Procedure	56-3
	DISABLE_CREDENTIAL Procedure	56-4
	DROP_CREDENTIAL Procedure	56-5
	ENABLE_CREDENTIAL Procedure	56-6
	UPDATE_CREDENTIAL Procedure	56-6
57	DBMS_CRYPTO	
	DBMS_CRYPTO Overview	57-2
	DBMS_CRYPTO Security Model	57-3
	DBMS_CRYPTO Constants	57-3
	DBMS_CRYPTO Datatypes	57-5
	DBMS_CRYPTO Algorithms	57-5
	DBMS_CRYPTO Restrictions	57-8
	DBMS_CRYPTO Exceptions	57-9
	DBMS_CRYPTO Operational Notes	57-9
	DBMS_CRYPTO Examples	57-11
	Summary of DBMS_CRYPTO Subprograms	57-15
	DECRYPT Functions	57-16
	DECRYPT Procedures	57-17
	ECDHDERIVE_SHAREDSECRET Function	57-18
	ECDH_GENKEYPAIR Function	57-19
	ENCRYPT Functions	57-19
	ENCRYPT Procedures	57-21
	HASH Function	57-22
	HASH_LEN Function	57-23
	MAC Function	57-24
	KMACXOF Function	57-25
	PKDECRYPT Function	57-25
	PKENCRYPT Function	57-26
	RANDOMBYTES Function	57-26



	RANDOMINTEGER Function	57-27
	RANDOMNUMBER Function	57-27
	SIGN Function	57-27
	VERIFY Function	57-29
58	DBMS_CSX_ADMIN	
	DBMS_CSX_ADMIN Overview	58-1
	DBMS_CSX_ADMIN Security Model	58-1
	DBMS_CSX_ADMIN Constants	58-1
	Summary of DBMS_CSX_ADMIN Subprograms	58-2
	GETTOKENTABLEINFO Procedure & Function	58-2
	GETTOKENTABLEINFOBYTABLESPACE Procedure	58-3
	NAMESPACEIDTABLE Function	58-4
	PATHIDTABLE Function	58-4
	QNAMEIDTABLE Function	58-4
59	DBMS_CUBE	
	Using DBMS_CUBE	59-1
	DBMS_CUBE Security Model	59-2
	Using SQL Aggregation Management	59-2
	Subprograms in SQL Aggregation Management	59-3
	Requirements for the Relational Materialized View	59-3
	Permissions for Managing and Querying Cube Materialized Views	59-4
	Example of SQL Aggregation Management	59-4
	Upgrading 10g Analytic Workspaces	59-8
	Summary of DBMS_CUBE Subprograms	59-13
	BUILD Procedure	59-13
	CREATE_EXPORT_OPTIONS Procedure	59-25
	CREATE_IMPORT_OPTIONS Procedure	59-28
	CREATE_MVIEW Function	59-29
	DERIVE_FROM_MVIEW Function	59-34
	DROP_MVIEW Procedure	59-35
	EXPORT_XML Procedure	59-37
	EXPORT_XML_TO_FILE Procedure	59-39
	IMPORT_XML Procedure	59-40
	INITIALIZE_CUBE_UPGRADE Procedure	59-43
	REFRESH_MVIEW Procedure	59-44
	UPGRADE_AW Procedure	59-46
	VALIDATE_XML Procedure	59-47



60 DBMS_CUBE_ADVISE

	DBMS_CUBE_ADVISE Security Model	60-1
	Summary of DBMS_CUBE_ADVISE Subprograms	60-1
	MV_CUBE_ADVICE Function	60-1
	SET_CNS_EXCEPTION_LOG Procedure	60-4
	TRACE Procedure	60-5
61	DBMS_CUBE_LOG	
	Using DBMS_CUBE_LOG	61-1
	DBMS_CUBE_LOG — Logging Types	61-2
	DBMS_CUBE_LOG — Logging Targets	61-2
	DBMS_CUBE_LOG — Verbosity Levels	61-3
	DBMS_CUBE_LOG Security Model	61-3
	DBMS_CUBE_LOG — Creating Cube Logs	61-3
	DBMS_CUBE_LOG — Cube Build Log	61-4
	DBMS_CUBE_LOG — Cube Dimension Compile Log	61-5
	DBMS_CUBE_LOG — Cube Operations Log	61-6
	DBMS_CUBE_LOG — Cube Rejected Records Log	61-7
	Summary of DBMS_CUBE_LOG Subprograms	61-7
	DEFAULT_NAME Function	61-8
	DISABLE Procedure	61-9
	ENABLE Procedure	61-10
	FLUSH Procedure	61-11
	GET_LOG Procedure	61-12
	GET_LOG_SPEC Function	61-13
	GET_PARAMETER Function	61-14
	LEVEL_HIGH Function	61-14
	LEVEL_HIGHEST Function	61-15
	LEVEL_LOW Function	61-15
	LEVEL_LOWEST Function	61-16
	LEVEL_MEDIUM Function	61-16
	SET_LOG_SPEC Procedure	61-17
	SET_PARAMETER Procedure	61-17
	TABLE_CREATE Procedure	61-19
	TARGET_FILE Function	61-20
	TARGET_LOB Function	61-20
	TARGET_TABLE Function	61-20
	TARGET_TRACE Function	61-21
	TYPE_BUILD Function	61-21
	TYPE_DIMENSION_COMPILE Function	61-22



TYPE_OPERATIONS Function	61-22
TYPE_REJECTED_RECORDS Function	61-23
VERSION Function	61-23
DBMS_DATA_MINING	
DBMS_DATA_MINING Overview	62-1
DBMS_DATA_MINING Security Model	62-3
DBMS_DATA_MINING — Machine Learning Functions	62-3
DBMS_DATA_MINING — Model Settings	62-5
DBMS_DATA_MINING — Algorithm Names	62-5
DBMS_DATA_MINING — Automatic Data Preparation	62-6
DBMS_DATA_MINING — Machine Learning Function Settings	62-7
DBMS_DATA_MINING — Global Settings	62-20
DBMS_DATA_MINING — Algorithm Specific Model Settings	62-25
DBMS_DATA_MINING — Algorithm Settings: ALGO_EXTENSIBLE_LANG	62-25
DBMS_DATA_MINING — Algorithm Settings: CUR Matrix Decomposition	62-27
DBMS_DATA_MINING — Algorithm Settings: Decision Tree	62-28
DBMS_DATA_MINING — Algorithm Settings: Expectation Maximization	62-29
DBMS_DATA_MINING — Algorithm Settings: Explicit Semantic Analysis	62-34
DBMS_DATA_MINING — Algorithm Settings: Exponential Smoothing	62-35
DBMS_DATA_MINING — Algorithm Settings: Generalized Linear Model	62-43
DBMS_DATA_MINING — Algorithm Settings: k-Means	62-47
DBMS_DATA_MINING - Algorithm Settings: Multivariate State Estimation Technique - Sequential Probability Ratio Test	62-50
DBMS_DATA_MINING — Algorithm Settings: Naive Bayes	62-51
DBMS_DATA_MINING — Algorithm Settings: Neural Network	62-52
DBMS_DATA_MINING — Algorithm Settings: Non-Negative Matrix Factorization	62-56
DBMS_DATA_MINING — Algorithm Settings: O-Cluster	62-57
DBMS_DATA_MINING — Algorithm Settings: Random Forest	62-58
DBMS_DATA_MINING — Algorithm Constants and Settings: Singular Value	
·	62-59
DBMS_DATA_MINING — Algorithm Settings: Support Vector Machine	62-62
DBMS_DATA_MINING — Algorithm Settings: XGBoost	62-65
	62-76
	62-77
	62-77
	62-78
DBMS_DATA_MINING Datatypes	62-79
Deprecated Types	62-80
Summary of DBMS_DATA_MINING Subprograms	62-84
ADD_COST_MATRIX Procedure	62-87
ADD_PARTITION Procedure	62-89
	TYPE_REJECTED_RECORDS Function VERSION Function DBMS_DATA_MINING DBMS_DATA_MINING Overview DBMS_DATA_MINING Security Model DBMS_DATA_MINING — Machine Learning Functions DBMS_DATA_MINING — Model Settings DBMS_DATA_MINING — Algorithm Names DBMS_DATA_MINING — Automatic Data Preparation DBMS_DATA_MINING — Automatic Data Preparation DBMS_DATA_MINING — Automatic Data Preparation DBMS_DATA_MINING — Algorithm Sectifice Model Settings DBMS_DATA_MINING — Algorithm Sectifice Model Settings DBMS_DATA_MINING — Algorithm Settings: ALGO_EXTENSIBLE_LANG DBMS_DATA_MINING — Algorithm Settings: CUR Matrix Decomposition DBMS_DATA_MINING — Algorithm Settings: Expectation Maximization DBMS_DATA_MINING — Algorithm Settings: Expectation Maximization DBMS_DATA_MINING — Algorithm Settings: Expectation Maximization DBMS_DATA_MINING — Algorithm Settings: Exponential Smoothing DBMS_DATA_MINING — Algorithm Settings: Expenential Smoothing DBMS_DATA_MINING — Algorithm Settings: Remeralized Linear Model DBMS_DATA_MINING — Algorithm Settings: Multivariate State Estimation Technique - Sequential Probability Ratio Test DBMS_DATA_MINING — Algorithm Settings: Non-Negative Matrix Factorization DBMS_DATA_MINING — Algorithm Settings: Non-Negative Matrix Factorization DBMS_DATA_MINING — Algorithm Settings: Random Forest DBMS_DATA_MINING — Algorithm Settings: Random Forest DBMS_DATA_MINING — Algorithm Settings: Support Vector Machine DBMS_DATA_MINING — Algorithm Settings: Support Vector Machine DBMS_DATA_MINING — Algorithm Settings: Support Vector Machine DBMS_DATA_MINING — Solver Settings: Adam DBMS_DATA_MINING — Solver Settings: Adam DBMS_DATA_MINING — Solver Settings: Adam DBMS_DATA_MINING — Solver Settings: LBFGS DBMS_DATA_MINING — Solver Settings: LBFGS



ALTER_REVERSE_EXPRESSION Procedure	62-90
APPLY Procedure	62-93
COMPUTE_CONFUSION_MATRIX Procedure	62-96
COMPUTE_CONFUSION_MATRIX_PART Procedure	62-102
COMPUTE_LIFT Procedure	62-109
COMPUTE_LIFT_PART Procedure	62-113
COMPUTE_ROC Procedure	62-118
COMPUTE_ROC_PART Procedure	62-123
CREATE_MODEL Procedure	62-127
CREATE_MODEL2 Procedure	62-131
Create Model Using Registration Information	62-133
DROP_ALGORITHM Procedure	62-133
DROP_PARTITION Procedure	62-134
DROP_MODEL Procedure	62-134
EXPORT_MODEL Procedure	62-135
EXPORT_SERMODEL Procedure	62-138
FETCH_JSON_SCHEMA Procedure	62-139
GET_ASSOCIATION_RULES Function	62-139
GET_FREQUENT_ITEMSETS Function	62-144
GET_MODEL_COST_MATRIX Function	62-146
GET_MODEL_DETAILS_AI Function	62-147
GET_MODEL_DETAILS_EM Function	62-149
GET_MODEL_DETAILS_EM_COMP Function	62-150
GET_MODEL_DETAILS_EM_PROJ Function	62-152
GET_MODEL_DETAILS_GLM Function	62-154
GET_MODEL_DETAILS_GLOBAL Function	62-157
GET_MODEL_DETAILS_KM Function	62-159
GET_MODEL_DETAILS_NB Function	62-161
GET_MODEL_DETAILS_NMF Function	62-163
GET_MODEL_DETAILS_OC Function	62-164
GET_MODEL_SETTINGS Function	62-166
GET_MODEL_SIGNATURE Function	62-167
GET_MODEL_DETAILS_SVD Function	62-169
GET_MODEL_DETAILS_SVM Function	62-171
GET_MODEL_DETAILS_XML Function	62-173
GET_MODEL_TRANSFORMATIONS Function	62-175
GET_TRANSFORM_LIST Procedure	62-178
IMPORT_MODEL Procedure	62-181
IMPORT_ONNX_MODEL Procedure	62-185
IMPORT_SERMODEL Procedure	62-186
JSON Schema for R Extensible Algorithm	62-187
REGISTER_ALGORITHM Procedure	62-191



	RANK_APPLY Procedure	62-192
	REMOVE_COST_MATRIX Procedure	62-195
	RENAME_MODEL Procedure	62-196
63	DBMS_DATA_MINING_TRANSFORM	
	DBMS_DATA_MINING_TRANSFORM Overview	63-1
	DBMS_DATA_MINING_TRANSFORM Operational Notes	63-4
	DBMS_DATA_MINING_TRANSFORM — About Transformation Lists	63-6
	DBMS_DATA_MINING_TRANSFORM — About Stacking and Stack Procedures	63-8
	DBMS_DATA_MINING_TRANSFORM — Nested Data Transformations	63-9
	DBMS_DATA_MINING_TRANSFORM Security Model	63-13
	DBMS_DATA_MINING_TRANSFORM Datatypes	63-13
	DBMS_DATA_MINING_TRANSFORM Constants	63-14
	Summary of DBMS_DATA_MINING_TRANSFORM Subprograms	63-15
	CREATE_BIN_CAT Procedure	63-17
	CREATE_BIN_NUM Procedure	63-18
	CREATE_CLIP Procedure	63-20
	CREATE_COL_REM Procedure	63-21
	CREATE_MISS_CAT Procedure	63-23
	CREATE_MISS_NUM Procedure	63-24
	CREATE_NORM_LIN Procedure	63-25
	DESCRIBE_STACK Procedure	63-27
	GET_EXPRESSION Function	63-28
	INSERT_AUTOBIN_NUM_EQWIDTH Procedure	63-29
	INSERT_BIN_CAT_FREQ Procedure	63-33
	INSERT_BIN_NUM_EQWIDTH Procedure	63-37
	INSERT_BIN_NUM_QTILE Procedure	63-41
	INSERT_BIN_SUPER Procedure	63-43
	INSERT_CLIP_TRIM_TAIL Procedure	63-47
	INSERT_CLIP_WINSOR_TAIL Procedure	63-49
	INSERT_MISS_CAT_MODE Procedure	63-52
	INSERT_MISS_NUM_MEAN Procedure	63-54
	INSERT_NORM_LIN_MINMAX Procedure	63-57
	INSERT_NORM_LIN_SCALE Procedure	63-59
	INSERT_NORM_LIN_ZSCORE Procedure	63-61
	SET_EXPRESSION Procedure	63-63
	SET_TRANSFORM Procedure	63-65
	STACK_BIN_CAT Procedure	63-66
	STACK_BIN_NUM Procedure	63-68
	STACK_CLIP Procedure	63-70
	STACK_COL_REM Procedure	63-72



	STACK_MISS_CAT Procedure	63-74
	STACK_MISS_NUM Procedure	63-76
	STACK_NORM_LIN Procedure	63-78
	XFORM_BIN_CAT Procedure	63-80
	XFORM_BIN_NUM Procedure	63-82
	XFORM_CLIP Procedure	63-84
	XFORM_COL_REM Procedure	63-86
	XFORM_EXPR_NUM Procedure	63-87
	XFORM_EXPR_STR Procedure	63-89
	XFORM_MISS_CAT Procedure	63-92
	XFORM_MISS_NUM Procedure	63-94
	XFORM_NORM_LIN Procedure	63-95
	XFORM_STACK Procedure	63-97
64	DBMS_DATAPUMP	
[DBMS_DATAPUMP Overview	64-1
!	DBMS_DATAPUMP Security Model	64-1
!	DBMS_DATAPUMP Constants	64-2
!	DBMS_DATAPUMP Data Structures	64-3
:	Summary of DBMS_DATAPUMP Subprograms	64-12
	ADD_FILE Procedure	64-13
	ATTACH Function	64-21
	DATA_FILTER Procedures	64-22
	DATA_REMAP Procedure	64-25
	DETACH Procedure	64-26
	GET_DUMPFILE_INFO Procedure	64-27
	GET_STATUS Procedure	64-30
	LOG_ENTRY Procedure	64-32
	METADATA_FILTER Procedure	64-33
	METADATA_REMAP Procedure	64-37
	METADATA_TRANSFORM Procedure	64-39
	OPEN Function	64-44
	SET_PARALLEL Procedure	64-47
	SET_PARAMETER Procedures	64-48
	START_JOB Procedure	64-57
	STOP_JOB Procedure	64-58
	WAIT_FOR_JOB Procedure	64-60



DBMS_DB_VERSION	
DBMS_DB_VERSION Overview	65-1
DBMS_DB_VERSION Constants	65-2
DBMS_DB_VERSION Examples	65-3
DBMS_DBCOMP	
Using DBMS_DBCOMP	66-1
DBMS_DBCOMP Security Model	66-2
Summary of the DBMS_DBCOMP Subprogram	66-2
DBCOMP Procedure	66-2
DBMS_DBFS_CONTENT	
DBMS_DBFS_CONTENT Overview	67-1
DBMS_DBFS_CONTENT Security Model	67-1
DBMS_DBFS_CONTENT Constants	67-2
Exceptions	67-13
DBMS_DBFS_CONTENT Operational Notes	67-13
DBMS_DBFS_CONTENT Data Structures	67-14
DBMS_DBFS_CONTENT FEATURE_T Record Type	67-15
DBMS_DBFS_CONTENT MOUNT_T Record Type	67-16
DBMS_DBFS_CONTENT PATH_ITEM_T Record Type	67-16
DBMS_DBFS_CONTENT PROP_ITEM_T Record Type	67-18
PROPERTY_T Record Type	67-19
DBMS_DBFS_CONTENT STORE_T Record Type	67-19
DBMS_DBFS_CONTENT FEATURES_T Table Type	67-20
MOUNTS T Table Type	67-20
DBMS DBFS CONTENT PATH ITEMS T Table Type	67-20
DBMS_DBFS_CONTENT PROP_ITEMS_T Table Type	67-21
DBMS_DBFS_CONTENT PROPERTIES_T Table Type	67-21
STORES T Table Type	67-21
Summary of DBMS_DBFS_CONTENT Subprograms	67-21
CHECKACCESS Function	67-24
CHECKSPI Functions and Procedures	67-24
CREATEDIRECTORY Procedures	67-25
CREATEFILE Procedures	67-26
CREATELINK Procedures	67-27
CREATEREFERENCE Procedures	67-28
DECODEFEATURES Function	67-28
DELETECONTENT Procedure	67-29



DELETEDIRECTORY Procedure	67-29
DELETEFILE Procedure	67-30
FEATURENAME Function	67-30
FLUSHSTATS Function	67-31
GETDEFAULTACL Procedure	67-31
GETDEFAULTASOF Procedure	67-31
GETDEFAULTCONTEXT Procedure	67-32
GETDEFAULTOWNER Procedure	67-32
GETDEFAULTPRINCIPAL Procedure	67-33
GETFEATURESBYMOUNT Function	67-33
GETFEATURESBYNAME Function	67-34
GETFEATURESBYPATH Function	67-34
GETPATH Procedures	67-34
GETPATHBYMOUNTID Function	67-37
GETPATHBYSTOREID Function	67-37
GETPATHNOWAIT Procedures	67-38
GETSTOREBYMOUNT Function	67-39
GETSTOREBYNAME Function	67-39
GETSTOREBYPATH Function	67-40
GETSTATS Procedure	67-40
GETTRACE Function	67-40
GETVERSION Function	67-41
ISPATHLOCKED Procedure	67-41
LIST Function	67-41
LISTALLPROPERTIES Function	67-42
LISTALLCONTENT Function	67-42
LISTMOUNTS Function	67-42
LISTSTORES Function	67-43
LOCKPATH Procedure	67-43
MOUNTSTORE Procedure	67-44
NORMALIZEPATH Functions	67-44
PROPANY Functions	67-45
PROPERTIESH2T Function	67-46
PROPERTIEST2H Function	67-46
PROPNUMBER Function	67-47
PROPRAW Function	67-47
PROPTIMESTAMP Function	67-47
PROPVARCHAR2 Function	67-48
PURGEALL Procedure	67-48
PURGEPATH Procedure	67-49
PUTPATH Procedures	67-49
REGISTERSTORE Procedure	67-51



	RESTOREALL Procedure	67-52
	RESTOREPATH Procedure	67-53
	SETDEFAULTACL Procedure	67-53
	SETDEFAULTASOF Procedure	67-54
	SETDEFAULTCONTEXT Procedure	67-54
	SETDEFAULTOWNER Procedure	67-55
	SETDEFAULTPRINCIPAL Procedure	67-55
	SETPATH Procedures	67-56
	SETSTATS Procedure	67-56
	SETTRACE Procedure	67-57
	SPACEUSAGE Procedure	67-57
	TRACE Procedure	67-58
	TRACEENABLED Function	67-59
	UNLOCKPATH Procedure	67-60
	UNMOUNTSTORE Procedure	67-60
	UNREGISTERSTORE Procedure	67-61
68	DBMS_DBFS_CONTENT_SPI	
	ODBMS_DBFS_CONTENT_SPI Overview	68-1
	DBMS_DBFS_CONTENT_SPI Security Model	68-2
	DBMS_DBFS_CONTENT_SPI Operational Notes	68-2
	Summary of DBMS_DBFS_CONTENT_SPI Subprograms	68-3
	CHECKACCESS Function	68-4
	CREATEDIRECTORY Procedure	68-5
	CREATEFILE Procedure	68-6
	CREATELINK Procedure	68-6
	CREATEREFERENCE Procedure	68-7
	DELETECONTENT Procedure	68-8
	DELETEDIRECTORY Procedure	68-8
	DELETEFILE Procedure	68-9
	GETFEATURES Function	68-10
	GETPATH Procedures	68-10
	GETPATHBYSTOREID Function	68-11
	GETPATHNOWAIT Procedure	68-12
	GETSTOREID Function	68-13
	GETVERSION Function	68-13
	ISPATHLOCKED Procedure	68-14
	LIST Function	68-14
	LOCKPATH Procedure	68-15
	PURGEALL Procedure	68-16

RENAMEPATH Procedures



67-51

	PURGEPATH Procedure	68-16
	PUTPATH Procedures	68-17
	RENAMEPATH Procedure	68-18
	RESTOREALL Procedure	68-19
	RESTOREPATH Procedure	68-19
	SEARCH Function	68-20
	SETPATH Procedure	68-20
	SPACEUSAGE Procedure	68-21
	UNLOCKPATH Procedure	68-22
69	DBMS_DBFS_HS	
	DBMS_DBFS_HS Overview	69-1
	DBMS_DBFS_HS Security Model	69-1
	DBMS_DBFS_HS Constants	69-1
	DBMS_DBFS_HS Operational Notes	69-6
	Summary of DBMS_DBFS_HS Subprograms	69-6
	CLEANUPUNUSEDBACKUPFILES Procedure	69-7
	CREATEBUCKET Procedure	69-7
	CREATESTORE Procedure	69-8
	DEREGSTORECOMMAND Function	69-9
	DROPSTORE Procedure	69-9
	FLUSHCACHE Procedure	69-10
	GETSTOREPROPERTY Function	69-10
	RECONFIGCACHE Procedure	69-11
	REGISTERSTORECOMMAND Procedure	69-12
	SENDCOMMAND Procedure	69-13
	SETSTOREPROPERTY Procedure	69-13
	STOREPUSH Procedure	69-17
70	DBMS_DBFS_SFS	
	DBMS_DBFS_SFS Overview	70-1
	DBMS_DBFS_SFS Security Model	70-1
	DBMS_DBFS_SFS Constants	70-1
	Summary of DBMS_DBFS_SFS Subprograms	70-2
	CREATEFILESYSTEM Procedure	70-3
	CREATESTORE Procedure	70-4
	DROPFILESYSTEM Procedures	70-5
	INITFS Procedure	70-6



71 DBMS_DDL

	DBMS_DDL Deprecated Subprograms	71-1
	DBMS_DDL Security Model	71-1
	DBMS_DDL Operational Notes	71-1
	Summary of DBMS_DDL Subprograms	71-1
	ALTER_COMPILE Procedure	71-2
	ALTER_TABLE_NOT_REFERENCEABLE Procedure	71-3
	ALTER_TABLE_REFERENCEABLE Procedure	71-4
	CREATE_WRAPPED Procedures	71-4
	IS_TRIGGER_FIRE_ONCE Function	71-6
	SET_TRIGGER_FIRING_PROPERTY Procedures	71-7
	WRAP Functions	71-8
72	DBMS_DEBUG	
	DBMS_DEBUG Overview	72-1
	DBMS_DEBUG Constants	72-2
	DBMS_DEBUG Variables	72-2
	DBMS_DEBUG Exceptions	72-2
	DBMS_DEBUG Operational Notes	72-4
	DBMS_DEBUG Data Structures	72-11
	BREAKPOINT_INFO Record Type	72-11
	PROGRAM_INFO Record Type	72-12
	RUNTIME_INFO Record Type	72-13
	BACKTRACE_TABLE Table Type	72-13
	BREAKPOINT_TABLE Table Type	72-13
	INDEX_TABLE Table Type	72-14
	VC2_TABLE Table Type	72-14
	Summary of DBMS_DEBUG Subprograms	72-14
	ATTACH_SESSION Procedure	72-15
	CONTINUE Function	72-16
	DEBUG_OFF Procedure	72-16
	DEBUG_ON Procedure	72-17
	DELETE_BREAKPOINT Function	72-17
	DELETE_OER_BREAKPOINT Function	72-18
	DETACH_SESSION Procedure	72-18
	DISABLE_BREAKPOINT Function	72-18
	ENABLE_BREAKPOINT Function	72-19
	EXECUTE Procedure	72-20
	GET_INDEXES Function	72-21
	GET_MORE_SOURCE Procedure	72-22



	72-23
GET_RUNTIME_INFO Function	72-24
GET_TIMEOUT_BEHAVIOUR Function	72-24
GET_VALUE Function	72-25
INITIALIZE Function	72-27
PING Procedure	72-28
PRINT_BACKTRACE Procedure	72-28
PRINT_INSTANTIATIONS Procedure	72-29
PROBE_VERSION Procedure	72-30
SELF_CHECK Procedure	72-30
SET_BREAKPOINT Function	72-31
SET_OER_BREAKPOINT Function	72-32
SET_TIMEOUT Function	72-32
SET_TIMEOUT_BEHAVIOUR Procedure	72-33
SET_VALUE Function	72-33
SHOW_BREAKPOINTS Procedures	72-35
SHOW_FRAME_SOURCE Procedure	72-35
SHOW_SOURCE Procedures	72-36
SYNCHRONIZE Function	72-37
TARGET_PROGRAM_RUNNING Procedure	72-38
n it to E 1 _ 1 to E 1 u iii _ 1 to E 1 u iii _ 1 to E 1 u ii _ 1 to E 1 u ii _ 1 to E 1 u ii _ 1 u ii _ 1 to E 1 u ii _	
Wilkezi _ Ne en viiii _ Ne miner i nesseulle	
73 DBMS_DEBUG_JDWP	
	73-1
73 DBMS_DEBUG_JDWP	
73 DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview	73-1
73 DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model	73-1 73-1
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms	73-1 73-1 73-2
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure	73-1 73-1 73-2 73-2
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function	73-1 73-2 73-2 73-2 73-4
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function	73-1 73-1 73-2 73-2 73-4 73-4
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure	73-1 73-2 73-2 73-4 73-4 73-4
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure GET_NLS_PARAMETER Function	73-1 73-1 73-2 73-2 73-4 73-4 73-4 73-5
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure GET_NLS_PARAMETER Function PROCESS_CONNECT_STRING Procedure SET_NLS_PARAMETER Procedure	73-1 73-1 73-2 73-2 73-4 73-4 73-5 73-5
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure GET_NLS_PARAMETER Function PROCESS_CONNECT_STRING Procedure SET_NLS_PARAMETER Procedure T4 DBMS_DEBUG_JDWP_CUSTOM	73-1 73-1 73-2 73-2 73-4 73-4 73-5 73-5
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure GET_NLS_PARAMETER Function PROCESS_CONNECT_STRING Procedure SET_NLS_PARAMETER Procedure THE CONTENT OF THE CONTENT	73-1 73-1 73-2 73-2 73-4 73-4 73-5 73-5
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure GET_NLS_PARAMETER Function PROCESS_CONNECT_STRING Procedure SET_NLS_PARAMETER Procedure SET_NLS_PARAMETER Procedure THE CONTROL OF THE CONTROL	73-1 73-2 73-2 73-4 73-4 73-5 73-5 73-6
DBMS_DEBUG_JDWP DBMS_DEBUG_JDWP Overview DBMS_DEBUG_JDWP Security Model Summary DBMS_DEBUG_JDWP Subprograms CONNECT_TCP Procedure CURRENT_SESSION_ID Function CURRENT_SESSION_SERIAL Function DISCONNECT Procedure GET_NLS_PARAMETER Function PROCESS_CONNECT_STRING Procedure SET_NLS_PARAMETER Procedure THE CONTENT OF THE CONTENT	73-1 73-2 73-2 73-4 73-4 73-5 73-5 73-6



75	DBMS_DESCRIBE	
	DBMS_DESCRIBE Overview	75-1
	DBMS_DESCRIBE Security Model	75-2
	DBMS_DESCRIBE Types	75-1
	DBMS_DESCRIBE Exceptions	75-1
	DBMS_DESCRIBE Examples	75-2
	Summary of DBMS_DESCRIBE Subprograms DESCRIBE_PROCEDURE Procedure	75- { 75- {
76	DBMS_DEVELOPER	
	DBMS_DEVELOPER Overview	76-1
	DBMS_DEVELOPER Security	76-2
	Summary of DBMS_DEVELOPER Subprograms	76-2
	GET_METADATA Function	76-2
	JSON Schema for Different Object and Sub-Object Types	76-22
77	DBMS_DG	
	Using DBMS_DG	77-1
	DBMS_DG Security Model	77-2
	Summary of the DBMS_DG Subprogram	77-2
	INITIATE_FS_FAILOVER Procedure	77-2
78	DBMS_DICTIONARY_CHECK	
	Overview of Oracle Database Dictionary Check	78-2
	Using DBMS_DICTIONARY_CHECK	78-2
	Summary of DBMS_DICTIONARY_CHECK Subprograms	78-8
79	DBMS_DIMENSION	
	DBMS_DIMENSION Security Model	79-1
	Summary of DBMS_DIMENSION Subprograms	79-2
	DESCRIBE_DIMENSION Procedure	79-2
	VALIDATE_DIMENSION Procedure	79-2
80	DBMS_DISTRIBUTED_TRUST_ADMIN	
	DBMS_DISTRIBUTED_TRUST_ADMIN Overview	80-1
	DBMS_DISTRIBUTED_TRUST_ADMIN Security Model	80-2
	DBMS_DISTRIBUTED_TRUST_ADMIN Examples	80-2



	Summary of DBMS_DISTRIBUTED_TRUST_ADMIN Subprograms	80-2
	ALLOW_ALL Procedure	80-3
	ALLOW_SERVER Procedure	80-3
	DENY_ALL Procedure	80-4
	DENY_SERVER Procedure	80-4
81	DBMS_DNFS	
	DBMS_DNFS Security Model	81-1
	Summary of DBMS_DNFS Subprograms	81-1
	CLONEDB_RENAMEFILE Procedure	81-1
	RESTORE_DATAFILE_PERMISSIONS Procedure	81-2
	UNMOUNTVOLUME Procedure	81-2
82	DBMS_DST	
	DBMS_DST Overview	82-1
	DBMS_DST Security Model	82-1
	DBMS_DST Views	82-2
	Summary of DBMS_DST Subprograms	82-2
	BEGIN_PREPARE Procedure	82-3
	BEGIN_UPGRADE Procedure	82-3
	CREATE_AFFECTED_TABLE Procedure	82-4
	CREATE_ERROR_TABLE Procedure	82-4
	CREATE_TRIGGER_TABLE Procedure	82-5
	END_PREPARE Procedure	82-6
	END_UPGRADE Procedure	82-6
	FIND_AFFECTED_TABLES Procedure	82-6
	UPGRADE_DATABASE Procedure	82-7
	UPGRADE_SCHEMA Procedure	82-8
	UPGRADE_TABLE Procedure	82-10
83	DBMS_EDITIONS_UTILITIES	
	DBMS_EDITIONS_UTILITIES Overview	83-1
	DBMS_EDITIONS_UTILITIES Security Model	83-1
	DBMS_EDITIONS_UTILITIES Exceptions	83-1
	Summary of DBMS_EDITIONS_UTILITIES Subprograms	83-1
	CLEAN_UNUSABLE_EDITIONS Procedure	83-2
	SET_EDITIONING_VIEWS_READ_ONLY Procedure	83-2
	SET_NULL_COLUMN_VALUES_TO_EXPR Procedure	83-3



84 DBMS_EPG

	DBMS_EPG Overview	84-1
	DBMS_EPG Security Model	84-1
	DBMS_EPG Exceptions	84-1
	DBMS_EPG Data Structures	84-2
	DBMS_EPG Subprogram Groups	84-2
	DBMS_EPG Configuration Subprograms	84-2
	DBMS_EPG Authorization Subprograms	84-3
	Summary of DBMS_EPG Subprograms	84-3
	AUTHORIZE_DAD Procedure	84-4
	CREATE_DAD Procedure	84-5
	DEAUTHORIZE_DAD Procedure	84-5
	DELETE_DAD_ATTRIBUTE Procedure	84-6
	DELETE_GLOBAL_ATTRIBUTE Procedure	84-6
	DROP_DAD Procedure	84-7
	GET_ALL_DAD_ATTRIBUTES Procedure	84-7
	GET_ALL_DAD_MAPPINGS Procedure	84-8
	GET_ALL_GLOBAL_ATTRIBUTES Procedure	84-9
	GET_DAD_ATTRIBUTE Function	84-9
	GET_DAD_LIST Procedure	84-10
	GET_GLOBAL_ATTRIBUTE Function	84-10
	MAP_DAD Procedure	84-11
	SET_DAD_ATTRIBUTE Procedure	84-12
	SET_GLOBAL_ATTRIBUTE Procedure	84-14
	UNMAP_DAD Procedure	84-15
85	DBMS_ERRLOG	
	DBMS_ERRLOG Security Model	85-1
	Summary of DBMS_ERRLOG Subprograms	85-1
	CREATE_ERROR_LOG Procedure	85-1
86	DBMS_FGA	
	DBMS_FGA Security Model	86-1
	DBMS_FGA Operational Notes	86-1
	Summary of DBMS_FGA Subprograms	86-1
	ADD_POLICY Procedure	86-2
	DISABLE_POLICY Procedure	86-5
	DROP_POLICY Procedure	86-6



PRIMA ELLE TRANSFER A	07.4
DBMS_FILE_TRANSFER Overview	87-1
DBMS_FILE_TRANSFER Security Model	87-1
DBMS_FILE_TRANSFER Operational Notes	87-1 87-2
Summary of DBMS_FILE_TRANSFER Subprograms COPY_FILE Procedure	87-2 87-2
GET_FILE Procedure	87-2
PUT_FILE Procedure	87-6
DBMS_FLASHBACK	
DBMS_FLASHBACK Overview	88-1
DBMS_FLASHBACK Security Model	88-1
DBMS_FLASHBACK Types	88-2
DBMS_FLASHBACK Exceptions	88-2
DBMS_FLASHBACK Operational Notes	88-2
DBMS_FLASHBACK Examples	88-3
Summary of DBMS_FLASHBACK Subprograms	88-5
DISABLE Procedure	88-5
ENABLE_AT_SYSTEM_CHANGE_NUMBER Procedure	88-6
ENABLE_AT_TIME Procedure	88-6
GET_SYSTEM_CHANGE_NUMBER Function	88-7
TRANSACTION_BACKOUT Procedures	88-7
DBMS_FLASHBACK_ARCHIVE	
DBMS_FLASHBACK_ARCHIVE Overview	89-2
DBMS_FLASHBACK_ARCHIVE Security Model	89-2
DBMS_FLASHBACK_ARCHIVE Constants	89-2
Summary of DBMS_FLASHBACK_ARCHIVE Subprograms	89-3
ADD_TABLE_TO_APPLICATION Procedure	89-4
CREATE_TEMP_HISTORY_TABLE Procedure	89-4
DISABLE_APPLICATION Procedure	89-5
DISABLE_ASOF_VALID_TIME Procedure	89-5
DISASSOCIATE_FBA Procedure	89-5
DROP_APPLICATION Procedure	89-6
ENABLE_APPLICATION Procedure	89-6
ENABLE_AT_VALID_TIME Procedure	89-6
EXTEND_MAPPINGS Procedure	89-7



	GET_CURRENT_LIFESPAN_DIGEST Function	89-7
	GET_SYS_CONTEXT Function	89-8
	IMPORT_HISTORY Procedure	89-9
	LOCK_DOWN_APPLICATION Procedure	89-10
	PURGE_CONTEXT Procedure	89-10
	REASSOCIATE_FBA Procedure	89-10
	REGISTER_APPLICATION Procedure	89-11
	REMOVE_TABLE_FROM_APPLICATION Procedure	89-12
	SET_CONTEXT_LEVEL Procedure	89-12
	VERIFY_BLOCKCHAIN_LIFESPAN Procedure	89-12
90	DBMS_FLASHBACK_ARCHIVE_MIGRATE	
	DBMS_FLASHBACK_ARCHIVE_MIGRATE Overview	90-1
	DBMS_FLASHBACK_ARCHIVE_MIGRATE Security Model	90-1
	DBMS_FLASHBACK_ARCHIVE_MIGRATE Operational Notes	90-2
	DBMS_FLASHBACK_ARCHIVE_MIGRATE Examples	90-3
	Summary of DBMS_FLASHBACK Subprograms	90-4
	EXPORT Procedure	90-5
	EXPORT_ANALYZE Procedure	90-5
	IMPORT Procedure	90-6
91	DBMS_FREQUENT_ITEMSET	
	Summary of DBMS_FREQUENT_ITEMSET Subprograms	91-1
	FI_HORIZONTAL Function	91-1
	FI_TRANSACTIONAL Function	91-3
92	DBMS_FS	
	DBMS_FS Overview	92-1
	DBMS_FS Security Model	92-1
	Summary of DBMS_FS Subprograms	92-1
	DESTROY_ORACLE_FS Procedure	92-2
	FS_EXISTS Procedure	92-3
	LIST_FILES Procedure	92-3
	MAKE_ORACLE_FS Procedure	92-4
	MOUNT_ORACLE_FS Procedure	92-5
	UNMOUNT ORACLE FS Procedure	92-9



93 DBMS_GOLDENGATE_ADM

	Using DBMS_GOLDENGATE_ADM	93-1
	DBMS_GOLDENGATE_ADM Overview	93-1
	DBMS_GOLDENGATE_ADM Security Model	93-2
	Summary of DBMS_GOLDENGATE_ADM Subprograms	93-2
	ADD_AUTO_CDR Procedure	93-3
	ADD_AUTO_CDR_COLUMN_GROUP Procedure	93-5
	ADD_AUTO_CDR_DELTA_RES Procedure	93-6
	ALTER_AUTO_CDR Procedure	93-7
	ALTER_AUTO_CDR_COLUMN_GROUP Procedure	93-10
	DELETE_PROCREP_EXCLUSION_OBJ Procedure	93-10
	GG_PROCEDURE_REPLICATION_ON Function	93-11
	INSERT_PROCREP_EXCLUSION_OBJ Procedure	93-11
	PURGE_TOMBSTONES Procedure	93-12
	REMOVE_AUTO_CDR Procedure	93-12
	REMOVE_AUTO_CDR_COLUMN_GROUP Procedure	93-13
	REMOVE_AUTO_CDR_DELTA_RES Procedure	93-13
94	DBMS_GOLDENGATE_AUTH	
	DBMS_GOLDENGATE_AUTH Overview	94-1
	DBMS_GOLDENGATE_AUTH Security Model	94-1
	Summary of DBMS_GOLDENGATE_AUTH Subprograms	94-1
	GRANT_ADMIN_PRIVILEGE Procedure	94-2
	REVOKE_ADMIN_PRIVILEGE Procedure	94-5
95	DBMS_HADOOP	
	DBMS_HADOOP Overview	95-1
	DBMS_HADOOP Security Model	95-1
	Summary of DBMS_HADOOP Subprograms	95-1
	CREATE_EXTDDL_FOR_HIVE Procedure	95-2
	CREATE_HYBRID_PARTNED_TABLE Procedure	95-3
	SYNCHRONIZE_PARTITIONS_FOR_HIVE Procedure	95-3
96	DBMS_HEAT_MAP	
	DBMS_HEAT_MAP Overview	96-1
	DBMS_HEAT_MAP Security Model	96-1
	Summary of DBMS_HEAT_MAP Subprograms	96-1
	BLOCK_HEAT_MAP Function	96-2
	EXTENT_HEAT_MAP Function	96-3



	OBJECT_HEAT_MAP Function	96-4
	SEGMENT_HEAT_MAP Procedure	96-5
	TABLESPACE_HEAT_MAP Function	96-6
97	DBMS_HIERARCHY	
	DBMS_HIERARCHY Overview	97-1
	DBMS_HIERARCHY Security Model	97-1
	Summary of DBMS_HIERARCHY Subprograms	97-2
	CREATE_VALIDATE_LOG_TABLE Procedure	97-3
	CREATE_VIEW_FOR_FACT_ROWS Procedure	97-4
	CREATE_VIEW_FOR_STAR_ROWS Procedure	97-5
	GET_MV_SQL_FOR_AV_CACHE Function	97-6
	GET_MV_SQL_FOR_STAR_CACHE Function	97-6
	UPGRADE_VALIDATE_LOG_TABLE Procedure	97-7
	VALIDATE_ANALYTIC_VIEW Function	97-7
	VALIDATE_CHECK_SUCCESS Function	97-9
	VALIDATE_HIERARCHY Function	97-10
98	DBMS_HM	
	DBMS_HM Security Model	98-1
	Summary of DBMS_HM Subprograms	98-1
	GET_RUN_REPORT Function	98-1
	RUN_CHECK Procedure	98-2
99	DBMS_HPROF	
	DBMS_HPROF Security Model	99-1
	Summary of DBMS_HPROF Subprograms	99-1
	ANALYZE Function	99-2
	CREATE_TABLES Procedure	99-4
	START_PROFILING Procedure	99-4
	STOP_PROFILING Procedure	99-5
100	DBMS_HS_PARALLEL	
	Using the DBMS_HS_PARALLEL Subprogram	100-1
	Summary of DBMS_HS_PARALLEL Subprograms	100-1
	CREATE_OR_REPLACE_VIEW Procedure	100-1
	CREATE_TABLE_TEMPLATE Procedure	100-3
	DROP_VIEW Procedure	100-3



101 DBMS_HS_PASSTHROUGH

	DBMS_HS_PASSTHROUGH Overview	101-1
	DBMS_HS_PASSTHROUGH Operational Notes	101-1
	Summary of DBMS_HS_PASSTHROUGH Subprograms	101-1
	BIND_INOUT_VARIABLE Procedure	101-2
	BIND_INOUT_VARIABLE_RAW Procedure	101-3
	BIND_OUT_VARIABLE Procedure	101-4
	BIND_OUT_VARIABLE_RAW Procedure	101-5
	BIND_VARIABLE Procedure	101-6
	BIND_VARIABLE_RAW Procedure	101-7
	CLOSE_CURSOR Procedure	101-8
	EXECUTE_IMMEDIATE Procedure	101-9
	EXECUTE_NON_QUERY Function	101-10
	FETCH_ROW Function	101-10
	GET_VALUE Procedure	101-11
	GET_VALUE_RAW Procedure	101-12
	OPEN_CURSOR Function	101-13
	PARSE Procedure	101-14
L02	DBMS_HYBRID_VECTOR	
	SEARCH	102-1
	GET_SQL	102-20
	SEARCHPIPELINE	102-20
L03	DBMS_ILM	
	DBMS_ILM Overview	103-1
	DBMS_ILM Security Model	103-2
	DBMS_ILM Constants	103-2
	DBMS_ILM Exceptions	103-2
	Summary of DBMS_ILM Subprograms	103-3
	ADD_TO_ILM Procedure	103-3
	ARCHIVESTATENAME Function	103-4
	EXECUTE_ILM Procedure	103-4
	EXECUTE_ILM_TASK Procedure	103-5
	PREVIEW_ILM Procedure	103-6
	REMOVE_FROM_ILM Procedure	103-6



104	DBMS_	_ILM_	_ADMIN

	DBMS_ILM_ADMIN Overview	104-1
	DBMS_ILM_ADMIN Security Model	104-1
	DBMS_ILM_ADMIN Constants	104-1
	Summary of DBMS_ILM_ADMIN Subprograms	104-4
	CLEAR_HEAT_MAP_ALL Procedure	104-5
	CLEAR_HEAT_MAP_TABLE Procedure	104-5
	CUSTOMIZE_ILM Procedure	104-6
	DISABLE_AUTO_OPTIMIZE Procedure	104-6
	DISABLE_ILM Procedure	104-6
	ENABLE_AUTO_OPTIMIZE Procedure	104-7
	ENABLE_ILM Procedure	104-7
	IGNORE_AUTO_OPTIMIZE_CRITERIA Procedure	104-7
	SET_HEAT_MAP_ALL Procedure	104-7
	SET_HEAT_MAP_START Procedure	104-8
	SET_HEAT_MAP_TABLE Procedure	104-8
105	DBMS_IMMUTABLE_TABLE	
	DBMS_IMMUTABLE_TABLE Overview	105-1
	DBMS_IMMUTABLE_TABLE Security Model	105-1
	Summary of DBMS_IMMUTABLE_TABLE Subprograms	105-1
	ADD_INTERVAL_PARTITIONING Procedure	105-2
	DELETE_EXPIRED_ROWS Procedure	105-2
106	DBMS_INMEMORY	
	DBMS_INMEMORY Overview	106-1
	DBMS_INMEMORY Security Model	106-2
	Summary of DBMS_INMEMORY Subprograms	106-2
	IME_DROP_EXPRESSIONS Procedure	106-2
	POPULATE Procedure	106-3
	REPOPULATE Procedure	106-4
	SEGMENT_DEALLOCATE_VERSIONS Procedure	106-4
107	DBMS_INMEMORY_ADMIN	
	DBMS_INMEMORY_ADMIN Overview	107-1
	DBMS_INMEMORY_ADMIN Security Model	107-3



	DBMS_INMEMORY_ADMIN Operational Notes	107-3
	Summary of DBMS_INMEMORY_ADMIN Subprograms	107-3
	AIM_GET_PARAMETER Procedure	107-4
	AIM_SET_PARAMETER Procedure	107-5
	FASTSTART_DISABLE Procedure	107-6
	FASTSTART_ENABLE Procedure	107-7
	FASTSTART_MIGRATE_STORAGE Procedure	107-9
	GET_FASTSTART_TABLESPACE Function	107-10
	IME_CAPTURE_EXPRESSIONS Procedure	107-11
	IME_CLOSE_CAPTURE_WINDOW Procedure	107-13
	IME_DROP_ALL_EXPRESSIONS Procedure	107-14
	IME_GET_CAPTURE_STATE Procedure	107-14
	IME_OPEN_CAPTURE_WINDOW Procedure	107-15
	IME_POPULATE_EXPRESSIONS Procedure	107-16
	POPULATE_WAIT Function	107-16
108	DBMS_INMEMORY_ADVISE	
	DBMS_INMEMORY_ADVISE Overview	108-1
	Summary of DBMS_INMEMORY_ADVISE Subprograms	108-1
	IS_INMEMORY_ELIGIBLE Procedure	108-1
109	DBMS_IOT	
	Summary of DBMS_IOT Subprograms	109-1
	BUILD_CHAIN_ROWS_TABLE Procedure	109-1
	BUILD_EXCEPTIONS_TABLE Procedure	109-2
110	DBMS_JAVA	
111	DBMS_JOB	
	DBMS_JOB Security Model	111-1
	DBMS_JOB Operational Notes	111-1
	Summary of DBMS_JOB Subprograms	111-3
	BROKEN Procedure	111-3
	CHANGE Procedure	111-4
	INSTANCE Procedure	111-5
	INTERVAL Procedure	111-6
	NEXT_DATE Procedure	111-6
	REMOVE Procedure	111-7



	RUN Procedure	111-7
	SUBMIT Procedure	111-8
	USER_EXPORT Procedures	111-10
	WHAT Procedure	111-10
112	DBMS_JSON_DUALITY	
	DBMS_JSON_DUALITY Overview	112-1
	DBMS_JSON_DUALITY Security	112-2
	Summary of DBMS_JSON_Duality Subprograms	112-2
	INFER_SCHEMA Function	112-4
	GENERATE_SCHEMA Function	112-7
	INFER_AND_GENERATE_SCHEMA Function	112-8
	VALIDATE_SCHEMA_REPORT Function	112-9
	IMPORT Procedure	112-10
	IMPORT_ALL Procedure	112-12
	VALIDATE_IMPORT_REPORT Function	112-14
	BEGIN_TRANSACTION Procedure	112-15
	COMMIT_TRANSACTION Procedure	112-16
	REGISTER Procedure	112-16
113	DBMS_JSON	
	DBMS_JSON Overview	113-1
	DBMS_JSON Security Model	113-1
	DBMS_JSON Constants	113-1
	Summary of DBMS_JSON Subprograms	113-4
	ADD_VIRTUAL_COLUMNS Procedure	113-4
	CREATE_VIEW Procedure	113-6
	CREATE_VIEW_ON_PATH Procedure	113-7
	DROP_VIRTUAL_COLUMNS Procedure	113-8
	GET_INDEX_DATAGUIDE Function	113-9
	GET_VIEW_SQL Function	113-10
	JSON_TYPE_CONVERTIBLE_CHECK Procedure	113-11
	RENAME_COLUMN Procedure	113-12
114	DBMS_JSON_SCHEMA	
	DBMS_JSON_SCHEMA Security Model	114-1
	DBMS_JSON_SCHEMA Constants	114-1
	Summary of DBMS_JSON_SCHEMA Subprograms	114-2
	DESCRIBE Function	114-2



	IS_SCHEMA_VALID FUNCTION	114-3
	IS_VALID Function	114-3
	IS_VALID Procedure	114-4
	VALIDATE_REPORT Function	114-5
115	DBMS_KAFKA	
	DBMS_KAFKA Overview	115-1
	DBMS_KAFKA LOADING Mode	115-3
	CREATE_LOAD_APP	115-3
	DROP_LOAD_APP	115-4
	EXECUTE_LOAD_APP	115-5
	DBMS_KAFKA Global Temporary Tables	115-7
	LOAD_TEMP_TABLE	115-7
	DBMS_KAFKA Streaming Mode	115-9
	CREATE_STREAMING_APP	115-9
	DROP_STREAMING_APP	115-11
	INIT_OFFSET	115-12
	INIT_OFFSET_TS (Milliseconds Since Epoch)	115-13
	INIT_OFFSET_TS (Timestamp with Separate Timezone Parameter)	115-14
	INIT_OFFSET_TS (Timestamp with Time Zone)	115-15
	UPDATE_OFFSET	115-17
	DBMS_KAFKA Seekable Mode	115-19
	CREATE_SEEKABLE_APP	115-19
	DROP_SEEKABLE_APP	115-20
	SEEK_OFFSET_TS (Timestamp with Separate Timezone Parameter)	115-21
	SEEK_OFFSET_TS (Timestamp in Milliseconds)	115-23
	SEEK_OFFSET_TS (Timestamp with Timezone)	115-25
	ADD_PARTITIONS	115-27
	DROP_ALL_APPS	115-29
	ENABLE_VIEW_QUERY	115-29
	SET_TRACING	115-31
	DBMS_KAFKA OPTIONS Passed to CREATE_xxx_APP	115-32
116	DBMS_KAFKA_ADM	
	DBMS_KAFKA_ADM Overview	116-1
	DBMS_KAFKA_ADM Security Model	116-1
	DBMS_KAFKA_ADM Constants	116-2
	Summary of DBMS_KAFKA_ADM Procedures	116-3
	CHECK_CLUSTER	116-4
	DEREGISTER_CLUSTER	116-5



	DISABLE_CLUSTER	116-6
	ENABLE_CLUSTER	116-7
	REGISTER_CLUSTER	116-8
	UPDATE_CLUSTER_INFO	116-11
117	DBMS_LDAP	
118	DBMS_LDAP_UTL	
110	DDMC LIDCACLIE	
119	DBMS_LIBCACHE	
	DBMS_LIBCACHE Overview	119-1
	DBMS_LIBCACHE Security Model	119-1
	Summary of DBMS_LIBCACHE Subprograms	119-1
	COMPILE_FROM_REMOTE Procedure	119-2
120	DBMS_LOB	
	DBMS_LOB Overview	120-1
	DBMS_LOB Security Model	120-1
	DBMS_LOB Constants	120-2
	DBMS_LOB Datatypes	120-4
	DBMS_LOB Operational Notes	120-4
	DBMS_LOB Rules and Limits	120-7
	DBMS_LOB Exceptions	120-10
	Summary of DBMS_LOB Subprograms	120-11
	APPEND Procedures	120-13
	CLOB2FILE Procedure	120-14
	CLOSE Procedure	120-15
	COMPARE Functions	120-16
	CONVERTTOBLOB Procedure	120-18
	CONVERTTOCLOB Procedure	120-20
	COPY Procedures	120-23
	COPY_DBFS_LINK Procedures	120-24
	COPY_FROM_DBFS_LINK	120-25
	CREATETEMPORARY Procedures	120-26
	DBFS_LINK_GENERATE_PATH Functions	120-27
	ERASE Procedures	120-27
	FILECLOSE Procedure	120-29



	FILECLOSEALL Procedure	120-30
	FILEEXISTS Function	120-30
	FILEGETNAME Procedure	120-31
	FILEISOPEN Function	120-32
	FILEOPEN Procedure	120-33
	FRAGMENT_DELETE Procedure	120-34
	FRAGMENT_INSERT Procedures	120-35
	FRAGMENT_MOVE Procedure	120-36
	FRAGMENT_REPLACE Procedures	120-37
	FREETEMPORARY Procedures	120-38
	GET_DBFS_LINK Functions	120-39
	GET_DBFS_LINK_STATE Procedures	120-40
	GET_LOB_DEDUPLICATION_RATIO Function	120-41
	GETCONTENTTYPE Functions	120-42
	GET_STORAGE_LIMIT Function	120-43
	GETCHUNKSIZE Functions	120-44
	GETLENGTH Functions	120-45
	GETOPTIONS Functions	120-46
	INSTR Functions	120-47
	ISOPEN Functions	120-49
	ISREMOTE Function	120-50
	ISSECUREFILE Function	120-50
	ISTEMPORARY Functions	120-51
	LOADBLOBFROMFILE Procedure	120-52
	LOADCLOBFROMFILE Procedure	120-53
	MOVE_TO_DBFS_LINK Procedures	120-56
	OPEN Procedures	120-57
	READ Procedures	120-58
	SET_DBFS_LINK Procedures	120-60
	SETCONTENTTYPE Procedure	120-61
	SETOPTIONS Procedures	120-62
	SUBSTR Functions	120-63
	TRIM Procedures	120-65
	WRITE Procedures	120-66
	WRITEAPPEND Procedures	120-68
121	DBMS_LOCK	
	DBMS_LOCK Overview	121-1
	DBMS_LOCK Security Model	121-1
	DBMS_LOCK Constants	121-2
	DBMS_LOCK. Rules and Limits	121-2



	DBMS_LOCK Operational Notes	121-3
	Summary of DBMS_LOCK Subprograms	121-3
	ALLOCATE_UNIQUE Procedure	121-3
	ALLOCATE_UNIQUE_AUTONOMOUS Procedure	121-5
	CONVERT Function	121-6
	RELEASE Function	121-7
	REQUEST Function	121-8
122	DBMS_LOGMNR	
	DBMS_LOGMNR Overview	122-1
	DBMS_LOGMNR Security Model	122-2
	DBMS_LOGMNR Constants	122-2
	DBMS_LOGMNR Views	122-4
	DBMS_LOGMNR Operational Notes	122-4
	Summary of DBMS_LOGMNR Subprograms	122-4
	ADD_LOGFILE Procedure	122-5
	COLUMN_PRESENT Function	122-7
	END_LOGMNR Procedure	122-8
	MINE_VALUE Function	122-9
	REMOVE_LOGFILE Procedure	122-10
	START_LOGMNR Procedure	122-11
123	DBMS_LOGSTDBY	
	DBMS_LOGSTDBY Overview	123-1
	DBMS_LOGSTDBY Security Model	123-1
	DBMS_LOGSTDBY Constants	123-2
	Summary of DBMS_LOGSTDBY Subprograms	123-2
	APPLY_SET Procedure	123-4
	APPLY_UNSET Procedure	123-7
	BUILD Procedure	123-7
	INSTANTIATE_TABLE Procedure	123-8
	IS_APPLY_SERVER Function	123-10
	MAP_PRIMARY_SCN Function	123-10
	PREPARE_FOR_NEW_PRIMARY Procedure	123-11
	PURGE_SESSION Procedure	123-12
	REBUILD Procedure	123-13
	SET_TABLESPACE Procedure	123-13
	SKIP Procedure	123-14
	SKIP_ERROR Procedure	123-23
	SKIP_TRANSACTION Procedure	123-26



	UNSKIP Procedure UNSKIP_ERROR Procedure UNSKIP_TRANSACTION Procedure	123-28 123-29 123-30
124	DBMS_LOGMNR_D	
	DBMS_LOGMNR_D Overview	124-1
	DBMS_LOGMNR_D Security Model	124-2
	Summary of DBMS_LOGMNR_D Subprograms	124-2
	BUILD Procedure	124-2
	SET_TABLESPACE Procedure	124-5
125	DBMS_LOGSTDBY_CONTEXT	
	DBMS_LOGSTDBY_CONTEXT Overview	125-1
	DBMS_LOGSTDBY_CONTEXT Security Model	125-2
	Summary of DBMS_LOGSTDBY_CONTEXT Subprograms	125-2
	CLEAR_ALL_CONTEXT Procedure	125-3
	CLEAR_CONTEXT Procedure	125-3
	GET_CONTEXT Procedure	125-3
	SET_CONTEXT Procedure	125-4
126	DBMS_MEMOPTIMIZE	
	DBMS_MEMOPTIMIZE Overview	126-1
	Summary of DBMS_MEMOPTIMIZE Subprograms	126-1
	DROP_OBJECT Procedure	126-2
	GET_APPLY_HWM_SEQID Function	126-3
	GET_WRITE_HWM_SEQID Function	126-3
	POPULATE Procedure	126-3
	WRITE_END Procedure	126-4
127	DBMS_MEMOPTIMIZE_ADMIN	
	DBMS_MEMOPTIMIZE_ADMIN Overview	127-1
	Summary of DBMS_MEMOPTIMIZE_ADMIN Subprograms	127-1
	WRITES_FLUSH Procedure	127-2
128	DBMS_METADATA	
	DBMS_METADATA Overview	128-1
	DBMS_METADATA Security Model	128-2
	Rules and Limits	128-3



	DBMS_METADATA Data Structures - Object and Table Types	128-3
	DBMS_METADATA Subprogram Groupings	128-4
	DBMS_METADATA Subprograms for Retrieving Multiple Objects From the Database	128-4
	DBMS_METADATA Subprograms for Submitting XML to the Database	128-5
	Summary of All DBMS_METADATA Subprograms	128-5
	ADD_TRANSFORM Function	128-6
	CLOSE Procedure	128-10
	CONVERT Functions and Procedures	128-10
	FETCH_xxx Functions and Procedures	128-12
	GET_xxx Functions	128-15
	GET_QUERY Function	128-19
	OPEN Function	128-20
	OPENW Function	128-27
	PUT Function	128-28
	SET_COUNT Procedure	128-29
	SET_FILTER Procedure	128-30
	SET_PARSE_ITEM Procedure	128-41
	SET_TRANSFORM_PARAM and SET_REMAP_PARAM Procedures	128-44
129	DBMS_METADATA_DIFF	
	DBMS_METADATA_DIFF_Overview	129-1
	DBMS_METADATA_DIFF Security Model	129-1
	DBMS_METADATA_DIFF — Browsing APIs for Fetching and Comparing Objects	129-2
	Summary of DBMS_METADATA_DIFF Subprograms	129-3
	OPENC Function	129-4
	ADD_DOCUMENT Procedure	129-4
	FETCH_CLOB Functions and Procedures	129-5
	CLOSE Procedure	129-6
130	DBMS_MGD_ID_UTL	
	DBMS_MGD_ID_UTL Security Model	130-1
	DBMS_MGD_ID_UTL Constants	130-2
	DBMS_MGD_ID_UTL Exceptions	130-2
	Summary of DBMS_MGD_ID_UTL Subprograms	130-3
	ADD_SCHEME Procedure	130-4
	CREATE_CATEGORY Function	130-7
	EPC_TO_ORACLE_SCHEME Function	130-8
	GET_CATEGORY_ID Function	130-11
	GET_COMPONENTS Function	130-12
	GET_ENCODINGS Function	130-13



	GET_JAVA_LOGGING_LEVEL FUNCTION	130-13
	GET_PLSQL_LOGGING_LEVEL Function	130-14
	GET_SCHEME_NAMES Function	130-15
	GET_TDT_XML Function	130-15
	GET_VALIDATOR Function	130-17
	REFRESH_CATEGORY Function	130-20
	REMOVE_CATEGORY Procedure	130-21
	REMOVE_PROXY Procedure	130-22
	REMOVE_SCHEME Procedure	130-22
	SET_JAVA_LOGGING_LEVEL Procedure	130-23
	SET_PLSQL_LOGGING_LEVEL Procedure	130-23
	SET_PROXY Procedure	130-24
	VALIDATE_SCHEME Function	130-25
131	DBMS_MGWADM	
	DBMS_MGWADM Security Model	131-1
	DBMS_MGWADM Deprecated Subprograms	131-1
	DBMS_MGWADM Constants	131-2
	DBMS_MGWADM Data Structures	131-5
	DBMS_MGWADM SYS.MGW_MQSERIES_PROPERTIES Object Type	131-5
	DBMS_MGWADM SYS.MGW_PROPERTIES Object Type	131-7
	DBMS_MGWADM SYS.MGW_PROPERTY Object Type	131-8
	SYS.MGW_TIBRV_PROPERTIES Object Type	131-9
	Summary of DBMS_MGWADM Subprograms	131-10
	ADD_SUBSCRIBER Procedure	131-12
	ALTER_AGENT Procedures	131-15
	ALTER_JOB Procedure	131-16
	ALTER_MSGSYSTEM_LINK Procedure for TIB/Rendezvous	131-18
	ALTER_MSGSYSTEM_LINK Procedure for WebSphere MQ	131-19
	ALTER_PROPAGATION_SCHEDULE Procedure	131-20
	ALTER_SUBSCRIBER Procedure	131-21
	CLEANUP_GATEWAY Procedures	131-23
	CREATE_AGENT Procedure	131-25
	CREATE_JOB Procedure	131-27
	CREATE_MSGSYSTEM_LINK Procedures for TIB/Rendezvous	131-30
	CREATE_MSGSYSTEM_LINK Procedures for WebSphere MQ	131-31
	DB_CONNECT_INFO Procedure	131-32
	DISABLE_JOB Procedure	131-32
	DISABLE_PROPAGATION_SCHEDULE Procedure	131-33
	ENABLE_JOB Procedure	131-33
	ENABLE_PROPAGATION_SCHEDULE Procedure	131-34



	REGISTER_FOREIGN_QUEUE Procedure	131-34
	REMOVE_AGENT Procedure	131-35
	REMOVE_JOB Procedure	131-36
	REMOVE_MSGSYSTEM_LINK Procedure	131-36
	REMOVE_OPTION Procedure	131-37
	REMOVE_SUBSCRIBER Procedure	131-38
	RESET_JOB Procedure	131-39
	RESET_SUBSCRIBER Procedure	131-40
	SCHEDULE_PROPAGATION Procedure	131-40
	SET_LOG_LEVEL Procedures	131-42
	SET_OPTION Procedure	131-42
	SHUTDOWN Procedures	131-44
	STARTUP Procedures	131-44
	UNREGISTER_FOREIGN_QUEUE Procedure	131-45
	UNSCHEDULE_PROPAGATION Procedure	131-46
132	DBMS_MGWMSG	
	DBMS_MGWMSG Security Model	132-1
	DBMS_MGWMSG Constants	132-1
	DBMS_MGWMSG Types	132-3
	DBMS_MGWMSG SYS.MGW_NAME_VALUE_T Type	132-3
	DBMS_MGWMSG SYS.MGW_NAME_TYPE_ARRAY_T Type	132-6
	DBMS_MGWMSG SYS.MGW_TEXT_VALUE_T Type	132-6
	DBMS_MGWMSG SYS.MGW_RAW_VALUE_T Type	132-6
	DBMS_MGWMSG SYS.MGW_BASIC_MSG_T Type	132-7
	DBMS_MGWMSG SYS.MGW_NUMBER_ARRAY_T Type	132-8
	DBMS_MGWMSG SYS.MGW_TIBRV_FIELD_T Type	132-8
	DBMS_MGWMSG SYS.MGW_TIBRV_MSG_T Type	132-9
	Summary of DBMS_MGWMSG Subprograms	132-17
	LCR_TO_XML Function	132-18
	NVARRAY_ADD Procedure	132-19
	NVARRAY_FIND_NAME Function	132-19
	NVARRAY_FIND_NAME_TYPE Function	132-20
	NVARRAY_GET Function	132-21
	NVARRAY_GET_BOOLEAN Function	132-21
	NVARRAY_GET_BYTE Function	132-22
	NVARRAY_GET_DATE Function	132-22
	NVARRAY_GET_DOUBLE Function	132-23
	NVARRAY_GET_FLOAT Function	132-23
	NVARRAY_GET_INTEGER Function	132-24
	NVARRAY_GET_LONG Function	132-24



131-34

	NVARRAY_GET_RAW Function	132-25
	NVARRAY_GET_SHORT Function	132-25
	NVARRAY_GET_TEXT Function	132-26
	XML_TO_LCR Function	132-27
133	DBMS_MLE	
	DBMS_MLE Overview	133-1
	DBMS_MLE Security Model	133-2
	Summary of DBMS_MLE Subprograms	133-2
	CREATE_CONTEXT Function	133-3
	DISABLE_CTX_STDERR Procedure	133-4
	DISABLE_CTX_STDOUT Procedure	133-5
	DISABLE_DEBUGGING Procedure	133-5
	DISABLE_ICS_STDERR Procedure	133-6
	DISABLE_ICS_STDOUT Procedure	133-6
	DISABLE_STDERR Procedure	133-7
	DISABLE_STDOUT Procedure	133-7
	DROP_CONTEXT Procedure	133-8
	ENABLE_DEBUGGING Procedure	133-9
	EVAL Procedure	133-9
	EXPORT_TO_MLE Procedure	133-11
	GET_AVAILABLE_LANGUAGES Function	133-13
	GET_CTX_ERROR_STACK Function	133-13
	GET_ERROR_STACK Function	133-14
	IMPORT_FROM_MLE Procedure	133-14
	PARSE_DEBUG_OUTPUT Function	133-16
	SET_CTX_STDERR Procedure	133-17
	SET_CTX_STDERR_TO_DBMS_OUTPUT Procedure	133-18
	SET_CTX_STDOUT Procedure	133-18
	SET_CTX_STDOUT_TO_DBMS_OUTPUT Procedure	133-19
	SET_ICS_STDERR Procedure	133-19
	SET_ICS_STDERR_TO_DBMS_OUTPUT Procedure	133-20
	SET_ICS_STDOUT Procedure	133-21
	SET_ICS_STDOUT_TO_DBMS_OUTPUT Procedure	133-21
	SET_STDERR Procedure	133-22
	SET_STDERR_TO_DBMS_OUTPUT Procedure	133-23
	SET_STDOUT Procedure	133-23
	SET_STDOUT_TO_DBMS_OUTPUT Procedure	133-24



134 DBMS_MONITOR

	Summary of DBMS_MONITOR Subprograms	134-1
	CLIENT_ID_STAT_DISABLE Procedure	134-2
	CLIENT_ID_STAT_ENABLE Procedure	134-2
	CLIENT_ID_TRACE_DISABLE Procedure	134-3
	CLIENT_ID_TRACE_ENABLE Procedure	134-3
	DATABASE_TRACE_DISABLE Procedure	134-4
	DATABASE_TRACE_ENABLE Procedure	134-4
	SERV_MOD_ACT_STAT_DISABLE Procedure	134-5
	SERV_MOD_ACT_STAT_ENABLE Procedure	134-5
	SERV_MOD_ACT_TRACE_DISABLE Procedure	134-7
	SERV_MOD_ACT_TRACE_ENABLE Procedure	134-8
	SESSION_TRACE_DISABLE Procedure	134-9
	SESSION_TRACE_ENABLE Procedure	134-10
135	DBMS_MVIEW	
	DBMS_MVIEW Operational Notes	135-1
	DBMS_MVIEW Security Model	135-1
	DBMS_MVIEW Rules and Limits	135-1
	Summary of DBMS_MVIEW Subprograms	135-2
	BEGIN_TABLE_REORGANIZATION Procedure	135-2
	END_TABLE_REORGANIZATION Procedure	135-3
	ESTIMATE_MVIEW_SIZE Procedure	135-3
	EXPLAIN_MVIEW Procedure	135-4
	EXPLAIN_REWRITE Procedure	135-5
	I_AM_A_REFRESH Function	135-6
	PMARKER Function	135-6
	PURGE_DIRECT_LOAD_LOG Procedure	135-7
	PURGE_LOG Procedure	135-7
	PURGE_MVIEW_FROM_LOG Procedure	135-8
	REFRESH Procedures	135-9
	REFRESH_ALL_MVIEWS Procedure	135-11
	REFRESH_DEPENDENT Procedures	135-13
	REGISTER_MVIEW Procedure	135-15
	UNREGISTER_MVIEW Procedure	135-16
136	DBMS_MVIEW_STATS	
	DBMS_MVIEW_STATS Overview	136-1
	DBMS_MVIEW_STATS Security Model	136-1



	Summary of DBMS_MVIEW_STATS Supprograms	136-1
	PURGE_REFRESH_STATS Procedure	136-2
	SET_MVREF_STATS_PARAMS Procedure	136-3
	SET_SYSTEM_DEFAULT Procedure	136-4
137	DBMS_NETWORK_ACL_ADMIN	
	DBMS_NETWORK_ACL_ADMIN Overview	137-1
	DBMS_NETWORK_ACL_ADMIN Deprecated Subprograms	137-1
	DBMS_NETWORK_ACL_ADMIN Security Model	137-2
	DBMS_NETWORK_ACL_ADMIN Constants	137-2
	DBMS_NETWORK_ACL_ADMIN Exceptions	137-2
	DBMS_NETWORK_ACL_ADMIN Examples	137-3
	Summary of DBMS_NETWORK_ACL_ADMIN Subprograms	137-4
	ADD_PRIVILEGE Procedure	137-5
	APPEND_HOST_ACE Procedure	137-7
	APPEND_HOST_ACL Procedure	137-8
	APPEND_WALLET_ACE Procedure	137-9
	APPEND_WALLET_ACL Procedure	137-10
	ASSIGN_ACL Procedure	137-10
	ASSIGN_WALLET_ACL Procedure	137-12
	CHECK_PRIVILEGE Function	137-13
	CHECK_PRIVILEGE_ACLID Function	137-14
	CREATE_ACL Procedure	137-14
	DELETE_PRIVILEGE Procedure	137-16
	DROP_ACL Procedure	137-16
	REMOVE_HOST_ACE Procedure	137-17
	REMOVE_WALLET_ACE Procedure	137-18
	SET_HOST_ACL Procedure	137-18
	SET_WALLET_ACL Procedure	137-19
	UNASSIGN_ACL Procedure	137-19
	UNASSIGN_WALLET_ACL Procedure	137-20
138	DBMS_NETWORK_ACL_UTILITY	
	DBMS_NETWORK_ACL_UTILITY Security Model	138-1
	DBMS_NETWORK_ACL_UTILITY Examples	138-1
	Summary of DBMS_NETWORK_ACL_UTILITY Subprograms	138-2
	CONTAINS_HOST Function	138-3
	DOMAIN_LEVEL Function	138-4
	DOMAINS Function	138-4



	EQUALS_HOST Function	138-5
139	DBMS_ODCI	
	Summary of DBMS_ODCI Subprograms	139-1
	ESTIMATE_CPU_UNITS Function	139-1
140	DBMS_OPTIM_BUNDLE	
	DBMS_OPTIM_BUNDLE Security Model	140-1
	Summary of DBMS_OPTIM_BUNDLE Subprograms	140-1
	ENABLE_OPTIM_FIXES Procedure	140-1
	GETBUGSFORBUNDLE Procedure	140-3
	LISTBUNDLESWITHFCFIXES Procedure	140-3
	SET_FIX_CONTROLS Procedure	140-4
141	DBMS_OUTLN	
	DBMS_OUTLN Overview	141-1
	DBMS_OUTLN Security Model	141-2
	Summary of DBMS_OUTLN Subprograms	141-2
	CLEAR_USED Procedure	141-2
	CREATE_OUTLINE Procedure	141-3
	DROP_BY_CAT Procedure	141-3
	DROP_UNUSED Procedure	141-4
	EXACT_TEXT_SIGNATURES Procedure	141-4
	UPDATE_BY_CAT Procedure	141-4
	UPDATE_SIGNATURES Procedure	141-4
142	DBMS_OUTPUT	
	DBMS_OUTPUT Overview	142-1
	DBMS_OUTPUT Security Model	142-1
	DBMS_OUTPUT Operational Notes	142-1
	DBMS_OUTPUT Exceptions	142-2
	DBMS_OUTPUT Rules and Limits	142-2
	DBMS_OUTPUT Examples	142-2
	DBMS_OUTPUT Data Structures	142-5
	CHARARR Table Type	142-5
	DBMS_OUTPUT DBMSOUTPUT_LINESARRAY Object Type	142-5



Summary of DBMS_OUTPUT Subprograms

DISABLE Procedure

142-6

142-6

	ENABLE Procedure	142-6
	GET_LINE Procedure	142-7
	GET_LINES Procedure	142-8
	NEW_LINE Procedure	142-8
	PUT Procedure	142-9
	PUT_LINE Procedure	142-10
143	DBMS_PARALLEL_EXECUTE	
	DBMS_PARALLEL_EXECUTE Overview	143-1
	DBMS_PARALLEL_EXECUTE Security Model	143-1
	DBMS_PARALLEL_EXECUTE Constants	143-2
	DBMS_PARALLEL_EXECUTE Views	143-3
	DBMS_PARALLEL_EXECUTE Exceptions	143-3
	DBMS_PARALLEL_EXECUTE Examples	143-3
	Summary of DBMS_PARALLEL_EXECUTE Subprograms	143-6
	ADM_DROP_CHUNKS Procedure	143-7
	ADM_DROP_TASK Procedure	143-7
	ADM_TASK_STATUS Function	143-8
	ADM_STOP_TASK Procedure	143-8
	CREATE_TASK Procedure	143-8
	CREATE_CHUNKS_BY_NUMBER_COL Procedure	143-9
	CREATE_CHUNKS_BY_ROWID Procedure	143-9
	CREATE_CHUNKS_BY_SQL Procedure	143-10
	DROP_TASK Procedure	143-11
	DROP_CHUNKS Procedure	143-11
	GENERATE_TASK_NAME Function	143-11
	GET_NUMBER_COL_CHUNK Procedure	143-12
	GET_ROWID_CHUNK Procedure	143-12
	PURGE_PROCESSED_CHUNKS Procedure	143-13
	RESUME_TASK Procedures	143-14
	RUN_TASK Procedure	143-16
	SET_CHUNK_STATUS Procedure	143-17
	STOP_TASK Procedure	143-18
	TASK_STATUS Procedure	143-18
144	DBMS_PART	
	DBMS_PART Security Model	144-1
	DBMS_PART Operational Notes	144-1
	Summary of DBMS_PART Subprograms	144-1
	CLEANUP_GIDX Procedure	144-2



	CLEANUP_GIDX_JOB Procedure	144-2
	CLEANUP_ONLINE_OP Procedure	144-3
145	DBMS_PCLXUTIL	
	DBMS_PCLXUTIL Overview	145-1
	DBMS_PCLXUTIL Security Model	145-2
	DBMS_PCLXUTIL Operational Notes	145-2
	DBMS_PCLXUTIL Rules and Limits	145-2
	Summary of DBMS_PCLXUTIL Subprograms	145-3
	BUILD_PART_INDEX Procedure	145-3
146	DBMS_PDB	
	DBMS_PDB Overview	146-1
	DBMS_PDB Security Model	146-2
	Summary of DBMS_PDB Subprograms	146-2
	CHECK_PLUG_COMPATIBILITY Function	146-3
	DESCRIBE Procedure	146-4
	EXPORTRMANBACKUP Procedure	146-4
	RECOVER Procedure	146-5
	REMOVE_LINK Procedure	146-6
	SET_DATA_LINKED Procedure	146-6
	SET_EXT_DATA_LINKED Procedure	146-7
	SET_METADATA_LINKED Procedure	146-8
	SET_PROFILE_EXPLICIT Procedure	146-9
	SET_ROLE_EXPLICIT Procedure	146-9
	SET_USER_EXPLICIT Procedure	146-10
147	DBMS_PDB_ALTER_SHARING	
	DBMS_PDB_ALTER_SHARING Overview	147-1
	DBMS_PDB_ALTER_SHARING Security Model	147-2
	Summary of DBMS_PDB_ALTER_SHARING Subprograms	147-2
	REMOVE_LINK Procedure	147-3
	SET_DATA_LINKED Procedure	147-3
	SET_EXT_DATA_LINKED Procedure	147-4
	SET_METADATA_LINKED Procedure	147-5
	SET_PROFILE_EXPLICIT Procedure	147-6
	SET_ROLE_EXPLICIT Procedure	147-6
	SET_USER_EXPLICIT Procedure	147-7



148 DBMS_PERF

	DBMS_PERF Overview	148-1
	DBMS_PERF Security Model	148-1
	Summary of DBMS_PERF Subprograms	148-1
	REPORT_PERFHUB Function	148-2
	REPORT_SESSION Function	148-3
	REPORT_SQL Function	148-5
149	DBMS_PIPE	
	DBMS_PIPE Overview	149-1
	DBMS_PIPE Security Model	149-2
	DBMS_PIPE Constants	149-2
	DBMS_PIPE Operational Notes	149-2
	DBMS_PIPE Exceptions	149-5
	DBMS_PIPE Examples	149-5
	Summary of DBMS_PIPE Subprograms	149-14
	CREATE_PIPE Function	149-15
	GET_CREDENTIAL_NAME Function	149-17
	GET_LOCATION_URI Function	149-17
	NEXT_ITEM_TYPE Function	149-17
	PACK_MESSAGE Procedures	149-18
	PURGE Procedure	149-19
	RECEIVE_MESSAGE Function	149-20
	RESET_BUFFER Procedure	149-24
	REMOVE_PIPE Function	149-24
	SEND_MESSAGE Function	149-25
	SET_CREDENTIAL_NAME Procedure	149-28
	SET_LOCATION_URI Procedure	149-28
	UNIQUE_SESSION_NAME Function	149-29
	UNPACK_MESSAGE Procedures	149-29
150	DBMS_PLSQL_CODE_COVERAGE	
	DBMS_PLSQL_CODE_COVERAGE Overview	150-1
	DBMS_PLSQL_CODE_COVERAGE Security Model	150-1
	DBMS_PLSQL_CODE_COVERAGE Constants	150-2
	DBMS_PLSQL_CODE_COVERAGE Data Structures	150-2
	MAP_REC Record Type	150-2
	T_MAP_REC Table Type	150-3
	Summary of DBMS_PLSQL_CODE_COVERAGE Subprograms	150-3



	CREATE_COVERAGE_TABLES Procedure	150-3
	GET_BLOCK_MAP Function	150-4
	START_COVERAGE Function	150-4
	STOP_COVERAGE Procedure	150-5
151	DBMS_PREDICTIVE_ANALYTICS	
	DBMS_PREDICTIVE_ANALYTICS Overview	151-1
	DBMS_PREDICTIVE_ANALYTICS Security Model	151-1
	Summary of DBMS_PREDICTIVE_ANALYTICS Subprograms	151-2
	EXPLAIN Procedure	151-2
	PREDICT Procedure	151-4
	PROFILE Procedure	151-6
152	DBMS_PREPROCESSOR	
	DBMS_PREPROCESSOR Overview	152-1
	DBMS_PREPROCESSOR Operating Notes	152-1
	DBMS_PREPROCESSOR Data Structures	152-2
	DBMS_PREPROCESSOR SOURCE_LINES_T Table Type	152-2
	Summary of DBMS_PREPROCESSOR Subprograms	152-2
	GET_POST_PROCESSED_SOURCE Functions	152-3
	PRINT_POST_PROCESSED_SOURCE Procedures	152-4
153	DBMS_PRIVILEGE_CAPTURE	
	DBMS_PRIVILEGE_CAPTURE Overview	153-1
	DBMS_PRIVILEGE_CAPTURE Security Model	153-1
	DBMS_PRIVILEGE_CAPTURE Constants	153-1
	DBMS_PRIVILEGE_CAPTURE Examples	153-2
	Summary of DBMS_PRIVILEGE_CAPTURE Subprograms	153-3
	CAPTURE_DEPENDENCY_PRIVS Procedure	153-3
	CREATE_CAPTURE Procedure	153-3
	DELETE_RUN Procedure	153-5
	DISABLE_CAPTURE Procedure	153-5
	DROP_CAPTURE Procedure	153-6
	ENABLE_CAPTURE Procedure	153-6
	GENERATE_RESULT Procedure	153-7
154	DBMS_PROCESS	
	DBMS_PROCESS Overview	154-1



	DBMS_PROCESS Security Model	154-1
	Summary of DBMS_PROCESS Subprograms	154-2
	CONFIGURE_POOL Procedure	154-2
	START_POOL Procedure	154-3
	STOP_POOL Procedure	154-4
155	DBMS_PROFILER	
	DBMS_PROFILER Overview	155-1
	DBMS_PROFILER Security Model	155-3
	DBMS_PROFILER Operational Notes	155-3
	DBMS_PROFILER Exceptions	155-5
	Summary of DBMS_PROFILER Subprograms	155-6
	FLUSH_DATA Function and Procedure	155-6
	GET_VERSION Procedure	155-6
	INTERNAL_VERSION_CHECK Function	155-7
	PAUSE_PROFILER Function and Procedure	155-7
	RESUME_PROFILER Function and Procedure	155-7
	START_PROFILER Functions and Procedures	155-7
	STOP_PROFILER Function and Procedure	155-8
156	DBMS_PROPAGATION_ADM	
	DBMS_PROPAGATION_ADM Overview	156-1
	DBMS_PROPAGATION_ADM Security Model	156-1
	Summary of DBMS_PROPAGATION_ADM Subprograms	156-1
	ALTER_PROPAGATION Procedure	156-2
	CREATE_PROPAGATION Procedure	156-3
	DROP_PROPAGATION Procedure	156-6
	START_PROPAGATION Procedure	156-7
	STOP_PROPAGATION Procedure	156-7
157	DBMS_QOPATCH	
	DBMS_QOPATCH Overview	157-1
	DBMS_QOPATCH Security Model	157-1
	DBMS_QOPATCH Operational Notes	157-1
	DBMS_QOPATCH Exceptions	157-1
	Summary of DBMS_QOPATCH Subprograms	157-2
	CHECK_PATCH_INSTALLED Function	157-3
	GET_OPATCH_BUGS Function	157-3
	GET_OPATCH_COUNT Function	157-4



	GET_OPATCH_DATA FUNCTION	157-4
	GET_OPATCH_FILES Function	157-4
	GET_OPATCH_INSTALL_INFO Function	157-5
	GET_OPATCH_LIST Function	157-5
	GET_OPATCH_LSINVENTORY	157-5
	GET_OPATCH_OLAYS Function	157-5
	GET_OPATCH_PREQS Function	157-6
	GET_OPATCH_XSLT	157-6
	GET_PATCH_DETAILS Function	157-6
	GET_SQLPATCH_STATUS Procedure	157-7
	IS_PATCH_INSTALLED Function	157-7
	OPATCH_COMPARE_CURRENT Function	157-7
	OPATCH_COMPARE_NODES Function	157-8
	SET_CURRENT_OPINST Procedure	157-8
158	DBMS_RANDOM	
	DBMS_RANDOM Deprecated Subprograms	158-1
	DBMS_RANDOM Security Model	158-1
	DBMS_RANDOM Operational Notes	158-1
	Summary of DBMS_RANDOM Subprograms	158-2
	INITIALIZE Procedure	158-2
	NORMAL Function	158-3
	RANDOM Function	158-3
	SEED Procedures	158-4
	STRING Function	158-4
	TERMINATE Procedure	158-5
	VALUE Functions	158-5
159	DBMS_REDACT	
	DBMS_REDACT Overview	159-1
	DBMS_REDACT Security Model	159-1
	DBMS_REDACT Constants	159-2
	DBMS_REDACT Operating Procedures	159-2
	Summary of DBMS_REDACT Subprograms	159-7
	ADD_POLICY Procedure	159-7
	ALTER_POLICY Procedure	159-13
	APPLY_POLICY_EXPR_TO_COL Procedure	159-20
	CREATE_POLICY_EXPRESSION Procedure	159-21
	DISABLE_POLICY Procedure	159-22
	DROP_POLICY Procedure	159-23



	DROP_POLICY_EXPRESSION Procedure	159-23
	ENABLE_POLICY Procedure	159-24
	UPDATE_FULL_REDACTION_VALUES Procedure	159-25
	UPDATE_POLICY_EXPRESSION Procedure	159-26
160	DBMS_REDEFINITION	
	DBMS_REDEFINITION Overview	160-1
	DBMS_REDEFINITION Security Model	160-1
	DBMS_REDEFINITION Constants	160-1
	DBMS_REDEFINITION Operational Notes	160-2
	DBMS_REDEFINITION Rules and Limits	160-3
	DBMS_REDEFINITION Examples	160-3
	Summary of DBMS_REDEFINITION Subprograms	160-4
	ABORT_REDEF_TABLE Procedure	160-5
	ABORT_ROLLBACK Procedure	160-6
	ABORT_UPDATE Procedure	160-6
	CAN_REDEF_TABLE Procedure	160-7
	COPY_TABLE_DEPENDENTS Procedure	160-7
	EXECUTE_UPDATE Procedure	160-9
	FINISH_REDEF_TABLE Procedure	160-9
	REDEF_TABLE Procedure	160-10
	REGISTER_DEPENDENT_OBJECT Procedure	160-12
	ROLLBACK Procedure	160-13
	SET_PARAM Procedure	160-13
	START_REDEF_TABLE Procedure	160-14
	SYNC_INTERIM_TABLE Procedure	160-16
	UNREGISTER_DEPENDENT_OBJECT Procedure	160-16
161	DBMS_REFRESH	
	DBMS_REFRESH Overview	161-1
	DBMS_REFRESH Security Model	161-1
	Summary of DBMS_REFRESH Subprograms	161-1
	ADD Procedure	161-2
	CHANGE Procedure	161-2
	DESTROY Procedure	161-4
	MAKE Procedure	161-4
	REFRESH Procedure	161-6
	SUBTRACT Procedure	161-7



162 DBMS_REPAIR

	DBMS_REPAIR Overview	162-1
	DBMS_REPAIR Security Model	162-1
	DBMS_REPAIR Constants	162-1
	DBMS_REPAIR Operating Notes	162-2
	DBMS_REPAIR Exceptions	162-3
	DBMS_REPAIR Examples	162-4
	Summary of DBMS_REPAIR Subprograms	162-4
	ADMIN_TABLES Procedure	162-4
	CHECK_OBJECT Procedure	162-5
	DUMP_ORPHAN_KEYS Procedure	162-6
	FIX_CORRUPT_BLOCKS Procedure	162-7
	ONLINE_INDEX_CLEAN Function	162-8
	REBUILD_FREELISTS Procedure	162-9
	SEGMENT_FIX_STATUS Procedure	162-9
	SKIP_CORRUPT_BLOCKS Procedure	162-10
163	DBMS_RESCONFIG	
	DBMS_RESCONFIG Overview	163-1
	Summary of DBMS_RESCONFIG Subprograms	163-1
	ADDREPOSITORYRESCONFIG Procedure	163-2
	ADDRESCONFIG Procedure	163-3
	APPENDRESCONFIG Procedure	163-3
	DELETEREPOSITORYRESCONFIG Procedure	163-4
	DELETERESCONFIG Procedures	163-5
	GETLISTENERS Function	163-5
	GETREPOSITORYRESCONFIG Function	163-6
	GETREPOSITORYRESCONFIGPATHS Function	163-6
	GETRESCONFIG Function	163-7
	GETRESCONFIGPATHS Function	163-7
	PATCHREPOSITORYRESCONFIGLIST Procedure	163-8
164	DBMS_RESOURCE_MANAGER	
	DBMS_RESOURCE_MANAGER Deprecated Subprograms	164-1
	DBMS_RESOURCE_MANAGER Security Model	164-1
	DBMS_RESOURCE_MANAGER Constants	164-1
	Summary of DBMS_RESOURCE_MANAGER Subprograms	164-3
	BEGIN_SQL_BLOCK Procedure	164-4
	CALIBRATE_IO Procedure	164-5



-	NT_SWITCH_CONSUMER_GROUP Procedure	165-1
Summarv	of DBMS_RESOURCE_MANAGER_PRIVS Subprograms	165-1
165 DBMS	_RESOURCE_MANAGER_PRIVS	
VALIL	ALL LINDING ARLA FIOCEGUIE	104-40
	ATE_PLAN_DIRECTIVE Procedure DATE_PENDING_AREA Procedure	164-36 164-40
	ATE_PLAN Procedure	164-35 164-36
	ATE_CONSUMER_GROUP Procedure	164-34
	ATE_CDB_PROFILE_DIRECTIVE Procedure	164-33
	ATE_CDB_PLAN_DIRECTIVE Procedure	164-32
	ATE_CDB_PLAN_Procedure	164-31
	ATE_CDB_DEFAULT_DIRECTIVE Procedure	164-30
	ATE_CDB_AUTOTASK_DIRECTIVE Procedure	164-29
	ATE_CATEGORY Procedure	164-29
	CH_PLAN Procedure	164-28
	CH_CONSUMER_GROUP_FOR_USER Procedure	164-28
	CH_CONSUMER_GROUP_FOR_SESS Procedure	164-27
	/IIT_PENDING_AREA Procedure	164-27
_	INITIAL_CONSUMER_GROUP Procedure	164-26
	CONSUMER_GROUP_MAPPING_PRI Procedure	164-25
_	CONSUMER_GROUP_MAPPING Procedure	164-24
_	SQL_BLOCK Procedure	164-24
	JEUE_PARALLEL_STATEMENT Procedure	164-23
	TE_PLAN_DIRECTIVE Procedure	164-23
	TE_PLAN_CASCADE Procedure	164-22
	TE_PLAN Procedure	164-22
	TE_CONSUMER_GROUP Procedure	164-22
	TE_CDB_PROFILE_DIRECTIVE Procedure	164-21
	TE_CDB_PLAN_DIRECTIVE Procedure	164-21
	TE_CDB_PLAN Procedure	164-20
DELE	TE_CATEGORY Procedure	164-20
CREA	ATE_SIMPLE_PLAN Procedure	164-18
CREA	ATE_PLAN_DIRECTIVE Procedure	164-14
CREA	ATE_PLAN Procedure	164-13
CREA	ATE_PENDING_AREA Procedure	164-11
CREA	ATE_CONSUMER_GROUP Procedure	164-11
CREA	ATE_CDB_PROFILE_DIRECTIVE Procedure	164-10
CREA	ATE_CDB_PLAN_DIRECTIVE Procedure	164-8
CREA	ATE_CDB_PLAN Procedure	164-8
CREA	ATE_CATEGORY Procedure	164-7
CLEA	R_PENDING_AREA Procedure	164-7



	GRANT_SYSTEM_PRIVILEGE Procedure	165-2
	REVOKE_SWITCH_CONSUMER_GROUP Procedure	165-3
	REVOKE_SYSTEM_PRIVILEGE Procedure	165-4
166	DBMS_RESULT_CACHE	
	DBMS_RESULT_CACHE Security Model	166-1
	DBMS_RESULT_CACHE Constants	166-1
	Summary of DBMS_RESULT_CACHE Subprograms	166-2
	BLACK_LIST Function	166-3
	BLACK_LIST_ADD Procedure	166-3
	BLACK_LIST_CLEAR Procedure	166-3
	BLACK_LIST_REMOVE Procedure	166-3
	BYPASS Procedure	166-3
	FLUSH Function & Procedure	166-4
	IGNORE_LIST Function	166-5
	IGNORE_LIST_ADD Procedure	166-5
	IGNORE_LIST_CLEAR Procedure	166-6
	IGNORE_LIST_REMOVE Procedure	166-6
	INVALIDATE Functions & Procedures	166-7
	INVALIDATE_OBJECT Functions & Procedures	166-7
	MEMORY_REPORT Procedure	166-8
	OBJECT_BLACK_LIST Function	166-8
	OBJECT_BLACK_LIST_ADD Procedure	166-8
	OBJECT_BLACK_LIST_CLEAR Procedure	166-9
	OBJECT_BLACK_LIST_REMOVE Procedure	166-9
	STATUS Function	166-9
	BLOCK_LIST Function	166-9
	BLOCK_LIST_ADD Procedure	166-9
	BLOCK_LIST_CLEAR Procedure	166-10
	BLOCK_LIST_REMOVE Procedure	166-10
	OBJECT_BLOCK_LIST Function	166-10
	OBJECT_BLOCK_LIST_ADD Procedure	166-10
	OBJECT_BLOCK_LIST_CLEAR Procedure	166-11
	OBJECT_BLOCK_LIST_REMOVE Procedure	166-11
167	DBMS_RESUMABLE	
	DBMS_RESUMABLE Operational Notes	167-1
	Summary of DBMS_RESUMABLE Subprograms	167-1
	ABORT Procedure	167-2
	GET_SESSION_TIMEOUT Function	167-2



	GEI_TIMEOUT Function	167-3
	SET_SESSION_TIMEOUT Procedure	167-3
	SET_TIMEOUT Procedure	167-4
	SPACE_ERROR_INFO Function	167-4
168	DBMS_RLS	
	DBMS_RLS Overview	168-1
	DBMS_RLS Security Model	168-2
	DBMS_RLS Constants	168-2
	DBMS_RLS Operational Notes	168-3
	DBMS_RLS Rules and Limits	168-3
	Summary of DBMS_RLS Subprograms	168-3
	ADD_GROUPED_POLICY Procedure	168-4
	ADD_POLICY Procedure	168-5
	ADD_POLICY_CONTEXT Procedure	168-10
	ALTER_POLICY Procedure	168-11
	ALTER_GROUPED_POLICY Procedure	168-12
	CREATE_POLICY_GROUP Procedure	168-13
	DELETE_POLICY_GROUP Procedure	168-13
	DISABLE_GROUPED_POLICY Procedure	168-14
	DROP_GROUPED_POLICY Procedure	168-15
	DROP_POLICY Procedure	168-15
	DROP_POLICY_CONTEXT Procedure	168-16
	ENABLE_GROUPED_POLICY Procedure	168-16
	ENABLE_POLICY Procedure	168-17
	REFRESH_GROUPED_POLICY Procedure	168-18
	REFRESH_POLICY Procedure	168-18
169	DBMS_ROLLING	
	DBMS_ROLLING Overview	169-1
	DBMS_ROLLING Security Model	169-2
	Summary of DBMS_ROLLING Subprograms	169-2
	INIT_PLAN Procedure	169-3
	DESTROY_PLAN Procedure	169-4
	BUILD_PLAN Procedure	169-4
	SET_PARAMETER Procedure	169-5
	START_PLAN Procedure	169-8
	SWITCHOVER Procedure	169-9
	FINISH_PLAN Procedure	169-10



170 DBMS_ROWID

	DBMS_ROWID Security Model	170-1
	DBMS_ROWID Types	170-1
	DBMS_ROWID Exceptions	170-2
	DBMS_ROWID Operational Notes	170-3
	DBMS_ROWID Examples	170-4
	Summary of DBMS_ROWID Subprograms	170-4
	ROWID_BLOCK_NUMBER Function	170-4
	ROWID_CREATE Function	170-5
	ROWID_INFO Procedure	170-6
	ROWID_OBJECT Function	170-7
	ROWID_RELATIVE_FNO Function	170-8
	ROWID_ROW_NUMBER Function	170-8
	ROWID_TO_ABSOLUTE_FNO Function	170-9
	ROWID_TO_EXTENDED Function	170-10
	ROWID_TO_RESTRICTED Function	170-11
	ROWID_TYPE Function	170-12
	ROWID_VERIFY Function	170-12
171	DBMS_RULE	
	DBMS_RULE Overview	171-1
	DBMS_RULE Security Model	171-1
	Summary of DBMS_RULE Subprograms	171-1
	CLOSE_ITERATOR Procedure	171-2
	EVALUATE Procedure	171-3
	EVALUATE EXPRESSION Procedure	171-6
	EVALUATE_EXPRESSION_ITERATOR Procedure	171-7
	EVALUATE RULE Procedure	171-8
	EVALUATE_RULE_ITERATOR Procedure	171-9
	GET_NEXT_HIT Function	171-9
	GET_NEXT_RESULT Function	171-10
	IS_FAST Procedure	171-10
170		
172	DBMS_RULE_ADM	
	DBMS_RULE_ADM Overview	172-1
	DBMS_RULE_ADM Security Model	172-1
	Summary of DBMS RULE ADM Subprograms	172-1



	ADD_RULE Procedure	172-2
	ALTER_EVALUATION_CONTEXT Procedure	172-4
	ALTER_RULE Procedure	172-6
	CREATE_EVALUATION_CONTEXT Procedure	172-8
	CREATE_RULE Procedure	172-9
	CREATE_RULE_SET Procedure	172-11
	DROP_EVALUATION_CONTEXT Procedure	172-11
	DROP_RULE Procedure	172-12
	DROP_RULE_SET Procedure	172-13
	GRANT_OBJECT_PRIVILEGE Procedure	172-14
	GRANT_SCHEMA_PRIVILEGE Procedure	172-15
	GRANT_SYSTEM_PRIVILEGE Procedure	172-16
	REMOVE_RULE Procedure	172-18
	REVOKE_OBJECT_PRIVILEGE Procedure	172-19
	REVOKE_SCHEMA_PRIVILEGE Procedure	172-19
	REVOKE_SYSTEM_PRIVILEGE Procedure	172-20
173	DBMS_SAGA	
	DBMS_SAGA Overview	173-1
	DBMS_SAGA Security Model	173-1
	Summary of DBMS_SAGA Subprograms	173-1
	BEGIN_SAGA Function	173-2
	GET_SAGA_ID Function	173-2
	SET_SAGA_ID Procedure	173-2
	COMMIT_SAGA Procedure	173-3
	ROLLBACK_SAGA Procedure	173-3
	IS_INCOMPLETE Function	173-4
	SET_INCOMPLETE Procedure	173-4
	SEND_REQUEST Procedure	173-5
174	DBMS_SCHEDULER	
	DBMS_SCHEDULER Deprecated Subprograms	174-1
	DBMS_SCHEDULER Security Model	174-1
	DBMS_SCHEDULER Rules and Limits	174-1
	DBMS_SCHEDULER Operational Notes	174-2
	DBMS_SCHEDULER Data Structures	174-11
	DBMS_SCHEDULER JOBARG Object Type	174-12
	JOBARG_ARRAY Table Type	174-13
	DBMS_SCHEDULER JOB_DEFINITION Object Type	174-13
	JOB_DEFINITION_ARRAY Table Type	174-17



JOBATTR Object Type	174-17
JOBATTR_ARRAY Table Type	174-18
SCHEDULER\$_STEP_TYPE Object Type	174-18
SCHEDULER\$_STEP_TYPE_LIST Table Type	174-19
SCHEDULER\$_EVENT_INFO Object Type	174-19
SCHEDULER_FILEWATCHER_RESULT Object Type	174-20
SCHEDULER_FILEWATCHER_REQUEST Object Type	174-21
Summary of DBMS_SCHEDULER Subprograms	174-22
ADD_EVENT_QUEUE_SUBSCRIBER Procedure	174-25
ADD_GROUP_MEMBER Procedure	174-26
ADD_JOB_EMAIL_NOTIFICATION Procedure	174-27
ADD_TO_INCOMPATIBILITY Procedure	174-29
ALTER_CHAIN Procedure	174-30
ALTER_RUNNING_CHAIN Procedure	174-32
CLOSE_WINDOW Procedure	174-34
COPY_JOB Procedure	174-34
CREATE_CHAIN Procedure	174-35
CREATE_CREDENTIAL Procedure	174-36
CREATE_DATABASE_DESTINATION Procedure	174-37
CREATE_EVENT_SCHEDULE Procedure	174-38
CREATE_FILE_WATCHER Procedure	174-39
CREATE_GROUP Procedure	174-40
CREATE_INCOMPATIBILITY Procedure	174-42
CREATE_JOB Procedure	174-43
CREATE_JOB_CLASS Procedure	174-51
CREATE_JOBS Procedure	174-53
CREATE_PROGRAM Procedure	174-54
CREATE_RESOURCE Procedure	174-57
CREATE_SCHEDULE Procedure	174-58
CREATE_WINDOW Procedure	174-59
DEFINE_ANYDATA_ARGUMENT Procedure	174-61
DEFINE_CHAIN_EVENT_STEP Procedure	174-62
DEFINE_CHAIN_RULE Procedure	174-63
DEFINE_CHAIN_STEP Procedure	174-66
DEFINE_METADATA_ARGUMENT Procedure	174-67
DEFINE_PROGRAM_ARGUMENT Procedure	174-68
DISABLE Procedure	174-70
DROP_AGENT_DESTINATION Procedure	174-72
DROP_CHAIN Procedure	174-73
DROP_CHAIN_RULE Procedure	174-74
DROP_CHAIN_STEP Procedure	174-75
DROP_CREDENTIAL Procedure	174-75



DROP_DATABASE_DESTINATION Procedure	1/4-/6
DROP_FILE_WATCHER Procedure	174-77
DROP_GROUP Procedure	174-78
DROP_INCOMPATIBILITY Procedure	174-78
DROP_JOB Procedure	174-79
DROP_JOB_CLASS Procedure	174-80
DROP_PROGRAM Procedure	174-81
DROP_PROGRAM_ARGUMENT Procedure	174-81
DROP_RESOURCE Procedure	174-82
DROP_SCHEDULE Procedure	174-83
DROP_WINDOW Procedure	174-83
DUMP_IN_MEMORY_TRACE Procedure	174-84
ENABLE Procedure	174-84
END_DETACHED_JOB_RUN Procedure	174-85
EVALUATE_CALENDAR_STRING Procedure	174-86
EVALUATE_RUNNING_CHAIN Procedure	174-88
GENERATE_JOB_NAME Function	174-89
GET_AGENT_INFO Function	174-89
GET_AGENT_VERSION Function	174-90
GET_ATTRIBUTE Procedure	174-91
GET_FILE Procedure	174-91
GET_SCHEDULER_ATTRIBUTE Procedure	174-93
OPEN_WINDOW Procedure	174-94
PURGE_LOG Procedure	174-95
PUT_FILE Procedure	174-96
REMOVE_EVENT_QUEUE_SUBSCRIBER Procedure	174-97
REMOVE_FROM_INCOMPATIBILITY Procedure	174-97
REMOVE_GROUP_MEMBER Procedure	174-98
REMOVE_JOB_EMAIL_NOTIFICATION Procedure	174-99
RESET_JOB_ARGUMENT_VALUE Procedure	174-99
RUN_CHAIN Procedure	174-100
RUN_JOB Procedure	174-102
SET_AGENT_REGISTRATION_PASS Procedure	174-103
SET_ATTRIBUTE Procedure	174-104
SET_ATTRIBUTE_NULL Procedure	174-119
SET_JOB_ANYDATA_VALUE Procedure	174-120
SET_JOB_ARGUMENT_VALUE Procedure	174-121
SET_JOB_ATTRIBUTES Procedure	174-122
SET_RESOURCE_CONSTRAINT Procedure	174-123
SET_SCHEDULER_ATTRIBUTE Procedure	174-124
STOP JOB Procedure	174-125



175 DBMS_SEARCH

176	DBMS_SERVER_ALERT	
	DBMS_SERVER_ALERT Security Model	176-1
	DBMS_SERVER_ALERT Object Types	176-1
	DBMS_SERVER_ALERT Relational Operators	176-2
	DBMS_SERVER_ALERT Supported Metrics	176-2
	Summary of DBMS_SERVER_ALERT Subprograms	176-6
	EXPAND_MESSAGE Function	176-6
	GET_THRESHOLD Procedure	176-7
	SET_THRESHOLD Procedure	176-8
177	DBMS_SERVICE	
	DBMS_SERVICE Overview	177-1
	DBMS_SERVICE Security Model	177-2
	DBMS_SERVICE Constants	177-2
	DBMS_SERVICE Operating Procedures	177-4
	DBMS_SERVICE Exceptions	177-5
	Summary of DBMS_SERVICE Subprograms	177-6
	CREATE_SERVICE Procedure	177-7
	DELETE_SERVICE Procedure	177-11
	DISCONNECT_SESSION Procedure	177-11
	MODIFY_SERVICE Procedure	177-12
	START_SERVICE Procedure	177-16
	STOP_SERVICE Procedure	177-17
178	DBMS_SESSION	
	DBMS_SESSION Security Model	178-1
	DBMS_SESSION Operational Notes	178-1
	DBMS_SESSION Data Structures	178-1
	DBMS_SERVICE INTEGER_ARRAY Table Type	178-1
	DBMS_SERVICE LNAME_ARRAY Table Type	178-1
	Summary of DBMS_SESSION Subprograms	178-2
	CLEAR_ALL_CONTEXT Procedure	178-3
	CLEAR_ALL_LOCAL_CONTEXTS Procedure	178-3
	CLEAR_CONTEXT Procedure	178-3
	CLEAR_IDENTIFIER Procedure	178-4
	CLOSE_DATABASE_LINK Procedure	178-4



	CURRENT_IS_ROLE_ENABLED Function	178-5
	FREE_UNUSED_USER_MEMORY Procedure	178-5
	GET_PACKAGE_MEMORY_UTILIZATION Procedure	178-7
	IS_ROLE_ENABLED Function	178-8
	IS_SESSION_ALIVE Function	178-8
	LIST_CONTEXT Procedures	178-9
	MODIFY_PACKAGE_STATE Procedure	178-9
	RESET_PACKAGE Procedure	178-13
	SESSION_IS_ROLE_ENABLED Function	178-14
	SESSION_TRACE_DISABLE Procedure	178-14
	SESSION _TRACE_ENABLE Procedure	178-15
	SET_CONTEXT Procedure	178-15
	SET_EDITION_DEFERRED Procedure	178-17
	SET_IDENTIFIER Procedure	178-17
	SET_NLS Procedure	178-18
	SET_ROLE Procedure	178-18
	SET_SQL_TRACE Procedure	178-18
	SLEEP Procedure	178-19
	SWITCH_CURRENT_CONSUMER_GROUP Procedure	178-19
	UNIQUE_SESSION_ID Function	178-21
	USE_DEFAULT_EDITION_ALWAYS procedure	178-21
	USE_DEFAULT_EDITION_DEFERRED procedure	178-22
179	DBMS_SFW_ACL_ADMIN	
	DBMS_SFW_ACL_ADMIN Security Model	179-1
	DBMS_SFW_ACL_ADMIN Operational Notes	179-1
	DBMS_SFW_ACL_ADMIN Examples	179-2
	Summary of DBMS_SFW_ACL_ADMIN Subprograms	179-3
	COMMIT_ACL Procedure	179-3
	IP_ADD_ACE Procedure	179-3
	IP_ADD_PDB_ACE Procedure	179-4
	IP_REMOVE_ACE Procedure	179-4
	IP_REMOVE_ACL Procedure	179-5
	IP_REMOVE_PDB_ACE Procedure	179-5
	IP_REMOVE_PDB_ACL Procedure	179-6
180	DBMS_SHARED_POOL	
180		190-1
180	DBMS_SHARED_POOL Overview	180-1
180		180-1 180-1 180-1



	ABORTED_REQUEST_THRESHOLD Procedure	180-2
	KEEP Procedure	180-2
	MARKHOT Procedure	180-4
	PURGE Procedure	180-5
	PURGE_ROW_CACHE Procedure	180-6
	SIZES Procedure	180-7
	UNKEEP Procedure	180-7
	UNMARKHOT Procedure	180-8
181	DBMS_SHARDING_DIRECTORY	
	DBMS_SHARDING_DIRECTORY Overview	181-1
	DBMS_SHARDING_DIRECTORY Security Model	181-1
	DBMS_SHARDING_DIRECTORY Public Constants	181-2
	Summary of DBMS_SHARDING_DIRECTORY Subprograms	181-2
	addKeyToPartition Procedure	181-2
	addKeyToPartitionCommit Procedure	181-3
	flagKeyForSplit Procedure	181-4
	removeKey Procedure	181-4
	removeKeyCommit Procedure	181-5
	setAssignmentRule	181-5
182	DBMS_SODA	
	DBMS_SODA Security Model	182-1
	Summary of DBMS_SODA Subprograms	182-1
	CREATE_COLLECTION Function	182-2
	DROP_COLLECTION Function	182-3
	GET_AS_OF_SCN Function	182-4
	GET_AS_OF_TIMESTAMP Function	182-4
	GET_DEFAULT_METADATA_AS_CLOB Function	182-4
	GET_DEFAULT_METADATA_AS_VARCHAR2 Function	182-4
	LIST_COLLECTION_NAMES Function	182-4
	OPEN_COLLECTION Function	182-5
	Summary of SODA Online Redefinition Subprograms	182-6
	ABORT_REDEF_COLLECTION Procedure	182-7
	CAN_REDEF_COLLECTION Procedure	182-7
	COPY_COLLECTION_DEPENDENTS Procedure	182-7
	CREATE_INTERIM_COLLECTION Procedure	182-8
	FINISH_REDEF_COLLECTION Procedure	182-9
	START_REDEF_COLLECTION Procedure	182-9
	SYNC_INTERIM_COLLETION Procedure	182-10



TO_UUID Function 182-10

183 DBMS_SPACE

	DBMS_SPACE Security Model	183-1
	DBMS_SPACE Data Structures	183-1
	DBMS_SPACE CREATE_TABLE_COST_COLINFO Object Type	183-1
	DBMS_SPACE ASA_RECO_ROW Record Type	183-2
	DBMS_SPACE ASA_RECO_ROW_TB Table Type	183-3
	Summary of DBMS_SPACE Subprograms	183-3
	DBMS_SPACE ASA_RECOMMENDATIONS Function	183-3
	CREATE_INDEX_COST Procedure	183-5
	CREATE_TABLE_COST Procedures	183-5
	FREE_BLOCKS Procedure	183-7
	ISDATAFILEDROPPABLE_NAME Procedure	183-8
	OBJECT_DEPENDENT_SEGMENTS Function	183-9
	OBJECT_GROWTH_TREND Function	183-10
	SHRINK_TABLESPACE Procedure	183-11
	SPACE_USAGE Procedures	183-14
	UNUSED_SPACE Procedure	183-17
184	DBMS_SPACE_ADMIN	
	DBMS_SPACE_ADMIN Security Model	184-1
	DBMS_SPACE_ADMIN Constants	184-1
	DBMS_SPACE_ADMIN Operational Notes	184-3
	Summary of DBMS_SPACE_ADMIN Subprograms	184-3
	ASSM_SEGMENT_VERIFY Procedure	184-4
	ASSM_TABLESPACE_VERIFY Procedure	184-5
	DROP_EMPTY_SEGMENTS Procedure	184-6
	GET_SEGADV_ATTRIB Procedure	184-7
	MATERIALIZE_DEFERRED_SEGMENTS Procedure	184-8
	SEGMENT_CORRUPT Procedure	184-8
	SEGMENT_DROP_CORRUPT Procedure	184-9
	SEGMENT_DUMP Procedure	184-10
	SEGMENT_VERIFY Procedure	184-11
	SET_SEGADV_ATTRIB Procedure	184-11
	TABLESPACE_FIX_BITMAPS Procedure	184-12
	TABLESPACE_FIX_SEGMENT_STATES Procedure	184-13
	TABLESPACE_MIGRATE_FROM_LOCAL Procedure	184-13
	TABLESPACE_MIGRATE_TO_LOCAL Procedure	184-14
	TABLESPACE_REBUILD_BITMAPS Procedure	184-15



	TABLESPACE_REBUILD_QUOTAS Procedure	184-15
	TABLESPACE_RELOCATE_BITMAPS Procedure	184-16
	TABLESPACE_VERIFY Procedure	184-17
185	DBMS_SPD	
	DBMS_SPD Overview	185-1
	DBMS_SPD Security Model	185-1
	DBMS_SPD Views	185-1
	Summary of DBMS_SPD Subprograms	185-1
	ALTER_SQL_PLAN_DIRECTIVE Procedure	185-2
	CREATE_STGTAB_DIRECTIVE Procedure	185-3
	DROP_SQL_PLAN_DIRECTIVE Procedure	185-4
	FLUSH_SQL_PLAN_DIRECTIVE Procedure	185-4
	GET_PREFS Function	185-5
	PACK_STGTAB_DIRECTIVE Function	185-5
	SET_PREFS Procedure	185-7
	UNPACK_STGTAB_DIRECTIVE Function	185-8
186	DBMS_SPM	
	DBMS_SPM Overview	186-1
	DBMS_SPM Security Model	186-2
	DBMS_SPM Constants	186-2
	DBMS_SPM Examples	186-2
	DBMS_SPM Data Structures	186-2
	DBMS_SPM NAMELIST Table Type	186-3
	Summary of DBMS_SPM Subprograms	186-3
	ACCEPT_SQL_PLAN_BASELINE Procedure	186-4
	ADD_VERIFIED_SQL_PLAN_BASELINE Function	186-5
	ALTER_SQL_PLAN_BASELINE Function	186-8
	CANCEL_EVOLVE_TASK Procedure	186-10
	CONFIGURE Procedure	186-10
	CREATE_EVOLVE_TASK Function	186-13
	CREATE_STGTAB_BASELINE Procedure	186-14
	DROP_EVOLVE_TASK Procedure	186-15
	DROP_MIGRATED_STORED_OUTLINE Function	186-15
	DROP_SQL_PLAN_BASELINE Function	186-15
	EVOLVE_SQL_PLAN_BASELINE Function	186-16
	EXECUTE_EVOLVE_TASK Function	186-17
	INTERRUPT_EVOLVE_TASK Procedure	186-18
	LOAD_PLANS_FROM_AWR Function	186-18



	LOAD_PLANS_FROM_CURSOR_CACHE Functions	186-19
	LOAD_PLANS_FROM_SQLSET Function	186-21
	MIGRATE_STORED_OUTLINE Functions	186-22
	PACK_STGTAB_BASELINE Function	186-24
	RESET_EVOLVE_TASK Procedure	186-25
	RESUME_EVOLVE_TASK Procedure	186-25
	REPORT_AUTO_EVOLVE_TASK Function	186-25
	REPORT_EVOLVE_TASK Function	186-26
	SET_EVOLVE_TASK_PARAMETER Procedure	186-27
	UNPACK_STGTAB_BASELINE Function	186-29
187	DBMS_SQL	
	DBMS_SQL Overview	187-1
	DBMS_SQL Security Model	187-2
	DBMS_SQL Constants	187-3
	DBMS_SQL Operational Notes	187-4
	DBMS_SQL Execution Flow	187-4
	OPEN_CURSOR	187-5
	PARSE	187-5
	BIND_VARIABLE, BIND_VARIABLE_PKG or BIND_ARRAY	187-7
	DEFINE_COLUMN, DEFINE_COLUMN_LONG, or DEFINE_ARRAY	187-7
	EXECUTE	187-7
	FETCH_ROWS or EXECUTE_AND_FETCH	187-7
	VARIABLE_VALUE, VARIABLE_VALUE_PKG, COLUMN_VALUE, or COLUMN_VALUE_LONG	187-8
	CLOSE_CURSOR	187-8
	DBMS_SQL Exceptions	187-8
	DBMS_SQL Examples	187-9
	DBMS_SQL Data Structures	187-15
	DBMS_SQL DESC_REC Record Type	187-16
	DBMS_SQL DESC_REC2 Record Type	187-17
	DBMS_SQL DESC_REC3 Record Type	187-18
	DBMS_SQL DESC_REC4 Record Type	187-19
	DBMS_SQL BFILE_TABLE Table Type	187-20
	DBMS_SQL BINARY_DOUBLE_TABLE Table Type	187-20
	DBMS_SQL BINARY_FLOAT_TABLE Table Type	187-20
	DBMS_SQL BLOB_TABLE Table Type	187-21
	DBMS_SQL BOOLEAN_TABLE Table Type	187-21
	DBMS_SQL CLOB_TABLE Table Type	187-21
	DBMS_SQL DATE_TABLE Table Type	187-21
	DBMS_SQL DESC_TAB Table Type	187-21



DBMS_SQL DESC_TAB2 Table Type	187-21
DBMS_SQL DESC_TAB3 Table Type	187-22
DBMS_SQL DESC_TAB4 Table Type	187-22
DBMS_SQL INTERVAL_DAY_TO_SECOND_TABLE Table Type	187-22
DBMS_SQL INTERVAL_YEAR_TO_MONTH_TABLE Table Type	187-22
DBMS_SQL JSON_TABLE Table Type	187-23
DBMS_SQL NUMBER_TABLE Table Type	187-23
DBMS_SQL TIME_TABLE Table Type	187-23
DBMS_SQL TIME_WITH_TIME_ZONE_TABLE Table Type	187-23
DBMS_SQL TIMESTAMP_TABLE Table Type	187-23
DBMS_SQL TIMESTAMP_WITH_LTZ_TABLE Table Type	187-24
DBMS_SQL TIMESTAMP_WITH_TIME_ZONE_TABLE Table Type	e 187-24
DBMS_SQL UROWID_TABLE Table Type	187-24
DBMS_SQL VARCHAR2_TABLE Table Type	187-24
DBMS_SQL VARCHAR2A Table Type	187-24
DBMS_SQL VARCHAR2S Table Type	187-24
DBMS_SQL VECTOR Table Type	187-25
Summary of DBMS_SQL Subprograms	187-25
BIND_ARRAY Procedures	187-26
BIND_VARIABLE Procedures	187-32
BIND_VARIABLE_PKG Procedure	187-33
CLOSE_CURSOR Procedure	187-35
COLUMN_VALUE Procedure	187-36
COLUMN_VALUE_LONG Procedure	187-39
DEFINE_ARRAY Procedure	187-39
DEFINE_COLUMN Procedures	187-43
DEFINE_COLUMN_CHAR Procedure	187-44
DEFINE_COLUMN_LONG Procedure	187-45
DEFINE_COLUMN_RAW Procedure	187-46
DEFINE_COLUMN_ROWID Procedure	187-46
DESCRIBE_COLUMNS Procedure	187-47
DESCRIBE_COLUMNS2 Procedure	187-48
DESCRIBE_COLUMNS3 Procedure	187-49
EXECUTE Function	187-50
EXECUTE_AND_FETCH Function	187-51
FETCH_ROWS Function	187-52
GET_NEXT_RESULT Procedures	187-52
IS_OPEN Function	187-53
LAST_ERROR_POSITION Function	187-54
LAST_ROW_COUNT Function	187-54
LAST_ROW_ID Function	187-55
LAST_SQL_FUNCTION_CODE Function	187-55



	OPEN_CURSOR Functions	187-56
	PARSE Procedures	187-57
	RETURN_RESULT Procedures	187-60
	TO_CURSOR_NUMBER Function	187-61
	TO_REFCURSOR Function	187-62
	VARIABLE_VALUE Procedures	187-64
	VARIABLE_VALUE_PKG Procedure	187-65
L88	DBMS_SQL_FIREWALL	
	DBMS_SQL_FIREWALL Overview	188-1
	DBMS_SQL_FIREWALL Security Model	188-1
	DBMS_SQL_FIREWALL Constants	188-2
	Summary of DBMS_SQL_FIREWALL Subprograms	188-3
	ADD_ALLOWED_CONTEXT Procedure	188-4
	APPEND_ALLOW_LIST Procedure	188-5
	APPEND_ALLOW_LIST_SINGLE_SQL Procedure	188-6
	CREATE_CAPTURE Procedure	188-8
	DELETE_ALLOWED_CONTEXT Procedure	188-9
	DELETE_ALLOWED_SQL Procedure	188-10
	DISABLE Procedure	188-10
	DISABLE_ALLOW_LIST Procedure	188-11
	DROP_ALLOW_LIST Procedure	188-11
	DROP_CAPTURE Procedure	188-12
	ENABLE Procedure	188-12
	ENABLE_ALLOW_LIST Procedure	188-13
	EXCLUDE Procedure	188-14
	EXPORT_ALLOW_LIST Procedure	188-14
	FLUSH_LOGS Procedure	188-15
	GENERATE_ALLOW_LIST Procedure	188-16
	IMPORT_ALLOW_LIST Procedure	188-17
	INCLUDE Procedure	188-18
	PURGE_LOG Procedure	188-18
	START_CAPTURE Procedure	188-19
	STOP_CAPTURE Procedure	188-20
	UPDATE_ALLOW_LIST_ENFORCEMENT Procedure	188-20
L89	DBMS_SQL_MONITOR	
	DBMS_SQL_MONITOR Overview	189-1
	DBMS_SQL_MONITOR Security Model	189-1
	DBMS_SQL_MONITOR Constants	189-2



	Summary of DBMS_SQL_MONITOR Subprograms	189-2
	BEGIN_OPERATION Function	189-2
	END_OPERATION Procedure	189-3
	REPORT_SQL_MONITOR Function	189-4
	REPORT_SQL_MONITOR_XML Function	189-8
	REPORT_SQL_MONITOR_LIST Function	189-8
	REPORT_SQL_MONITOR_LIST_XML Function	189-10
L90	DBMS_SQL_TRANSLATOR	
	DBMS_SQL_TRANSLATOR Security Model	190-1
	DBMS_SQL_TRANSLATOR Constants	190-1
	DBMS_SQL_TRANSLATOR Operational Notes	190-2
	DBMS_SQL_TRANSLATOR Exceptions	190-4
	DBMS_SQL_TRANSLATOR Examples	190-4
	Summary of DBMS_SQL_TRANSLATOR Subprograms	190-4
	CREATE_PROFILE Procedure	190-5
	DEREGISTER_SQL_TRANSLATION Procedure	190-6
	DEREGISTER_ERROR_TRANSLATION Procedure	190-7
	DROP_PROFILE Procedure	190-8
	ENABLE_ERROR_TRANSLATION Procedure	190-8
	ENABLE_SQL_TRANSLATION Procedure	190-9
	EXPORT_PROFILE Procedure	190-10
	IMPORT_PROFILE Procedure	190-11
	REGISTER_ERROR_TRANSLATION Procedure	190-12
	REGISTER_SQL_TRANSLATION Procedure	190-13
	SET_ATTRIBUTE Procedure	190-14
	SQL_HASH Function	190-15
	SQL_ID Function	190-16
	TRANSLATE_ERROR Procedure	190-17
	TRANSLATE_SQL Procedure	190-18
L91	DBMS_SQLDIAG	
	DBMS SQLDIAG Overview	191-1
	DBMS_SQLDIAG Security Model	191-1
	DBMS_SQLDIAG Constants	191-1
	Summary of DBMS_SQLDIAG Subprograms	191-4
	ACCEPT_SQL_PATCH Function & Procedure	191-5
	ALTER_SQL_PATCH Procedure	191-7
	CANCEL DIAGNOSIS TASK Procedure	191-7
	CREATE_DIAGNOSIS_TASK Functions	191-8



	CREATE_SQL_PATCH Function	191-9
	CREATE_STGTAB_SQLPATCH Procedure	191-10
	DROP_DIAGNOSIS_TASK Procedure	191-11
	DROP_SQL_PATCH Procedure	191-11
	EXECUTE_DIAGNOSIS_TASK Procedure	191-11
	EXPLAIN_SQL_TESTCASE Function	191-12
	EXPORT_SQL_TESTCASE Procedures	191-12
	EXPORT_SQL_TESTCASE_DIR_BY_INC Function	191-16
	EXPORT_SQL_TESTCASE_DIR_BY_TXT Function	191-17
	GET_FIX_CONTROL Function	191-19
	GET_SQL Function	191-19
	IMPORT_SQL_TESTCASE Procedures	191-19
	INCIDENTID_2_SQL Procedure	191-21
	INTERRUPT_DIAGNOSIS_TASK Procedure	191-22
	LOAD_SQLSET_FROM_TCB Function	191-22
	PACK_STGTAB_SQLPATCH Procedure	191-23
	REPLAY_SQL_TESTCASE Function	191-23
	REPORT_SQL Function	191-25
	REPORT_DIAGNOSIS_TASK Function	191-26
	RESET_DIAGNOSIS_TASK Procedure	191-27
	RESUME_DIAGNOSIS_TASK Procedure	191-27
	SET_DIAGNOSIS_TASK_PARAMETER Procedure	191-27
	SQL_DIAGNOSE_AND_REPAIR Function	191-28
	UNPACK_STGTAB_SQLPATCH Procedure	191-29
192	DBMS_SQLPA	
	DBMS_SQLPA Overview	192-1
	DBMS_SQLPA Security Model	192-1
	Summary of DBMS_SQLPA Subprograms	192-1
	CANCEL_ANALYSIS_TASK Procedure	192-2
	CREATE_ANALYSIS_TASK Functions	192-3
	DROP_ANALYSIS_TASK Procedure	192-5
	EXECUTE_ANALYSIS_TASK Function & Procedure	192-6
	INTERRUPT_ANALYSIS_TASK Procedure	192-8
	REPORT_ANALYSIS_TASK Function	192-8
	RESET_ANALYSIS_TASK Procedure	192-10
	RESUME_ANALYSIS_TASK Procedure	192-10
	SET_ANALYSIS_TASK_PARAMETER Procedures	192-11
	SET_ANALYSIS_DEFAULT_PARAMETER Procedures	192-15



193 DBMS_SQLQ

	DBMS_SQLQ Overview	193-1
	Summary of DBMS_SQLQ Subprograms	193-1
	ALTER_QUARANTINE Procedure	193-2
	CREATE_QUARANTINE_BY_SQL_ID Function	193-3
	CREATE_QUARANTINE_BY_SQL_TEXT Function	193-4
	CREATE_STGTAB_QUARANTINE Procedure	193-5
	DROP_QUARANTINE Procedure	193-6
	GET_PARAM_VALUE_QUARANTINE Function	193-6
	PACK_STGTAB_QUARANTINE Function	193-7
	UNPACK_STGTAB_QUARANTINE Function	193-8
194	DBMS_SQLSET	
	DBMS_SQLSET Overview	194-1
	DBMS_SQLSET Security Model	194-2
	DBMS_SQLSET Data Structures	194-2
	SQLSET_ROW Object Type	194-2
	Summary of DBMS_SQLSET Subprograms	194-4
	ADD_REFERENCE Function	194-5
	CAPTURE_CURSOR_CACHE Procedure	194-6
	CREATE_SQLSET Procedure and Function	194-8
	CREATE_STGTAB Procedure	194-9
	DELETE_SQLSET Procedure	194-10
	DROP_SQLSET Procedure	194-10
	LOAD_SQLSET Procedure	194-11
	PACK_STGTAB Procedure	194-15
	REMAP_STGTAB Procedure	194-17
	REMOVE_REFERENCE Procedure	194-18
	SELECT_CURSOR_CACHE Function	194-19
	SELECT_SQL_TRACE Function	194-24
	SELECT_SQLPA_TASK Function	194-27
	SELECT_SQLSET Function	194-28
	SELECT_WORKLOAD_REPOSITORY Function	194-30
	UNPACK_STGTAB Procedure	194-32
	UPDATE_SQLSET Procedures	194-33
195	DBMS_SQLTUNE	
	DBMS_SQLTUNE Overview	195-1
	DBMS_SQLTUNE Security Model	195-4



DBMS_SQLTUNE Data Structures	195-5
SQLSET_ROW Object Type	195-5
DBMS_SQLTUNE Subprogram Groups	195-7
DBMS_SQLTUNE SQL Tuning Advisor Subprograms	195-7
DBMS_SQLTUNE SQL Profile Subprograms	195-8
DBMS_SQLTUNE SQL Tuning Set Subprograms	195-8
DBMS_SQLTUNE Real-Time SQL Monitoring Subprograms	195-9
DBMS_SQLTUNE SQL Performance Reporting Subprograms	195-10
Summary of DBMS_SQLTUNE Subprograms	195-10
ACCEPT_ALL_SQL_PROFILES Procedure	195-13
ACCEPT_SQL_PROFILE Procedure and Function	195-15
ADD_SQLSET_REFERENCE Function	195-19
ALTER_SQL_PROFILE Procedure	195-20
CANCEL_TUNING_TASK Procedure	195-21
CAPTURE_CURSOR_CACHE_SQLSET Procedure	195-22
CREATE_SQL_PLAN_BASELINE Procedure	195-24
CREATE_SQLSET Procedure and Function	195-25
CREATE_STGTAB_SQLPROF Procedure	195-25
CREATE_STGTAB_SQLSET Procedure	195-26
CREATE_TUNING_TASK Functions	195-28
DELETE_SQLSET Procedure	195-34
DROP_SQL_PROFILE Procedure	195-35
DROP_SQLSET Procedure	195-35
DROP_TUNING_TASK Procedure	195-36
EXECUTE_TUNING_TASK Function and Procedure	195-37
IMPLEMENT_TUNING_TASK Procedure	195-38
INTERRUPT_TUNING_TASK Procedure	195-39
LOAD_SQLSET Procedure	195-40
PACK_STGTAB_SQLPROF Procedure	195-44
PACK_STGTAB_SQLSET Procedure	195-45
REMAP_STGTAB_SQLPROF Procedure	195-46
REMAP_STGTAB_SQLSET Procedure	195-47
REMOVE_SQLSET_REFERENCE Procedure	195-49
REPORT_AUTO_TUNING_TASK Function	195-50
REPORT_SQL_DETAIL Function	195-51
REPORT_SQL_MONITOR Function	195-55
REPORT_SQL_MONITOR_LIST Function	195-60
REPORT_TUNING_TASK Function	195-62
REPORT_TUNING_TASK_XML Function	195-64
RESET_TUNING_TASK Procedure	195-66
RESUME_TUNING_TASK Procedure	195-66
SCHEDULE_TUNING_TASK Function	195-67



	SCRIPT_TUNING_TASK Function	195-69
	SELECT_CURSOR_CACHE Function	195-71
	SELECT_SQL_TRACE Function	195-75
	SELECT_SQLPA_TASK Function	195-78
	SELECT_SQLSET Function	195-79
	SELECT_WORKLOAD_REPOSITORY Function	195-82
	SET_TUNING_TASK_PARAMETER Procedures	195-84
	SQLTEXT_TO_SIGNATURE Function	195-86
	UNPACK_STGTAB_SQLPROF Procedure	195-87
	UNPACK_STGTAB_SQLSET Procedure	195-88
	UPDATE_SQLSET Procedures	195-89
196	DBMS_STAT_FUNCS	
	Summary of DBMS_STAT_FUNCS Subprograms	196-1
	EXPONENTIAL_DIST_FIT Procedure	196-1
	NORMAL_DIST_FIT Procedure	196-2
	POISSON_DIST_FIT Procedure	196-2
	SUMMARY Procedure	196-3
	UNIFORM_DIST_FIT Procedure	196-4
	WEIBULL_DIST_FIT Procedure	196-5
197	DBMS_STATS	
	DBMS_STATS Overview	197-1
	DBMS_STATS Deprecated Subprograms	197-2
	DBMS_STATS Types	197-2
	DBMS_STATS Constants	197-3
	DBMS_STATS Operational Notes	197-4
	DBMS_STATS Data Structures	197-11
	DBMS_STATS STAT_REC Record Type	197-11
	Summary of DBMS_STATS Subprograms	197-11
	ALTER_STATS_HISTORY_RETENTION Procedure	197-17
	CANCEL_ADVISOR_TASK Procedure	197-18
	CONFIGURE_ADVISOR_FILTER Function	197-19
	CONFIGURE_ADVISOR_OBJ_FILTER Function	197-25
	CONFIGURE_ADVISOR_OPR_FILTER Functions	197-26
	CONFIGURE_ADVISOR_RULE_FILTER Function	197-29
	CONVERT_RAW_VALUE Procedures	197-30
	CONVERT_RAW_VALUE_NVARCHAR Procedure	197-31
	CONVERT_RAW_VALUE_INVARCHAR Flocedure	197-31
	CONVERT_RAW_VALUE_ROWID Procedure	197-31



CREATE_ADVISOR_TASK Function	197-34
CREATE_EXTENDED_STATS Function	197-35
CREATE_STAT_TABLE Procedure	197-36
DELETE_COLUMN_STATS Procedure	197-37
DELETE_DATABASE_PREFS Procedure	197-39
DELETE_DATABASE_STATS Procedure	197-43
DELETE_DICTIONARY_STATS Procedure	197-44
DELETE_FIXED_OBJECTS_STATS Procedure	197-46
DELETE_INDEX_STATS Procedure	197-47
DELETE_PENDING_STATS Procedure	197-48
DELETE_PLSQL_PREFS Procedure	197-49
DELETE_PROCESSING_RATE Procedure	197-50
DELETE_SCHEMA_PREFS Procedure	197-50
DELETE_SCHEMA_STATS Procedure	197-56
DELETE_SYSTEM_STATS Procedure	197-57
DELETE_TABLE_PREFS Procedure	197-58
DELETE_TABLE_STATS Procedure	197-64
DIFF_TABLE_STATS_IN_HISTORY Function	197-66
DIFF_TABLE_STATS_IN_PENDING Function	197-66
DIFF_TABLE_STATS_IN_STATTAB Function	197-67
DROP_ADVISOR_TASK Procedure	197-68
DROP_EXTENDED_STATS Procedure	197-69
DROP_STAT_TABLE Procedure	197-70
EXECUTE_ADVISOR_TASK Function	197-70
EXPORT_COLUMN_STATS Procedure	197-72
EXPORT_DATABASE_PREFS Procedure	197-73
EXPORT_DATABASE_STATS Procedure	197-74
EXPORT_DICTIONARY_STATS Procedure	197-75
EXPORT_FIXED_OBJECTS_STATS Procedure	197-76
EXPORT_INDEX_STATS Procedure	197-76
EXPORT_PENDING_STATS Procedure	197-77
EXPORT_SCHEMA_PREFS Procedure	197-78
EXPORT_SCHEMA_STATS Procedure	197-79
EXPORT_SYSTEM_STATS Procedure	197-80
EXPORT_TABLE_PREFS Procedure	197-80
EXPORT_TABLE_STATS Procedure	197-81
FLUSH_DATABASE_MONITORING_INFO Procedure	197-83
GATHER_DATABASE_STATS Procedures	197-83
GATHER_DICTIONARY_STATS Procedure	197-87
GATHER_FIXED_OBJECTS_STATS Procedure	197-91
GATHER_INDEX_STATS Procedure	197-92
GATHER_PROCESSING_RATE Procedure	197-94



GATHER_SCHEMA_STATS Procedures	197-94
GATHER_SYSTEM_STATS Procedure	197-99
GATHER_TABLE_STATS Procedure	197-101
GENERATE_STATS Procedure	197-105
GET_ADVISOR_OPR_FILTER Procedure	197-106
GET_ADVISOR_RECS Function	197-107
GET_COLUMN_STATS Procedures	197-108
GET_INDEX_STATS Procedures	197-110
GET_PARAM Function	197-113
GET_PLSQL_PREFS Procedure	197-113
GET_PREFS Function	197-114
GET_STATS_HISTORY_AVAILABILITY Function	197-124
GET_STATS_HISTORY_RETENTION Function	197-124
GET_SYSTEM_STATS Procedure	197-124
GET_TABLE_STATS Procedure	197-126
IMPLEMENT_ADVISOR_TASK Function	197-128
IMPORT_COLUMN_STATS Procedure	197-130
IMPORT_DATABASE_PREFS Procedure	197-132
IMPORT_DATABASE_STATS Procedure	197-132
IMPORT_DICTIONARY_STATS Procedure	197-134
IMPORT_FIXED_OBJECTS_STATS Procedure	197-135
IMPORT_INDEX_STATS Procedure	197-136
IMPORT_SCHEMA_PREFS Procedure	197-137
IMPORT_SCHEMA_STATS Procedure	197-138
IMPORT_SYSTEM_STATS Procedure	197-139
IMPORT_TABLE_PREFS Procedure	197-140
IMPORT_TABLE_STATS Procedure	197-141
INTERRUPT_ADVISOR_TASK Procedure	197-142
LOCK_PARTITION_STATS Procedure	197-144
LOCK_SCHEMA_STATS Procedure	197-144
LOCK_TABLE_STATS Procedure	197-145
MERGE_COL_USAGE Procedure	197-146
PREPARE_COLUMN_VALUES Procedures	197-147
PREPARE_COLUMN_VALUES_NVARCHAR Procedure	197-149
PREPARE_COLUMN_VALUES_ROWID Procedure	197-151
PUBLISH_PENDING_STATS Procedure	197-153
PURGE_STATS Procedure	197-154
REMAP_STAT_TABLE Procedure	197-154
REPORT_ADVISOR_TASK Function	197-155
REPORT_COL_USAGE Function	197-159
REPORT_GATHER_AUTO_STATS Function	197-160
REPORT_GATHER_DATABASE_STATS Functions	197-162



REPORT_GATHER_DICTIONARY_STATS Functions	197-167
REPORT_GATHER_FIXED_OBJ_STATS Function	197-170
REPORT_GATHER_SCHEMA_STATS Functions	197-173
REPORT_GATHER_TABLE_STATS Function	197-178
REPORT_SINGLE_STATS_OPERATION Function	197-183
REPORT_STATS_OPERATIONS Function	197-185
RESET_ADVISOR_TASK Procedure	197-187
RESET_COL_USAGE Procedure	197-188
RESET_GLOBAL_PLSQL_PREFS_DEF Procedure	197-188
RESET_PARAM_DEFAULTS Procedure	197-189
RESTORE_DATABASE_STATS Procedure	197-189
RESTORE_DICTIONARY_STATS Procedure	197-190
RESTORE_FIXED_OBJECTS_STATS Procedure	197-191
RESTORE_SCHEMA_STATS Procedure	197-191
RESTORE_SYSTEM_STATS Procedure	197-192
RESTORE_TABLE_STATS Procedure	197-193
RESUME_ADVISOR_TASK Procedure	197-194
SCRIPT_ADVISOR_TASK Function	197-195
SEED_COL_USAGE Procedure	197-198
SET_ADVISOR_TASK_PARAMETER Procedure	197-199
SET_COLUMN_STATS Procedures	197-200
SET_DATABASE_PREFS Procedure	197-202
SET_GLOBAL_PLSQL_PREFS Procedure	197-209
SET_GLOBAL_PREFS Procedure	197-211
SET_INDEX_STATS Procedures	197-221
SET_PARAM Procedure	197-224
SET_PLSQL_PREFS Procedure	197-225
SET_PROCESSING_RATE Procedure	197-227
SET_SCHEMA_PREFS Procedure	197-229
SET_SYSTEM_STATS Procedure	197-236
SET_TABLE_PREFS Procedure	197-237
SET_TABLE_STATS Procedure	197-246
SHOW_EXTENDED_STATS_NAME Function	197-249
TRANSFER_STATS Procedure	197-249
UNLOCK_PARTITION_STATS Procedure	197-250
UNLOCK_SCHEMA_STATS Procedure	197-251
UNLOCK_TABLE_STATS Procedure	197-251
UPGRADE_STAT_TABLE Procedure	197-252



198 DBMS_STORAGE_MAP

	DBMS_STORAGE_MAP Overview	198-1
	DBMS_STORAGE_MAP Operational Notes	198-2
	Summary of DBMS_STORAGE_MAP Subprograms	198-2
	DROP_ALL Function	198-2
	DROP_ELEMENT Function	198-3
	DROP_FILE Function	198-3
	LOCK_MAP Procedure	198-4
	MAP_ALL Function	198-4
	MAP_ELEMENT Function	198-4
	MAP_FILE Function	198-5
	MAP_OBJECT Function	198-6
	RESTORE Function	198-6
	SAVE Function	198-7
	UNLOCK_MAP Procedure	198-7
199	DBMS_SYNC_REFRESH	
	DBMS_SYNC_REFRESH Overview	199-1
	DBMS_SYNC_REFRESH Security Model	199-1
	Summary of DBMS_SYNC_REFRESH Subprograms	199-2
	ABORT_REFRESH Procedure	199-2
	ALTER_REFRESH_STATS_RETENTION Procedure	199-3
	CAN_SYNCREF_TABLE Procedure	199-4
	EXECUTE_REFRESH Procedure	199-5
	GET_ALL_GROUP_IDS Function	199-6
	GET_GROUP_ID Function	199-6
	GET_GROUP_ID_LIST Function	199-7
	PREPARE_REFRESH Procedure	199-7
	PREPARE_STAGING_LOG Procedure	199-8
	PURGE_REFRESH_STATS Procedure	199-10
	REGISTER_MVIEWS	199-10
	REGISTER_PARTITION_OPERATION Procedure	199-11
	UNREGISTER_MVIEWS	199-12
	UNREGISTER_PARTITION_OPERATION Procedure	199-12
200	DBMS_TABLE_DATA	
	DBMS_TABLE_DATA Overview	200-1
	DBMS_TABLE_DATA Security Model	200-1
	Summary of DBMS_TABLE_DATA Subprograms	200-2



	GET_BYTES_FOR_COLUMN Procedure	200-2
	GET_BYTES_FOR_COLUMNS Procedure	200-3
	GET_BYTES_FOR_ROW Procedure	200-3
201	DBMS_TDB	
	DBMS_TDB Overview	201-1
	DBMS_TDB Security Model	201-2
	DBMS_TDB Constants	201-2
	DBMS_TDB Views	201-2
	DBMS_TDB Operational Notes	201-2
	Summary of DBMS_TDB Subprograms	201-2
	CHECK_DB Function	201-3
	CHECK_EXTERNAL Function	201-4
202	DBMS_TF	
	DBMS_TF Overview	202-1
	DBMS_TF Security Model	202-1
	DBMS_TF Constants	202-2
	DBMS_TF Operational Notes	202-2
	PTF Client Interface	202-3
	DESCRIBE Only Polymorphic Table Function	202-5
	PTF Server Side Interface	202-5
	Read Columns	202-6
	Pass-Through Columns	202-6
	State Management	202-7
	CSTORE Compilation State Management	202-7
	XSTORE Execution State Management	202-9
	Method Name Overrides	202-9
	Using the COLUMNS Pseudo-Operator	202-11
	Query Transformations	202-11
	Parallel Execution	202-12
	DBMS_TF Execution Flow	202-12
	DBMS_TF Restrictions	202-14
	DBMS_TF Examples	202-15
	Echo Polymorphic Table Function Example	202-16
	DBMS_TF Data Structures	202-19
	Supported Types Collections	202-20
	COLUMN_DATA_T Record Type	202-21
	COLUMN_METADATA_T Record Type	202-22
	COLUMN_T Record Type	202-23



DESCRIBE_I Record Type	202-23
ENV_T Record Type	202-23
PARALLEL_ENV_T Record Type	202-24
TABLE_T Record Type	202-25
COLUMNS_NEW_T Table Type	202-25
COLUMNS_T Table Type	202-25
COLUMNS_WITH_TYPE_T Table Type	202-25
TABLE_COLUMNS_T Table Type	202-26
ROW_SET_T Table Type	202-26
XID_T Subtype	202-26
Summary of DBMS_TF Subprograms	202-26
COLUMN_TYPE_NAME Function	202-27
COL_TO_CHAR Function	202-28
CSTORE_EXISTS Function	202-29
CSTORE_GET Procedure	202-29
GET_COL Procedure	202-30
GET_ENV Function	202-32
GET_ROW_SET Procedure	202-32
Stack Polymorphic Table Function Example	202-33
GET_XID Function	202-36
PUT_COL Procedure	202-36
Rand_col Polymorphic Table Function Example	202-37
PUT_ROW_SET Procedure	202-40
Split Polymorphic Table Function Example	202-40
ROW_REPLICATION Procedure	202-43
ROW_TO_CHAR Function	202-45
SUPPORTED_TYPE Function	202-46
TRACE Procedure	202-46
XSTORE_CLEAR Procedure	202-47
XSTORE_EXISTS Function	202-48
XSTORE_GET Procedure	202-48
Row_num Polymorphic Table Function Example	202-49
XSTORE_REMOVE Procedure	202-51
XSTORE_SET Procedure	202-52
DBMS_TNS	
DBMS_TNS Overview	203-1
DBMS_TNS Security Model	203-1
Summary of DBMS_TNS Subprograms	203-1
RESOLVE_TNSNAME Function	203-2



203

204 DBMS_TRACE

	DBMS_TRACE Overview	204-1
	DBMS_TRACE Security Model	204-1
	DBMS_TRACE Constants	204-1
	DBMS_TRACE Restrictions	204-2
	DBMS_TRACE Operational Notes	204-3
	Summary of DBMS_TRACE Subprograms	204-5
	CLEAR_PLSQL_TRACE Procedure	204-5
	GET_PLSQL_TRACE_LEVEL Function	204-6
	PLSQL_TRACE_VERSION Procedure	204-6
	SET_PLSQL_TRACE Procedure	204-6
205	DBMS_TRANSACTION	
	DBMS_TRANSACTION Security Model	205-1
	Summary of DBMS_TRANSACTION Subprograms	205-1
	ADVISE_COMMIT Procedure	205-2
	ADVISE_NOTHING Procedure	205-3
	ADVISE_ROLLBACK Procedure	205-3
	COMMIT Procedure	205-3
	COMMIT_COMMENT Procedure	205-3
	COMMIT_FORCE Procedure	205-3
	GET_TRANSACTION_ID Function	205-4
	GET_TRANSACTION_TIMEOUT Function	205-4
	GET_TRANSACTION_TYPE Function	205-4
	LOCAL_TRANSACTION_ID Function	205-5
	PURGE_LOST_DB_ENTRY Procedure	205-5
	PURGE_MIXED Procedure	205-7
	READ_ONLY Procedure	205-7
	READ_WRITE Procedure	205-8
	ROLLBACK Procedure	205-8
	ROLLBACK_FORCE Procedure	205-8
	ROLLBACK_SAVEPOINT Procedure	205-8
	SAVEPOINT Procedure	205-9
	START_TRANSACTION Function	205-9
	STEP_ID Function	205-10
	SUSPEND_TRANSACTION Procedure	205-10
	USE_ROLLBACK_SEGMENT Procedure	205-11



206 DBMS_TRANSFORM

	Summary of DBMS_TRANSFORM Subprograms	206-1
	CREATE_TRANSFORMATION Procedure	206-1
	DROP_TRANSFORMATION Procedure	206-2
	MODIFY_TRANSFORMATION Procedure	206-3
207	DBMS_TSDP_MANAGE	
	DBMS_TSDP_MANAGE Overview	207-1
	DBMS_TSDP_MANAGE Security Model	207-1
	Summary of DBMS_TSDP_MANAGE Subprograms	207-2
	ADD_SENSITIVE_COLUMN Procedure	207-2
	ALTER_SENSITIVE_COLUMN Procedure	207-3
	ADD_SENSITIVE_TYPE Procedure	207-4
	DROP_SENSITIVE_COLUMN Procedure	207-4
	DROP_SENSITIVE_TYPE Procedure	207-5
	DROP_SENSITIVE_TYPE_SOURCE Procedure	207-5
	IMPORT_DISCOVERY_RESULT Procedure	207-6
	IMPORT_SENSITIVE_TYPES Procedure	207-6
	REMOVE_DISCOVERY_RESULT Procedure	207-7
208	DBMS_TSDP_PROTECT	
	DBMS_TSDP_PROTECT Overview	208-1
	DBMS_TSDP_PROTECT Security Model	208-1
	DBMS_TSDP_PROTECT Constants	208-2
	DBMS_TSDP_PROTECT Data Structures	208-2
	FEATURE_OPTIONS Table Type	208-2
	POLICY_CONDITIONS Table Type	208-2
	Summary of DBMS_TSDP_PROTECT Subprograms	208-2
	ADD_POLICY Procedure	208-3
	ALTER_POLICY Procedure	208-4
	ASSOCIATE_POLICY Procedure	208-5
	DISABLE_PROTECTION_COLUMN Procedure	208-6
	DISABLE_PROTECTION_SOURCE Procedure	208-7
	DISABLE_PROTECTION_TYPE Procedure	208-7
	DROP_POLICY Procedure	208-7
	ENABLE_PROTECTION_COLUMN Procedure	208-9
	ENABLE_PROTECTION_SOURCE Procedure	208-9
	ENABLE_PROTECTION_TYPE Procedure	208-10



209 DBMS_TTS

	DBMS_TTS Security Model DBMS_TTS Exceptions DBMS_TTS Operational Notes	209-1 209-1
	DOWNGRADE Procedure TRANSPORT_SET_CHECK Procedure	209-2 209-2 209-2
210	DBMS_TYPES	
	DBMS_TYPES Constants DBMS_TYPES Exceptions	210-1 210-2
211	DBMS_UMF	
	Summary of DBMS_UMF Subprograms CONFIGURE_NODE Procedure CREATE_LINK Procedure CREATE_TOPOLOGY Procedure DROP_LINK Procedure DROP_TOPOLOGY Procedure ENABLE_SERVICE Procedure GET_NODE_ID_LOCAL Function GET_NODE_NAME_LOCAL Function GET_TARGET_ID Function GET_TOPOLOGY_NAME_LOCAL Function QUERY_LINK_INFO Procedure QUERY_NODE_INFO Procedures REGISTER_NODE Function and Procedure SWITCH_DESTINATION Procedure UNCONFIGURE_NODE Procedure UNREGISTER_NODE Procedure	211-1 211-2 211-3 211-3 211-3 211-4 211-4 211-5 211-6 211-7 211-7 211-8 211-9 211-10
212	DBMS_UNDO_ADV	
	Summary of DBMS_UNDO_ADV Subprograms BEST_POSSIBLE_RETENTION Function RBU_MIGRATION Function LONGEST_QUERY Function REQUIRED_RETENTION Function REQUIRED_UNDO_SIZE Function UNDO_ADVISOR Function	212-1 212-2 212-3 212-4 212-5 212-6



	UNDO_AUTOTUNE Function UNDO_HEALTH Function UNDO_INFO Function	212-7 212-7 212-9
213	DBMS_USER_CERTS	
	DBMS_USER_CERTS Overview	213-1
	DBMS USER CERTS Security Model	213-1
	Summary of DBMS_USER_CERTS Subprograms	213-2
	ADD_CERTIFICATE Procedure	213-2
	ADD_COPY Procedure	213-2
	DROP_CERTIFICATE Procedure	213-3
214	DBMS_USERDIAG	
	DBMS_USERDIAG Overview	214-1
	Summary of DBMS_USERDIAG Subprograms	214-1
	CHECK_SQL_TRACE_EVENT Procedure	214-2
	ENABLE_SQL_TRACE_EVENT Procedure	214-2
	GET_CALL_ERROR_MSG Function	214-3
	GET_CALL_STATUS Function	214-3
	SET_EXCEPTION_MODE Procedure	214-4
	SET_TRACEFILE_IDENTIFIER Procedure	214-4
	TRACE Procedure	214-4
215	DBMS_UTILITY	
	DBMS_UTILITY Deprecated Subprograms	215-1
	DBMS_UTILITY Security Model	215-1
	DBMS_UTILITY Constants	215-2
	DBMS_UTILITY Exceptions	215-2
	DBMS_UTILITY Data Structures	215-2
	DBMS_UTILITY INSTANCE_RECORD Record Type	215-3
	DBMS_UTILITY DBLINK_ARRAY TABLE Type	215-3
	DBMS_UTILITY INDEX_TABLE_TYPE Table Type	215-3
	DBMS_UTILITY INSTANCE_TABLE Table Type	215-3
	DBMS_UTILITY LNAME_ARRAY Table Type	215-4
	DBMS_UTILITY NAME_ARRAY Table Type	215-4
	DBMS_UTILITY NUMBER_ARRAY Table Type	215-4
	DBMS_UTILITY UNCL_ARRAY Table Type	215-4
	Summary of DBMS_UTILITY Subprograms	215-4
	ACTIVE_INSTANCES Procedure	215-6



	Summary of DBMS_VECTOR Subprograms	216-1
216	DBMS_VECTOR	
	WAIT_ON_PENDING_DML Function	215-31
	VALIDATE Procedure	215-30
	TABLE_TO_COMMA Procedures	215-30
	SQLID_TO_SQLHASH Function	215-29
	PORT_STRING Function	215-29
	OLD_CURRENT_USER Function	215-29
	OLD_CURRENT_SCHEMA Function	215-29
	NAME_TOKENIZE Procedure	215-28
	NAME_RESOLVE Procedure	215-27
	MAKE_DATA_BLOCK_ADDRESS Function	215-26
	IS_CLUSTER_DATABASE Function	215-26
	IS_BIT_SET Function	215-25
	INVALIDATE Procedure	215-23
	GET_TZ_TRANSITIONS Procedure	215-22
	GET_TIME Function	215-22
	GET_SQL_HASH Function	215-21
	GET_PARAMETER_VALUE Function	215-20
	GET_HASH_VALUE Function	215-19
	GET_ENDIANNESS Function	215-19
	GET_DEPENDENCY Procedure	215-18
	GET_CPU_TIME Function	215-18
	FORMAT_ERROR_STACK Function	215-18
	FORMAT_ERROR_BACKTRACE Function	215-15
	FORMAT_CALL_STACK Function	215-15
	EXPAND_SQL_TEXT Procedure	215-14
	EXEC_DDL_STATEMENT Procedure	215-14
	DB_VERSION Procedure	215-13
	DATA_BLOCK_ADDRESS_FILE Function	215-13
	DATA_BLOCK_ADDRESS_BLOCK Function	215-12
	CURRENT_INSTANCE Function	215-12
	CREATE_ALTER_TYPE_ERROR_TABLE Procedure	215-11
	COMPILE_SCHEMA Procedure	215-10
	COMMA_TO_TABLE Procedures	215-10
	CANONICALIZE Procedure	215-9
	ANALYZE_SCHEMA Procedure	215-8
	ANALYZE PART OBJECT Procedure	215-7
	ANALYZE_DATABASE Procedure	215-6



CREATE_CREDENTIAL

216-2

	CREATE_INDEX	216-5
	DISABLE_CHECKPOINT	216-8
	DROP_CREDENTIAL	216-9
	ENABLE_CHECKPOINT	216-9
	DROP_ONNX_MODEL Procedure	216-10
	GET_INDEX_STATUS	216-11
	INDEX_ACCURACY_QUERY	216-12
	INDEX_ACCURACY_REPORT	216-13
	INDEX_VECTOR_MEMORY_ADVISOR	216-14
	LOAD_ONNX_MODEL	216-16
	JSON Metadata Parameters for ONNX Models	216-18
	LOAD_ONNX_MODEL_CLOUD	216-24
	QUERY	216-25
	REBUILD_INDEX	216-26
	RERANK	216-30
	UTL_TO_CHUNKS	216-34
	UTL_TO_EMBEDDING and UTL_TO_EMBEDDINGS	216-40
	UTL_TO_GENERATE_TEXT	216-49
217	DBMS_VECTOR_CHAIN	
	Summary of DBMS_VECTOR_CHAIN Subprograms	217-1
	CREATE_CREDENTIAL	217-2
	CREATE_LANG_DATA	217-5
	CREATE_PREFERENCE	217-6
	CREATE_VOCABULARY	217-16
	DROP_CREDENTIAL	217-19
	DROP_LANG_DATA	217-19
	DROP_PREFERENCE	217-20
	DROP_VOCABULARY	217-20
	RERANK	217-21
	UTL_TO_CHUNKS	217-25
	UTL_TO_EMBEDDING and UTL_TO_EMBEDDINGS	217-31
	UTL_TO_GENERATE_TEXT	217-40
	UTL_TO_TEXT	217-49
	UTL_TO_SUMMARY	217-50
	Supported Languages and Data File Locations	217-59
218	DBMS_WARNING	
	DBMS_WARNING Security Model	218-1
	Summary of DBMS_WARNING Subprograms	218-1



	ADD_WARNING_SETTING_NUM Procedure	218-2
	GET_CATEGORY Function	218-3
	GET_WARNING_SETTING_CAT Function	218-4
	GET_WARNING_SETTING_NUM Function	218-4
	GET_WARNING_SETTING_STRING Function	218-4
	SET_WARNING_SETTING_STRING Procedure	218-5
219	DBMS_WM	
220	DBMS_WORKLOAD_CAPTURE	
220	DBMS WORKLOAD CAPTURE Overview	220-1
	DBMS_WORKLOAD_CAPTURE Security Model	220-1
	Summary of DBMS_WORKLOAD_CAPTURE Subprograms	220-2
	ADD_FILTER Procedures	220-2
	DECRYPT_CAPTURE Procedure	220-4
	DELETE_CAPTURE_INFO Procedure	220-4
	DELETE_FILTER Procedure	220-5
	ENCRYPT_CAPTURE Procedure	220-5
	EXPORT_AWR Procedure	220-6
	FINISH_CAPTURE Procedure	220-7
	GET_CAPTURE_INFO Function	220-7
	IMPORT_AWR Function	220-8
	REPORT Function	220-9
	START_CAPTURE Procedure	220-10
221	DBMS_WORKLOAD_REPLAY	
	DBMS_WORKLOAD_REPLAY Overview	221-1
	DBMS_WORKLOAD_REPLAY Security Model	221-1
	Summary of DBMS_WORKLOAD_REPLAY Subprograms	221-2
	ADD_CAPTURE Function	221-4
	ADD_FILTER Procedure	221-5
	ADD_SCHEDULE_ORDERING Function	221-5
	ASSIGN_GROUP_TO_INSTANCE Procedure	221-6
	BEGIN_REPLAY_SCHEDULE Procedure	221-7
	CALIBRATE Function	221-7
	CANCEL_REPLAY Procedure	221-8
	COMPARE_PERIOD_REPORT Procedure	221-9
	COMPARE_SQLSET_REPORT Function	221-9

ADD_WARNING_SETTING_CAT Procedure



218-2

	CREATE_FILTER_SET Procedure	221-10
	DELETE_FILTER Procedure	221-11
	DELETE_REPLAY_INFO Procedure	221-11
	END_REPLAY_SCHEDULE Procedure	221-12
	EXPORT_AWR Procedure	221-12
	GENERATE_CAPTURE_SUBSET Procedure	221-12
	GET_DIVERGING_STATEMENT Function	221-13
	GET_REPLAY_DIRECTORY Function	221-14
	GET_REPLAY_INFO Function	221-14
	GET_REPLAY_TIMEOUT Procedure	221-15
	IMPORT_AWR Function	221-15
	INITIALIZE_CONSOLIDATED_REPLAY Procedure	221-16
	INITIALIZE_REPLAY Procedure	221-17
	IS_REPLAY_PAUSED Function	221-19
	LOAD_LONG_SQLTEXT Procedure	221-19
	PAUSE_REPLAY Procedure	221-19
	POPULATE_DIVERGENCE Procedure	221-20
	PREPARE_CONSOLIDATED_REPLAY Procedure	221-20
	PREPARE_REPLAY Procedure	221-22
	PROCESS_CAPTURE Procedure	221-26
	REMAP_CONNECTION Procedure	221-27
	REMOVE_CAPTURE Procedure	221-28
	REMOVE_SCHEDULE_ORDERING Procedure	221-29
	REPORT Function	221-29
	RESUME_REPLAY Procedure	221-30
	REUSE_REPLAY_FILTER_SET Procedure	221-30
	SET_ADVANCED_PARAMETER Procedure	221-31
	SET_REPLAY_DIRECTORY Procedure	221-32
	SET_REPLAY_TIMEOUT Procedure	221-32
	SET_SQL_MAPPING Procedure	221-33
	SET_USER_MAPPING Procedure	221-34
	START_CONSOLIDATED_REPLAY Procedure	221-34
	START_REPLAY Procedure	221-35
	USE_FILTER_SET Procedure	221-35
222	DBMS_WORKLOAD_REPOSITORY	
	DBMS_WORKLOAD_REPOSITORY Examples	222-1
	DBMS_WORKLOAD_REPOSITORY Data Structures	222-1
	DBMS_WORKLOAD_REPOSITORY AWR_BASELINE_METRIC_TYPE Object Type	222-2
	DBMS_WORKLOAD_REPOSITORY AWR_BASELINE_METRIC_TYPE_TABLE Table Type	222-2



	DBMS_WORKLOAD_REPOSITORY AWRRPT_INSTANCE_LIST_TYPE Table Type	222-3
Su	mmary of DBMS_WORKLOAD_REPOSITORY Subprograms	222-3
	ADD_COLORED_SQL Procedure	222-5
	ASH_GLOBAL_REPORT_HTML Function	222-5
	ASH_GLOBAL_REPORT_TEXT Function	222-7
	ASH_REPORT_ANALYTICS Function	222-9
	ASH_REPORT_HTML Function	222-10
	ASH_REPORT_TEXT Function	222-12
	AWR_DIFF_REPORT_HTML Function	222-15
	AWR_DIFF_REPORT_TEXT Function	222-15
	AWR_EXP Procedure	222-16
	AWR_GLOBAL_DIFF_REPORT_HTML Functions	222-17
	AWR_GLOBAL_DIFF_REPORT_TEXT Functions	222-18
	AWR_GLOBAL_REPORT_HTML Functions	222-19
	AWR_GLOBAL_REPORT_TEXT Functions	222-20
	AWR_IMP Procedure	222-21
	AWR_REPORT_HTML Function	222-21
	AWR_REPORT_TEXT Function	222-22
	AWR_SET_REPORT_THRESHOLDS Procedure	222-23
	AWR_SQL_REPORT_HTML Function	222-24
	AWR_SQL_REPORT_TEXT Function	222-25
	CONTROL_RESTRICTED_SNAPSHOT Procedure	222-26
	CREATE_BASELINE Functions and Procedures	222-26
	CREATE_BASELINE_TEMPLATE Procedures	222-28
	CREATE_REMOTE_SNAPSHOT Function and Procedure	222-29
	CREATE_SNAPSHOT Function and Procedure	222-30
	DROP_BASELINE Procedure	222-31
	DROP_BASELINE_TEMPLATE Procedure	222-32
	DROP_SNAPSHOT_RANGE Procedure	222-32
	LOCAL_AWR_DBID Function	222-33
	MODIFY_BASELINE_WINDOW_SIZE Procedure	222-33
	MODIFY_SNAPSHOT_SETTINGS Procedures	222-34
	PURGE_SQL_DETAILS Procedure	222-35
	REGISTER_REMOTE_DATABASE Procedures	222-36
	REMOVE_COLORED_SQL Procedure	222-36
	RENAME_BASELINE Procedure	222-37
	SELECT_BASELINE_DETAILS Function	222-37
	SELECT_BASELINE_METRIC Function	222-38
	UNREGISTER_REMOTE_DATABASE Procedures	222-38
	UPDATE_DATAFILE_INFO Procedure	222-39
	UPDATE OBJECT INFO Procedure	222-39



223 DBMS_XDB

DBMS_XDB Overview	223-1
DBMS_XDB Security Model	223-2
DBMS_XDB Constants	223-2
Summary of DBMS_XDB Subprograms	223-3
ACLCHECKPRIVILEGES Function	223-4
APPENDRESOURCEMETADATA Procedure	223-5
CHANGEOWNER Procedure	223-6
CHANGEPRIVILEGES Function	223-7
CHECKPRIVILEGES Function	223-7
CREATEFOLDER Function	223-8
CREATEOIDPATH Function	223-9
CREATERESOURCE Functions	223-9
DELETERESOURCE Procedure	223-11
DELETERESOURCEMETADATA Procedures	223-12
ENABLEDIGESTAUTHENTICATION Procedure	223-13
EXISTSRESOURCE Function	223-13
GETACLDOCUMENT Function	223-14
GETCONTENTBLOB Function	223-14
GETCONTENTCLOB Function	223-15
GETCONTENTVARCHAR2 Function	223-16
GETCONTENTXMLREF Function	223-16
GETCONTENTXMLTYPE Function	223-17
GETHTTPREQUESTHEADER Function	223-17
GETLOCKTOKEN Procedure	223-18
GETPRIVILEGES Function	223-19
GETRESOID Function	223-19
GETXDB_TABLESPACE Function	223-20
HASBLOBCONTENT Function	223-20
HASCHARCONTENT Function	223-21
HASXMLCONTENT Function	223-21
HASXMLREFERENCE Function	223-22
ISFOLDER Function	223-22
LINK Procedures	223-23
LOCKRESOURCE Function	223-24
PROCESSLINKS Procedure	223-25
PURGERESOURCEMETADATA Procedure	223-25
RENAMERESOURCE Procedure	223-26
SETACL Procedure	223-26
SPLITPATH Procedure	223-27
TOUCHRESOURCE Procedure	223-28



	UNLOCKRESOURCE Function	223-28
	UPDATERESOURCEMETADATA Procedures	223-29
224	DBMS_XA	
	DBMS_XA Overview	224-1
	DBMS_XA Security Model	224-1
	DBMS_XA Constants	224-2
	DBMS_XA Operational Notes	224-3
	DBMS_XA Data Structures	224-4
	DBMS_XA DBMS_XA_XID Object Type	224-4
	DBMS_XA DBMS_XA_XID_ARRAY Table Type	224-5
	Summary of DBMS_XA Subprograms	224-5
	DIST_TXN_SYNC Procedure	224-6
	XA_COMMIT Function	224-6
	XA_END Function	224-7
	XA_FORGET Function	224-8
	XA_GETLASTOER Function	224-8
	XA_PREPARE Function	224-8
	XA_RECOVER Function	224-9
	XA_ROLLBACK Function	224-9
	XA_SETTIMEOUT Function	224-10
	XA_START Function	224-10
225	DBMS_XDB_ADMIN	
	DBMS_XDB_ADMIN Security Model	225-1
	Summary of DBMS_XDB_ADMIN Subprograms	225-1
	CREATENONCEKEY Procedure	225-1
	INSTALLDEFAULTWALLET Procedure	225-2
	MOVEXDB_TABLESPACE Procedure	225-2
	REBUILDHIERARCHICALINDEX Procedure	225-2
226	DBMS_XDB_CONFIG	
	DBMS_XDB_CONFIG Overview	226-1
	DBMS_XDB_CONFIG Security Model	226-2
	DBMS_XDB_CONFIG Constants	226-2
	Summary of DBMS_XDB_CONFIG Subprograms	226-2
	ADDHTTPEXPIREMAPPING Procedure	226-4
	ADDMIMEMAPPING Procedure	226-4
	ADDSCHEMALOCMAPPING Procedure	226-5



	ADDSERVLET Procedure	226-5
	ADDSERVLETMAPPING Procedure	226-6
	ADDSERVLETSECROLE Procedure	226-7
	ADDXMLEXTENSION Procedure	226-7
	CFG_GET Function	226-8
	CFG_REFRESH Procedure	226-8
	CFG_UPDATE Procedure	226-8
	DELETEHTTPEXPIREMAPPING Procedure	226-8
	DELETEMIMEMAPPING Procedure	226-9
	DELETESCHEMALOCMAPPING Procedure	226-9
	DELETESERVLET Procedure	226-9
	DELETESERVLETMAPPING Procedure	226-10
	DELETESERVLETSECROLE Procedure	226-10
	DELETEXMLEXTENSION Procedure	226-10
	ENABLEDIGESTAUTHENTICATION Procedure	226-11
	GETFTPPORT Function	226-11
	GETHTTPCONFIGREALM Function	226-11
	GETHTTPPORT Function	226-11
	GETHTTPSPORT Function	226-11
	GETLISTENERENDPOINT Procedure	226-12
	GETREMOTEHTTPPORT Function	226-12
	GETREMOTEHTTPSPORT Function	226-12
	ISGLOBALPORTENABLED Function	226-12
	SETFTPPORT Procedure	226-13
	SETHTTPPORT Procedure	226-13
	SETHTTPCONFIGREALM Procedure	226-13
	SETHTTPSPORT Procedure	226-14
	SETLISTENERENDPOINT Procedure	226-14
	SETLISTENERLOCALACCESS Procedure	226-15
	SETREMOTEHTTPPORT Procedure	226-15
	SETREMOTEHTTPSPORT Procedure	226-15
	USEDPORT Function	226-16
227	DBMS_XDB_CONSTANTS	
	DBMS_XDB_CONSTANTS Security Model	227-1
	Summary of DBMS_XDB_CONSTANTS Subprograms	227-1
	ENCODING_DEFAULT Function	227-2
	ENCODING_ISOLATIN1 Function	227-3
	ENCODING_UTF8 Function	227-3
	ENCODING_WIN1252 Function	227-3
	NAMESPACE_ACL Function	227-3



	NAMESPACE_METADATA Function	227-4
	NAMESPACE_ORACLE Function	227-4
	NAMESPACE_ORACLE_XDB Function	227-4
	NAMESPACE_RESOURCE Function	227-4
	NAMESPACE_RESOURCE_EVENT Function	227-5
	NAMESPACE_RESOURCE_CONFIG Function	227-5
	NAMESPACE_XDBSCHEMA Function	227-5
	NAMESPACE_XMLDIFF Function	227-5
	NAMESPACE_XMLINSTANCE Function	227-6
	NAMESPACE_XMLSCHEMA Function	227-6
	NSPREFIX_ACL_ACL Function	227-6
	NSPREFIX_RESCONFIG_RC Function	227-6
	NSPREFIX_RESOURCE_R Function	227-7
	NSPREFIX_XDB_XDB Function	227-7
	NSPREFIX_XMLINSTANCE_XSI Function	227-7
	NSPREFIX_XMLDIFF_XD Function	227-7
	NSPREFIX_XMLSCHEMA_XSD Function	227-8
	SCHEMAURL_ACL Function	227-8
	SCHEMAELEM_RES_ACL Function	227-8
	SCHEMAELEM_RESCONTENT_BINARY Funct	ion 227-8
	SCHEMAELEM_RESCONTENT_TEXT Function	227-9
	SCHEMAURL_RESOURCE Function	227-9
	SCHEMAURL_XDBSCHEMA Function	227-9
	XDBSCHEMA_PREFIXES Function	227-9
	XSD_ATTRIBUTE Function	227-10
	XSD_COMPLEX_TYPE Function	227-10
	XSD_ELEMENT Function	227-10
	XSD_GROUP Function	227-10
228	DBMS_XDB_REPOS	
	DBMS_XDB_REPOS Overview	228-1
	DBMS_XDB_REPOS Security Model	228-1
	DBMS_XDB_REPOS Constants	228-2
	Summary of DBMS_XDB_REPOS Subprograms	228-2
	ACLCHECKPRIVILEGES Function	228-4
	APPENDRESOURCEMETADATA Procedure	228-4
	CHANGEOWNER Procedure	228-5
	CHANGEPRIVILEGES Function	228-5
	CHECKPRIVILEGES Function	228-6
	CREATEFOLDER Function	228-6
	CREATEOIDPATH Function	228-7



	CREATERESOURCE Functions	228-7
	DELETERESOURCE Procedure	228-9
	DELETERESOURCEMETADATA Procedures	228-9
	EXISTSRESOURCE Function	228-10
	GETACLDOCUMENT Function	228-10
	GETCONTENTBLOB Function	228-11
	GETCONTENTCLOB Function	228-11
	GETCONTENTVARCHAR2 Function	228-12
	GETCONTENTXMLREF Function	228-12
	GETCONTENTXMLTYPE Function	228-13
	GETLOCKTOKEN Procedure	228-13
	GETPRIVILEGES Function	228-13
	GETRESOID Function	228-14
	GETXDB_TABLESPACE Function	228-14
	HASBLOBCONTENT Function	228-14
	HASCHARCONTENT Function	228-15
	HASXMLCONTENT Function	228-15
	HASXMLREFERENCE Function	228-16
	ISFOLDER Function	228-16
	LINK Procedures	228-16
	LOCKRESOURCE Function	228-17
	PROCESSLINKS Procedure	228-18
	PURGERESOURCEMETADATA Procedure	228-18
	RENAMERESOURCE Procedure	228-18
	SETACL Procedure	228-19
	SPLITPATH Procedure	228-19
	TOUCHRESOURCE Procedure	228-20
	UNLOCKRESOURCE Function	228-20
	UPDATERESOURCEMETADATA Procedures	228-20
229	DBMS_XDB_VERSION	
	DBMS_XDB_VERSION Security Model	229-1
	Summary of DBMS_XDB_VERSION Subprograms	229-1
	CHECKIN Function	229-2
	CHECKOUT Procedure	229-3
	GETCONTENTSBLOBBYRESID Function	229-3
	GETCONTENTSCLOBBYRESID Function	229-3
	GETCONTENTSXMLBYRESID Function	229-4
	GETPREDECESSORS Function	229-4
	GETPREDSBYRESID Function	229-5
	GETRESOURCEBYRESID Function	229-5



	GETSUCCESSORS Function	229-5
	GETSUCCSBYRESID Function	229-6
	MAKEVERSIONED Function	229-6
	UNCHECKOUT Function	229-7
230	DBMS_XDBRESOURCE	
	DBMS_XDBRESOURCE Overview	230-1
	DBMS_XDBRESOURCE Security Model	230-1
	Summary of DBMS_XDBRESOURCE Subprograms	230-1
	FREERESOURCE Procedure	230-3
	GETACL Function	230-4
	GETACLDOCFROMRES Function	230-4
	GETAUTHOR Function	230-4
	GETCHARACTERSET Function	230-5
	GETCOMMENT Function	230-5
	GETCONTENTBLOB Function	230-5
	GETCONTENTCLOB Function	230-6
	GETCONTENTREF Function	230-6
	GETCONTENTTYPE Function	230-6
	GETCONTENTXML Function	230-7
	GETCONTENTVARCHAR2 Function	230-7
	GETCREATIONDATE Function	230-7
	GETCREATOR Function	230-8
	GETCUSTOMMETADATA Function	230-8
	GETDISPLAYNAME Function	230-9
	GETLANGUAGE Function	230-9
	GETLASTMODIFIER Function	230-9
	GETMODIFICATIONDATE Function	230-10
	GETOWNER Function	230-10
	GETREFCOUNT Function	230-10
	GETVERSIONID Function	230-11
	HASACLCHANGED Function	230-11
	HASAUTHORCHANGED Function	230-11
	HASCHANGED Function	230-12
	HASCHARACTERSETCHANGED Function	230-12
	HASCOMMENTCHANGED Function	230-12
	HASCONTENTCHANGED Function	230-13
	HASCONTENTTYPECHANGED Function	230-13
	HASCREATIONDATECHANGED Function	230-14
	HASCREATORCHANGED Function	230-14
	HASCUSTOMMETADATACHANGED Function	230-14



	HASDISPLAYNAMECHANGED Function	230-15
	HASLANGUAGECHANGED Function	230-15
	HASLASTMODIFIERCHANGED Function	230-15
	HASMODIFICATIONDATECHANGED Function	230-16
	HASOWNERCHANGED Function	230-16
	HASREFCOUNTCHANGED Function	230-17
	HASVERSIONIDCHANGED Function	230-17
	ISFOLDER Function	230-17
	ISNULL Function	230-18
	MAKEDOCUMENT Function	230-18
	SAVE Procedure	230-19
	SETACL Procedure	230-19
	SETAUTHOR Procedure	230-19
	SETCHARACTERSET Procedure	230-20
	SETCOMMENT Procedure	230-20
	SETCONTENT Procedures	230-20
	SETCONTENTTYPE Procedure	230-21
	SETCUSTOMMETADATA Procedure	230-21
	SETDISPLAYNAME Procedure	230-22
	SETLANGUAGE Procedure	230-22
	SETOWNER Procedure	230-23
221	DDMC VDD7	
231	DBMS_XDBZ	
	DBMS_XDBZ Security Model	231-1
	DBMS_XDBZ Constants	231-1
	Summary of DBMS_XDBZ Subprograms	231-2
	CREATENONCEKEY Procedure	231-2
	DISABLE_HIERARCHY Procedure	231-3
	ENABLE_HIERARCHY Procedure	231-3
	GET_ACLOID Function	231-4
	GET_USERID Function	231-4
	IS_HIERARCHY_ENABLED Function	231-5
	PURGELDAPCACHE Function	231-6
232	DBMS_XEVENT	
	DBMS_XEVENT Security Model	232-1
	DBMS_XEVENT Constants	232-1
	Subprogram Groups	232-2
	DBMS_XEVENT XDBEvent Type Subprograms	232-2
	DBMS_XEVENT XDBRepositoryEvent Type Subprograms	232-3



DBMS_XEVENT XDBHandlerList Type Subprograms	232-4
DBMS_XEVENT XDBHandler Type Subprograms	232-4
DBMS_XEVENT XDBPath Type Subprograms	232-5
DBMS_XEVENT XDBLink Type Subprograms	232-5
Summary of DBMS_XEVENT Subprograms	232-5
CLEAR Procedure	232-7
GETAPPLICATIONDATA Function	232-8
GETCHILDOID Function	232-8
GETCURRENTUSER Function	232-9
GETEVENT Function	232-9
GETFIRST Function	232-10
GETHANDLERLIST Function	232-10
GETINTERFACE Function	232-11
GETLANGUAGE Function	232-11
GETLINK Function	232-12
GETLINKNAME Function	232-12
GETLOCK Function	232-13
GETLANGUAGE Function	232-13
GETNAME Function	232-14
GETNEXT Function	232-14
GETOLDRESOURCE Function	232-15
GETOPENACCESSMODE Function	232-15
GETOPENDENYMODE Function	232-16
GETOUTPUTSTREAM Function	232-16
GETPARAMETER Function	232-17
GETPARENT Function	232-17
GETPARENTNAME Function	232-18
GETPARENTOID Function	232-18
GETPARENTPATH Function	232-19
GETPATH Function	232-19
GETRESOURCE Function	232-20
GETSCHEMA Function	232-20
GETSOURCE Function	232-21
GETUPDATEBYTECOUNT Function	232-21
GETUPDATEBYTEOFFSET Function	232-22
GETXDBEVENT Function	232-22
ISNULL Functions	232-23
REMOVE Procedure	232-24
SETRENDERPATH Procedure	232-24
SETRENDERSTREAM Procedure	232-25



233 DBMS_XMLDOM

DBMS_XMLDOM Overview	233-1
DBMS_XMLDOM Security Model	233-2
DBMS_XMLDOM Constants	233-3
DBMS_XMLDOM Types	233-3
DBMS_XMLDOM Exceptions	233-4
DBMS_XMLDOM Subprogram Groups	233-4
DBMS_XMLDOM DOMNode Subprograms	233-5
DBMS_XMLDOM DOMAttr Subprograms	233-6
DBMS_XMLDOM DOMCDataSection Subprograms	233-7
DBMS_XMLDOM DOMCharacterData Subprograms	233-7
DBMS_XMLDOM DOMComment Subprograms	233-8
DBMS_XMLDOM DOMDocument Subprograms	233-8
DBMS_XMLDOM DOMDocumentFragment Subprograms	233-9
DBMS_XMLDOM DOMDocumentType Subprograms	233-9
DBMS_XMLDOM DOMElement Subprograms	233-10
DBMS_XMLDOM DOMEntity Subprograms	233-10
DBMS_XMLDOM DOMEntityReference Subprograms	233-11
DBMS_XMLDOM DOMImplementation Subprograms	233-11
DBMS_XMLDOM DOMNamedNodeMap Subprograms	233-11
DBMS_XMLDOM DOMNodeList Subprograms	233-12
DBMS_XMLDOM DOMNotation Subprograms	233-12
DBMS_XMLDOM DOMProcessingInstruction Subprograms	233-12
DBMS_XMLDOM DOMText Subprograms	233-12
Summary of DBMS_XMLDOM Subprograms	233-13
ADOPTNODE Function	233-20
APPENDCHILD Function	233-20
APPENDDATA Procedure	233-21
CLONENODE Function	233-21
CREATEATTRIBUTE Functions	233-22
CREATECDATASECTION Function	233-23
CREATECOMMENT Function	233-23
CREATEDOCUMENT Function	233-24
CREATEDOCUMENTFRAGMENT Function	233-24
CREATEELEMENT Functions	233-25
CREATEENTITYREFERENCE Function	233-26
CREATEPROCESSINGINSTRUCTION Function	233-26
CREATETEXTNODE Function	233-27
DELETEDATA Procedure	233-27
FINDENTITY Function	233-28
FINDNOTATION Function	233-28



FREEDOCFRAG Procedure	233-29
FREEDOCUMENT Procedure	233-29
FREEELEMENT Procedure	233-30
FREENODE Procedure	233-30
FREENODELIST Procedure	233-31
GETATTRIBUTE Functions	233-31
GETATTRIBUTENODE Functions	233-32
GETATTRIBUTES Function	233-33
GETCHARSET Function	233-33
GETCHILDNODES Function	233-34
GETCHILDRENBYTAGNAME Functions	233-34
GETDATA Functions	233-35
GETDOCTYPE Function	233-35
GETDOCUMENTELEMENT Function	233-36
GETELEMENTSBYTAGNAME Functions	233-36
GETENTITIES Function	233-37
GETEXPANDEDNAME Procedure and Functions	233-38
GETFIRSTCHILD Function	233-38
GETIMPLEMENTATION Function	233-39
GETLASTCHILD Function	233-39
GETLENGTH Functions	233-40
GETLOCALNAME Procedure and Functions	233-40
GETNAME Functions	233-41
GETNAMEDITEM Function	233-42
GETNAMESPACE Procedure and Functions	233-42
GETNEXTSIBLING Function	233-43
GETNODETYPE Function	233-43
GETNODENAME Function	233-44
GETNODEVALUE Function	233-44
GETNODEVALUEASBINARYSTREAM Function & Procedure	233-45
GETNODEVALUEASCHARACTERSTREAM Function & Procedure	233-45
GETNOTATIONNAME Function	233-46
GETNOTATIONS Function	233-47
GETTARGET Function	233-47
GETOWNERDOCUMENT Function	233-48
GETOWNERELEMENT Function	233-48
GETPARENTNODE Function	233-49
GETPREFIX Function	233-49
GETPREVIOUSSIBLING Function	233-50
GETPUBLICID Functions	233-50
GETQUALIFIEDNAME Functions	233-51
GETSCHEMANODE Function	233-51



GETSPECIFIED Function	233-52
GETSTANDALONE Function	233-52
GETSYSTEMID Functions	233-53
GETTAGNAME Function	233-53
GETVALUE Function	233-54
GETVERSION Function	233-54
GETXMLTYPE Function	233-55
HASATTRIBUTE Functions	233-55
HASATTRIBUTES Function	233-56
HASCHILDNODES Function	233-56
HASFEATURE Function	233-57
IMPORTNODE Function	233-57
INSERTBEFORE Function	233-58
INSERTDATA Procedure	233-59
ISNULL Functions	233-59
ITEM Functions	233-62
MAKEATTR Function	233-63
MAKECDATASECTION Function	233-63
MAKECHARACTERDATA Function	233-64
MAKECOMMENT Function	233-64
MAKEDOCUMENT Function	233-65
MAKEDOCUMENTFRAGMENT Function	233-65
MAKEDOCUMENTTYPE Function	233-66
MAKEELEMENT Function	233-66
MAKEENTITY Function	233-67
MAKEENTITYREFERENCE Function	233-67
MAKENODE Functions	233-68
MAKENOTATION Function	233-70
MAKEPROCESSINGINSTRUCTION Function	233-70
MAKETEXT Function	233-71
NEWDOMDOCUMENT Functions	233-71
NORMALIZE Procedure	233-72
REMOVEATTRIBUTE Procedures	233-72
REMOVEATTRIBUTENODE Function	233-73
REMOVECHILD Function	233-74
REMOVENAMEDITEM Function	233-74
REPLACECHILD Function	233-75
REPLACEDATA Procedure	233-76
RESOLVENAMESPACEPREFIX Function	233-76
SETATTRIBUTE Procedures	233-77
SETATTRIBUTENODE Functions	233-78
SETCHARSET Procedure	233-78



	SETDOCTYPE Procedure	233-79
	SETNAMEDITEM Function	233-80
	SETNODEVALUE Procedure	233-81
	SETNODEVALUEASBINARYSTREAM Function & Procedure	233-81
	SETNODEVALUEASCHARACTERSTREAM Function & Procedure	233-82
	SETPREFIX Procedure	233-83
	SETSTANDALONE Procedure	233-83
	SETVALUE Procedure	233-84
	SETVERSION Procedure	233-84
	SPLITTEXT Function	233-85
	SUBSTRINGDATA Function	233-85
	USEBINARYSTREAM Function	233-86
	WRITETOBUFFER Procedures	233-86
	WRITETOCLOB Procedures	233-87
	WRITETOFILE Procedures	233-88
234	DBMS_XMLGEN	
	DBMS_XMLGEN Security Model	234-1
	Summary of DBMS_XMLGEN Subprograms	234-1
	CLOSECONTEXT Procedure	234-2
	CONVERT Functions	234-3
	GETNUMROWSPROCESSED Function	234-3
	GETXML Functions	234-4
	GETXMLTYPE Functions	234-5
	NEWCONTEXT Functions	234-6
	NEWCONTEXTFROMHIERARCHY Function	234-6
	RESTARTQUERY Procedure	234-7
	SETCONVERTSPECIALCHARS Procedure	234-7
	SETMAXROWS Procedure	234-8
	SETNULLHANDLING Procedure	234-8
	SETROWSETTAG Procedure	234-9
	SETROWTAG Procedure	234-9
	SETSKIPROWS Procedure	234-10
	USEITEMTAGSFORCOLL Procedure	234-10
	USENULLATTRIBUTEINDICATOR Procedure	234-11
235	DBMS_XMLINDEX	
	DBMS_XMLINDEX Overview	235-1
	DBMS_XMLINDEX Security Model	235-1

SETDATA Procedures



233-79

	Summary of DBMS_XMLINDEX Subprograms	235-1
	CREATEDATEINDEX Procedure	235-2
	CREATENUMBERINDEX Procedure	235-3
	DROPPARAMETER Procedure	235-3
	MODIFYPARAMETER Procedure	235-4
	PROCESS_PENDING Procedure	235-4
	REGISTERPARAMETER Procedure	235-5
	SYNCINDEX Procedure	235-6
236	DBMS_XMLPARSER	
	DBMS_XMLPARSER Security Model	236-1
	Summary of DBMS_XMLPARSER Subprograms	236-1
	FREEPARSER	236-2
	GETDOCTYPE	236-3
	GETDOCUMENT	236-3
	GETRELEASEVERSION	236-3
	GETVALIDATIONMODE	236-4
	NEWPARSER	236-4
	PARSE	236-4
	PARSEBUFFER	236-5
	PARSECLOB	236-5
	PARSEDTD	236-6
	PARSEDTDBUFFER	236-6
	PARSEDTDCLOB	236-7
	SETBASEDIR	236-7
	SETDOCTYPE Procedure	236-8
	SETERRORLOG Procedure	236-8
	SETPRESERVEWHITESPACE	236-8
	SETVALIDATIONMODE	236-9
	SHOWWARNINGS	236-9
237	DBMS_XMLSCHEMA	
	DBMS_XMLSCHEMA Overview	237-1
	DBMS_XMLSCHEMA Security Model	237-1
	DBMS_XMLSCHEMA Constants	237-1
	Views	237-3
	DBMS_XMLSCHEMA Operational Notes	237-4
	Summary of DBMS_XMLSCHEMA Subprograms	237-4
	COMPILESCHEMA Procedure	237-5
	COPYEVOLVE Procedure	237-5



	DELETESCHEMA Procedure	237-7
	INPLACEEVOLVE Procedure	237-8
	PURGESCHEMA Procedure	237-10
	REGISTERSCHEMA Procedures	237-10
	REGISTERURI Procedure	237-14
238	DBMS_XMLSCHEMA_ANNOTATE	
230		
	DBMS_XMLSCHEMA_ANNOTATE Overview	238-1
	DBMS_XMLSCHEMA_ANNOTATE Security Model	238-1
	Summary of DBMS_XMLSCHEMA_ANNOTATE Subprograms	238-1
	ADDXDBNAMESPACE Procedure	238-3
	DISABLEDEFAULTTABLECREATION Procedure	238-3
	DISABLEMAINTAINDOM Procedure	238-4
	ENABLEDEFAULTTABLECREATION Procedure	238-4
	ENABLEMAINTAINDOM Procedure	238-5
	GETSCHEMAANNOTATIONS Function	238-5
	GETSIDXDEFFROMVIEW Function	238-6
	PRINTWARNINGS Procedure	238-7
	REMOVEANYSTORAGE Procedure	238-7
	REMOVEDEFAULTTABLE Procedure	238-8
	REMOVEMAINTAINDOM Procedure	238-8
	REMOVEOUTOFLINE Procedure	238-9
	REMOVESQLCOLLTYPE Procedure	238-10
	REMOVESQLNAME Procedure	238-10
	REMOVESQLTYPE Procedure	238-11
	REMOVESQLTYPEMAPPING Procedure	238-12
	REMOVETABLEPROPS Procedure	238-12
	REMOVETIMESTAMPWITHTIMEZONE Procedure	238-13
	SETANYSTORAGE Procedure	238-14
	SETDEFAULTTABLE Procedure	238-14
	SETOUTOFLINE Procedure	238-15
	SETSCHEMAANNOTATATIONS Procedure	238-17
	SETSQLCOLLTYPE Procedure	238-18
	SETSQLNAME Procedure	238-19
	SETSQLTYPE Procedure	238-19
	SETSQLTYPEMAPPING Procedure	238-21
	SETTABLEPROPS Procedure	238-21
	SETTIMESTAMPWITHTIMEZONE Procedure	238-22



239 DBMS_XMLSCHEMA_UTIL

	DBMS_XMLSCHEMA_UTIL Security Model	239-1
	Summary of DBMS_XMLSCHEMA_UTIL Subprograms	239-1
	CONFORMING Functions	239-1
	VALIDATE Procedures	239-3
240	DBMS_XMLSTORAGE_MANAGE	
	DBMS_XMLSTORAGE_MANAGE Overview	240-1
	DBMS_XMLSTORAGE_MANAGE Security Model	240-1
	Summary of DBMS_XMLSTORAGE_MANAGE Subprograms	240-1
	DISABLEINDEXESANDCONSTRAINTS Procedure	240-2
	ENABLEINDEXESANDCONSTRAINTS Procedure	240-4
	EXCHANGEPOSTPROC Procedure	240-5
	EXCHANGEPREPROC Procedure	240-5
	INDEXXMLREFERENCES Procedure	240-5
	REFPARTITIONEXCHANGEIN Procedure	240-6
	REFPARTITIONEXCHANGEOUT Procedure	240-7
	RENAMECOLLECTIONTABLE Procedure	240-8
	SCOPEXMLREFERENCES Procedure	240-10
	XPATH2TABCOLMAPPING Function	240-10
241	DBMS_XMLSTORE	
	DBMS_XMLSTORE Security Model	241-1
	Types	241-1
	Summary of DBMS_XMLSTORE Subprograms	241-2
	CLEARKEYCOLUMNLIST	241-2
	CLEARUPDATECOLUMNLIST	241-2
	CLOSECONTEXT	241-3
	DELETEXML	241-3
	INSERTXML	241-4
	NEWCONTEXT	241-4
	SETKEYCOLUMN	241-5
	SETROWTAG	241-5
	SETUPDATECOLUMN	241-5
	UPDATEXML	241-6
242	DBMS_XPLAN	
	DBMS_XPLAN Overview	242-1
	DBMS_XPLAN Security Model	242-2



	DBMS_XPLAN Data Structures	242-2
	DBMS_XPLAN PLAN_OBJECT_LIST Table Type	242-2
	Examples	242-4
	Summary of DBMS_XPLAN Subprograms	242-7
	COMPARE_PLANS Function	242-7
DIFF_PLAN Function	242-9	
	DISPLAY Function	242-10
	DISPLAY_AWR Function	242-12
	DISPLAY_CURSOR Function	242-15
	DISPLAY_PLAN Function	242-18
	DISPLAY_SQL_PLAN_BASELINE Function	242-20
	DISPLAY_SQLSET Function	242-21
	DISPLAY_WORKLOAD_REPOSITORY Function	242-25
243	DBMS_XSLPROCESSOR	
	DBMS_XSLPROCESSOR Overview	243-1
	DBMS_XSLPROCESSOR Security Model	243-1
	Summary of DBMS_XSLPROCESSOR Subprograms	243-2
	FREEPROCESSOR Procedure	243-2
	FREESTYLESHEET Procedure	243-2
	NEWPROCESSOR Function	243-3
	NEWSTYLESHEET Functions	243-3
	PROCESSXSL Functions and Procedures	243-4
	REMOVEPARAM Procedure	243-6
	RESETPARAMS Procedure	243-6
	SELECTNODES Function	243-6
	SELECTSINGLENODE Function	243-7
	SETERRORLOG Procedure	243-7
	SETPARAM Procedure	243-8
	SHOWWARNINGS Procedure	243-8
	TRANSFORMNODE Function	243-9
	VALUEOF Function and Procedure	243-9
244	DBMS_XSTREAM_ADM	
	DBMS_XSTREAM_ADM Overview	244-1
	DBMS_XSTREAM_ADM Security Model	244-2
	DBMS_XSTREAM_ADM Operational Notes	244-2
	Summary of DBMS_XSTREAM_ADM Subprograms	244-3
	ADD_COLUMN Procedure	244-5
	ADD_GLOBAL_PROPAGATION_RULES Procedure	244-8



ADD_GLOBAL_RULES Procedure	244-12
ADD_OUTBOUND Procedure	244-16
ADD_SCHEMA_PROPAGATION_RULES Procedure	244-20
ADD_SCHEMA_RULES Procedure	244-24
ADD_SUBSET_OUTBOUND_RULES Procedure	244-28
ADD_SUBSET_PROPAGATION_RULES Procedure	244-31
ADD_SUBSET_RULES Procedure	244-34
ADD_TABLE_PROPAGATION_RULES Procedure	244-39
ADD_TABLE_RULES Procedure	244-43
ALTER_INBOUND Procedure	244-47
ALTER_OUTBOUND Procedure	244-48
CREATE_INBOUND Procedure	244-53
CREATE_OUTBOUND Procedure	244-55
DELETE_COLUMN Procedure	244-60
DROP_INBOUND Procedure	244-62
DROP_OUTBOUND Procedure	244-62
ENABLE_GG_XSTREAM_FOR_STREAMS Procedure	244-63
GET_MESSAGE_TRACKING Function	244-64
GET_TAG Function	244-65
IS_GG_XSTREAM_FOR_STREAMS Function	244-65
KEEP_COLUMNS Procedure	244-66
MERGE_STREAMS Procedure	244-68
MERGE_STREAMS_JOB Procedure	244-71
PURGE_SOURCE_CATALOG Procedure	244-74
RECOVER_OPERATION Procedure	244-75
REMOVE_QUEUE Procedure	244-77
REMOVE_RULE Procedure	244-78
REMOVE_SUBSET_OUTBOUND_RULES Procedure	244-79
REMOVE_XSTREAM_CONFIGURATION Procedure	244-80
RENAME_COLUMN Procedure	244-82
RENAME_SCHEMA Procedure	244-84
RENAME_TABLE Procedure	244-86
SET_MESSAGE_TRACKING Procedure	244-88
SET_PARAMETER Procedure	244-89
SET_TAG Procedure	244-90
SET_UP_QUEUE Procedure	244-91
SPLIT_STREAMS Procedure	244-93
START_OUTBOUND Procedure	244-97
STOP OUTBOUND Procedure	244-97



245 DEBUG_EXTPROC

	DEBUG_EXTPROC Security Model	245-1
	DEBUG_EXTPROC Operational Notes	245-1
	Rules and Limits	245-2
	Summary of DEBUG_EXTPROC Subprograms	245-2
	STARTUP_EXTPROC_AGENT Procedure	245-2
246	HTF	
	HTF Deprecated Subprograms	246-1
	HTF Operational Notes	246-1
	Rules and Limits	246-2
	HTF Examples	246-2
	Summary of Tags	246-2
	Summary of HTF Subprograms	246-5
	ADDRESS Function	246-11
	ANCHOR Function	246-12
	ANCHOR2 Function	246-12
	APPLETCLOSE Function	246-13
	APPLETOPEN Function	246-13
	AREA Function	246-14
	BASE Function	246-15
	BASEFONT Function	246-15
	BGSOUND Function	246-16
	BIG Function	246-16
	BLOCKQUOTECLOSE Function	246-17
	BLOCKQUOTEOPEN Function	246-17
	BODYCLOSE Function	246-18
	BODYOPEN Function	246-18
	BOLD Function	246-19
	BR Function	246-19
	CENTER Function	246-20
	CENTERCLOSE Function	246-20
	CENTEROPEN Function	246-20
	CITE Function	246-21
	CODE Function	246-21
	COMMENT Function	246-22
	DFN Function	246-22
	DIRLISTCLOSE Function	246-23
	DIRLISTOPEN Function	246-23
	DIV Function	246-24



DLISTCLOSE Function	246-24
DLISTDEF Function	246-25
DLISTOPEN Function	246-25
DLISTTERM Function	246-26
EM Function	246-26
EMPHASIS Function	246-27
ESCAPE_SC Function	246-27
ESCAPE_URL Function	246-28
FONTCLOSE Function	246-29
FONTOPEN Function	246-29
FORMAT_CELL Function	246-30
FORMCHECKBOX Function	246-30
FORMCLOSE Function	246-31
FORMFILE Function	246-31
FORMHIDDEN Function	246-32
FORMIMAGE Function	246-32
FORMOPEN Function	246-33
FORMPASSWORD Function	246-34
FORMRADIO Function	246-34
FORMRESET Function	246-35
FORMSELECTCLOSE Function	246-35
FORMSELECTOPEN Function	246-36
FORMSELECTOPTION Function	246-37
FORMSUBMIT Function	246-37
FORMTEXT Function	246-38
FORMTEXTAREA Function	246-38
FORMTEXTAREA2 Function	246-39
FORMTEXTAREACLOSE Function	246-40
FORMTEXTAREAOPEN Function	246-40
FORMTEXTAREAOPEN2 Function	246-41
FRAME Function	246-42
FRAMESETCLOSE Function	246-42
FRAMESETOPEN Function	246-43
HEADCLOSE Function	246-43
HEADER Function	246-44
HEADOPEN Function	246-44
HR Function	246-45
HTMLCLOSE Function	246-45
HTMLOPEN Function	246-45
IMG Function	246-46
IMG2 Function	246-46
ISINDEX Function	246-47



ITALIC Function	246-48
KBD Function	246-48
KEYBOARD Function	246-49
LINE Function	246-49
LINKREL Function	246-50
LINKREV Function	246-50
LISTHEADER Function	246-51
LISTINGCLOSE Function	246-52
LISTINGOPEN Function	246-52
LISTITEM Function	246-52
MAILTO Function	246-53
MAPCLOSE Function	246-54
MAPOPEN Function	246-54
MENULISTCLOSE Function	246-54
MENULISTOPEN Function	246-55
META Function	246-55
NL Function	246-56
NOBR Function	246-56
NOFRAMESCLOSE Function	246-57
NOFRAMESOPEN Function	246-57
OLISTCLOSE Function	246-57
OLISTOPEN Function	246-58
PARA Function	246-58
PARAGRAPH Function	246-59
PARAM Function	246-59
PLAINTEXT Function	246-60
PRECLOSE Function	246-60
PREOPEN Function	246-61
PRINT Functions	246-61
PRN Functions	246-62
S Function	246-63
SAMPLE Function	246-63
SCRIPT Function	246-64
SMALL Function	246-64
STRIKE Function	246-65
STRONG Function	246-65
STYLE Function	246-66
SUB Function	246-66
SUP Function	246-67
TABLECAPTION Function	246-67
TABLECLOSE Function	246-68
TABLEDATA Function	246-68



	TABLEOPEN Function	246-70
	TABLEROWCLOSE Function	246-70
	TABLEROWOPEN Function	246-71
	TELETYPE Function	246-71
	TITLE Function	246-72
	ULISTCLOSE Function	246-72
	ULISTOPEN Function	246-73
	UNDERLINE Function	246-73
	VARIABLE Function	246-74
	WBR Function	246-74
247	HTP	
	HTP Operational Notes	247-1
	HTP Rules and Limits	247-2
	HTP Examples	247-2
	HTP Summary of Tags	247-2
	Summary of HTP Subprograms	247-5
	ADDRESS Procedure	247-11
	ANCHOR Procedure	247-11
	ANCHOR2 Procedure	247-12
	APPLETCLOSE Procedure	247-13
	APPLETOPEN Procedure	247-13
	AREA Procedure	247-14
	BASE Procedure	247-15
	BASEFONT Procedure	247-15
	BGSOUND Procedure	247-16
	BIG Procedure	247-16
	BLOCKQUOTECLOSE Procedure	247-17
	BLOCKQUOTEOPEN Procedure	247-17
	BODYCLOSE Procedure	247-17
	BODYOPEN Procedure	247-18
	BOLD Procedure	247-18
	BR Procedure	247-19
	CENTER Procedure	247-19
	CENTERCLOSE Procedure	247-20
	CENTEROPEN Procedure	247-20
	CITE Procedure	247-20
	CODE Procedure	247-21
	COMMENT Procedure	247-21
	DFN Procedure	247-22

TABLEHEADER Function



246-69

DIRLISTCLOSE Procedure	247-22
DIRLISTOPEN Procedure	247-23
DIV Procedure	247-23
DLISTCLOSE Procedure	247-24
DLISTDEF Procedure	247-24
DLISTOPEN Procedure	247-25
DLISTTERM Procedure	247-25
EM Procedure	247-26
EMPHASIS Procedure	247-26
ESCAPE_SC Procedure	247-27
FONTCLOSE Procedure	247-27
FONTOPEN Procedure	247-28
FORMCHECKBOX Procedure	247-28
FORMCLOSE Procedure	247-29
FORMOPEN Procedure	247-29
FORMFILE Procedure	247-30
FORMHIDDEN Procedure	247-30
FORMIMAGE Procedure	247-31
FORMPASSWORD Procedure	247-32
FORMRADIO Procedure	247-32
FORMRESET Procedure	247-33
FORMSELECTCLOSE Procedure	247-33
FORMSELECTOPEN Procedure	247-34
FORMSELECTOPTION Procedure	247-35
FORMSUBMIT Procedure	247-35
FORMTEXT Procedure	247-36
FORMTEXTAREA Procedure	247-36
FORMTEXTAREA2 Procedure	247-37
FORMTEXTAREACLOSE Procedure	247-38
FORMTEXTAREAOPEN Procedure	247-38
FORMTEXTAREAOPEN2 Procedure	247-39
FRAME Procedure	247-39
FRAMESETCLOSE Procedure	247-40
FRAMESETOPEN Procedure	247-40
HEADCLOSE Procedure	247-41
HEADER Procedure	247-41
HEADOPEN Procedure	247-42
HR Procedure	247-42
HTMLCLOSE Procedure	247-43
HTMLOPEN Procedure	247-43
IMG Procedure	247-43
IMG2 Procedure	247-44



ISINDEX Procedure	247-45
ITALIC Procedure	247-45
KBD Procedure	247-46
KEYBOARD Procedure	247-46
LINE Procedure	247-47
LINKREL Procedure	247-47
LINKREV Procedure	247-48
LISTHEADER Procedure	247-49
LISTINGCLOSE Procedure	247-49
LISTINGOPEN Procedure	247-49
LISTITEM Procedure	247-50
MAILTO Procedure	247-50
MAPCLOSE Procedure	247-51
MAPOPEN Procedure	247-51
MENULISTCLOSE Procedure	247-52
MENULISTOPEN Procedure	247-52
META Procedure	247-53
NL Procedure	247-53
NOBR Procedure	247-54
NOFRAMESCLOSE Procedure	247-54
NOFRAMESOPEN Procedure	247-55
OLISTCLOSE Procedure	247-55
OLISTOPEN Procedure	247-55
PARA Procedure	247-56
PARAGRAPH Procedure	247-56
PARAM Procedure	247-57
PLAINTEXT Procedure	247-57
PRECLOSE Procedure	247-58
PREOPEN Procedure	247-58
PRINT Procedures	247-59
PRINTS Procedure	247-59
PRN Procedures	247-60
PS Procedure	247-61
S Procedure	247-61
SAMPLE Procedure	247-62
SCRIPT Procedure	247-62
SMALL Procedure	247-63
STRIKE Procedure	247-64
STRONG Procedure	247-64
STYLE Procedure	247-65
SUB Procedure	247-65
SUP Procedure	247-66



	TABLECAPTION Procedure	247-66
	TABLECLOSE Procedure	247-67
	TABLEDATA Procedure	247-67
	TABLEHEADER Procedure	247-68
	TABLEOPEN Procedure	247-68
	TABLEROWCLOSE Procedure	247-69
	TABLEROWOPEN Procedure	247-69
	TELETYPE Procedure	247-70
	TITLE Procedure	247-70
	ULISTCLOSE Procedure	247-71
	ULISTOPEN Procedure	247-71
	UNDERLINE Procedure	247-72
	VARIABLE Procedure	247-72
	WBR Procedure	247-73
248	OWA_CACHE	
	OWA CACHE Constants	248-1
	Summary of OWA_CACHE Subprograms	248-1
	DISABLE Procedure	248-2
	GET_ETAG Function	248-2
	GET_LEVEL Function	248-2
	SET CACHE Procedure	248-2
	SET_EXPIRES Procedure	248-3
	SET_NOT_MODIFIED Procedure	248-3
	SET_SURROGATE_CONTROL Procedure	248-4
249	OWA_COOKIE	
	OWA_CUSTOM Overview	249-1
	OWA_COOKIE Types	249-1
	OWA_COOKIE Rules and Limits	249-1
	Summary of OWA_COOKIE Subprograms	249-2
	GET Function	249-2
	GET_ALL Procedure	249-2
	REMOVE Procedure	249-3
	SEND procedure	249-3
250	OWA_CUSTOM	
	OWA_CUSTOM Constants	250-1
	Summary of OWA_CUSTOM Subprograms	250-1



AUTHORIZE Function 250-1

	OWA_IMAGE	OWA_IMAGE		
	OWA_IMAGE Overview	251-1		
	OWA_IMAGE Types	251-1		
	OWA_IMAGE Variables	251-1		
	OWA_IMAGE Examples	251-2		
	Summary of OWA_IMAGE Subprograms	251-2		
	GET_X Function	251-2		
	GET_Y Function	251-3		
252	OWA_OPT_LOCK			
	OWA_OPT_LOCK Overview	252-1		
	OWA_TEXT Types	252-1		
	Summary of OWA_OPT_LOCK Subprograms	252-2		
	CHECKSUM Functions	252-2		
	GET_ROWID Function	252-3		
	STORE_VALUES Procedure	252-3		
	VERIFY_VALUES Function	252-4		
253	OWA_PATTERN			
	OWA_PATTERN Types	253-1		
	OWA_PATTERN Operational Notes	253-1		
	OWA_PATTERN Wildcards	253-2		
	OWA_PATTERN Quantifiers	253-2		
	OWA_PATTERN Flags	253-3		
	Summary of OWA_PATTERN Subprograms	253-3		
	AMATCH Function	253-3		
	CHANGE Functions and Procedures	253-5		
	GETPAT Procedure	253-6		
	MATCH Function	253-6		
254	OWA_SEC			
254	ONIA CEO Oceandianal Nata			
204	OWA_SEC Operational Notes	254-1		
2 34	Summary of OWA_SEC Subprograms			
2 34		254-1		
2 J4	Summary of OWA_SEC Subprograms	254-1 254-1 254-1 254-2 254-2		



	GET_USER_ID Function	254-2
	SET_AUTHORIZATION Procedure	254-3
	SET_PROTECTION_REALM Procedure	254-4
255	OWA_TEXT	
	OWA_OPT_LOCK Types	255-1
	MULTI_LINE DATA TYPE	255-1
	ROW_LIST DATA TYPE	255-1
	VC_ARR DATA TYPE	255-2
	Summary of OWA_TEXT Subprograms	255-2
	ADD2MULTI Procedure	255-2
	NEW_ROW_LIST Function and Procedure	255-3
	PRINT_MULTI Procedure	255-3
	PRINT_ROW_LIST Procedure	255-4
	STREAM2MULTI Procedure	255-4
256	OWA_UTIL	
	OWA_UTIL Overview	256-1
	OWA_UTIL Types	256-1
	DATETYPE Datatype	256-1
	IDENT_ARR Datatype	256-2
	IP_ADDRESS Datatype	256-2
	Summary of OWA_UTIL Subprograms	256-2
	BIND_VARIABLES Function	256-3
	CALENDARPRINT Procedures	256-3
	CELLSPRINT Procedures	256-4
	CHOOSE_DATE Procedure	256-6
	GET_CGI_ENV Function	256-7
	GET_OWA_SERVICE_PATH Function	256-7
	GET_PROCEDURE Function	256-8
	HTTP_HEADER_CLOSE Procedure	256-8
	LISTPRINT Procedure	256-8
	MIME_HEADER Procedure	256-9
	PRINT_CGI_ENV Procedure	256-10
	REDIRECT_URL Procedure	256-10
	SHOWPAGE Procedure	256-11
	SHOWSOURCE Procedure	256-12
	SIGNATURE procedure	256-12
	STATUS_LINE Procedure	256-13
	TABLEPRINT Function	256-13



257	SDO_CS
258	SDO_CSW_PROCESS
259	SDO_GCDR
260	SDO_GEOM
261	SDO_GEOR
262	SDO_GEOR_ADMIN
263	SDO_GEOR_AGGR
264	SDO_GEOR_RA
265	SDO_GEOR_UTL
266	SDO_LRS

267	SDO_MIGRATE
268	SDO_NET
269	SDO_NFE
270	SDO_OLS
074	
2/1	SDO_PC_PKG
272	SDO_SAM
212	SDO_SAIVI
273	SDO_TIN_PKG
274	SDO_TOPO
275	SDO_TOPO_MAP
276	SDO_TUNE
277	SDO_UTIL

278	SDO_WFS_LOCK	
279	SDO_WFS_PROCESS	
280	SEM_APIS	
281	SEM_OLS	
282	SEM_PERF	
283	SEM_RDFCTX	
284	SEM_RDFSA	
285	UTL_CALL_STACK	
	UTL_CALL_STACK Overview	285-1
	UTL_CALL_STACK Security Model	285-2
	UTL_CALL_STACK Operational Notes	285-3
	UTL_CALL_STACK Exceptions	285-3
	UTL_CALL_STACK Data Structures	285-3
	UNIT_QUALIFIED_NAME	285-3
	Summary of UTL_CALL_STACK Subprograms	285-4
	BACKTRACE_DEPTH Function	285-4
	BACKTRACE_LINE Function	285-5
	BACKTRACE_UNIT Function CURRENT_EDITION Function	285-5 285-5
	CONCATENATE SUBPROGRAM Function	285-6
	DYNAMIC_DEPTH Function	285-6
	ERROR_DEPTH Function	285-6
	ERROR_MSG Function	285-7



	ERROR_NUMBER Function	285-7
	LEXICAL_DEPTH Function	285-8
	OWNER Function	285-8
	UNIT_LINE Function	285-8
	SUBPROGRAM Function	285-9
286	UTL_COLL	
	Summary of UTL_COLL Subprograms	286-1
	IS_LOCATOR Function	286-1
287	UTL_COMPRESS	
	UTL_COMPRESS Constants	287-1
	UTL_COMPRESS Exceptions	287-1
	UTL_COMPRESS Operational Notes	287-1
	Summary of UTL_COMPRESS Subprograms	287-2
	ISOPEN Function	287-2
	LZ_COMPRESS Functions and Procedures	287-3
	LZ_COMPRESS_ADD Procedure	287-4
	LZ_COMPRESS_CLOSE	287-4
	LZ_COMPRESS_OPEN	287-5
	LZ_UNCOMPRESS Functions and Procedures	287-6
	LZ_UNCOMPRESS_EXTRACT Procedure	287-6
	LZ_UNCOMPRESS_OPEN Function	287-7
	LZ_UNCOMPRESS_CLOSE Procedure	287-8
288	UTL_ENCODE	
	Summary of UTL_ENCODE Subprograms	288-1
	BASE64_DECODE Function	288-2
	BASE64_ENCODE Function	288-2
	MIMEHEADER_DECODE Function	288-3
	MIMEHEADER_ENCODE Function	288-4
	QUOTED_PRINTABLE_DECODE Function	288-5
	QUOTED_PRINTABLE_ENCODE Function	288-5
	TEXT_DECODE Function	288-6
	TEXT_ENCODE Function	288-7
	UUDECODE Function	288-8
	UUENCODE Function	288-9



289 UTL_FILE

LITE FILE Socurity Model	289-1
UTL_FILE Security Model	
UTL_FILE Operational Notes	289-2 289-3
UTL_FILE Rules and Limits	289-3
UTL_FILE Exceptions	
UTL_FILE Examples	289-4
UTL_FILE Data Structures	289-5
FILETYPE Record Type	289-5
Summary of UTL_FILE Subprograms	289-6
FCLOSE Procedure	289-7
FCLOSE_ALL Procedure	289-7
FCOPY Procedure	289-8
FFLUSH Procedure	289-8
FGETATTR Procedure	289-9
FGETPOS Function	289-10
FOPEN Function	289-10
FOPEN_NCHAR Function	289-12
FREMOVE Procedure	289-13
FRENAME Procedure	289-13
FSEEK Procedure	289-14
GET_LINE Procedure	289-15
GET_LINE_NCHAR Procedure	289-16
GET_RAW Procedure	289-17
IS_OPEN Function	289-18
NEW_LINE Procedure	289-18
PUT Procedure	289-19
PUT_LINE Procedure	289-19
PUT_LINE_NCHAR Procedure	289-20
PUT_NCHAR Procedure	289-21
PUTF Procedure	289-22
PUTF_NCHAR Procedure	289-23
PUT_RAW Procedure	289-24
UTL_HTTP	
UTL_HTTP Overview	290-1
UTL_HTTP Security Model	290-2
UTL_HTTP Constants	290-2
UTL_HTTP Exceptions	290-5
UTL_HTTP Examples	290-7
UTL_HTTP General Usage	290-7



290

UTL_HTTP Retrieving HTTP Response Headers	290-7
UTL_HTTP Handling HTTP Authentication	290-8
UTL_HTTP Handling HTTP Digest Authentication	290-9
UTL_HTTP Retrieving and Restoring Cookies	290-9
UTL_HTTP Making HTTP Request with Private Wallet and Cookie Table	290-10
UTL_HTTP Using a Proxy Server	290-11
UTL_HTTP Data Structures	290-11
REQ Type	290-12
REQUEST_CONTEXT_KEY Type	290-12
RESP Type	290-13
COOKIE and COOKIE_TABLE Types	290-13
CONNECTION Type	290-14
UTL_HTTP Operations	290-15
UTL_HTTP Operational Flow	290-15
UTL_HTTP Simple HTTP Fetches	290-18
UTL_HTTP HTTP Requests	290-18
UTL_HTTP HTTP Responses	290-19
UTL_HTTP HTTP Cookies	290-19
UTL_HTTP HTTP Persistent Connections	290-19
UTL_HTTP Error Conditions	290-20
UTL_HTTP Session Settings	290-20
UTL_HTTP Request Context	290-20
UTL_HTTP External Password Store	290-21
UTL_HTTP Subprogram Groups	290-21
UTL_HTTP Simple HTTP Fetches in a Single Call Subprograms	290-21
UTL_HTTP Session Settings Subprograms	290-21
UTL_HTTP HTTP Requests Subprograms	290-22
UTL_HTTP HTTP Request Contexts Subprograms	290-23
UTL_HTTP HTTP Responses Subprograms	290-23
UTL_HTTP HTTP Cookies Subprograms	290-24
UTL_HTTP HTTP Persistent Connections Subprograms	290-24
UTL_HTTP Error Conditions Subprograms	290-25
Summary of UTL_HTTP Subprograms	290-25
ADD_COOKIES Procedure	290-29
BEGIN_REQUEST Function	290-30
CLEAR_COOKIES Procedure	290-31
CLOSE_PERSISTENT_CONN Procedure	290-32
CLOSE_PERSISTENT_CONNS Procedure	290-32
CREATE_REQUEST_CONTEXT Function	290-33
DESTROY_REQUEST_CONTEXT Procedure	290-35
END_REQUEST Procedure	290-35
END_RESPONSE Procedure	290-36



GET_AUTHENTICATION Procedure	290-36
GET_BODY_CHARSET Procedure	290-37
GET_COOKIE_COUNT Function	290-38
GET_COOKIE_SUPPORT Procedure	290-38
GET_COOKIES Function	290-39
GET_DETAILED_EXCP_SUPPORT Procedure	290-39
GET_DETAILED_SQLCODE Function	290-40
GET_DETAILED_SQLERRM Function	290-40
GET_FOLLOW_REDIRECT Procedure	290-40
GET_HEADER Procedure	290-41
GET_HEADER_BY_NAME Procedure	290-42
GET_HEADER_COUNT Function	290-42
GET_PERSISTENT_CONN_COUNT Function	290-43
GET_PERSISTENT_CONN_SUPPORT Procedure	290-43
GET_PERSISTENT_CONNS Procedure	290-44
GET_PROXY Procedure	290-45
GET_RESPONSE Function	290-45
GET_RESPONSE_ERROR_CHECK Procedure	290-47
GET_TRANSFER_TIMEOUT Procedure	290-47
READ_LINE Procedure	290-48
READ_RAW Procedure	290-49
READ_TEXT Procedure	290-50
REQUEST Function	290-51
REQUEST_PIECES Function	290-53
SET_AUTHENTICATION Procedure	290-56
SET_AUTHENTICATION_FROM_WALLET Procedure	290-57
SET_BODY_CHARSET Procedures	290-59
SET_COOKIE_SUPPORT Procedures	290-60
SET_DETAILED_EXCP_SUPPORT Procedure	290-61
SET_FOLLOW_REDIRECT Procedures	290-62
SET_HEADER Procedure	290-63
SET_PERSISTENT_CONN_SUPPORT Procedure	290-64
SET_PROXY Procedure	290-67
SET_RESPONSE_ERROR_CHECK Procedure	290-68
SET_TRANSFER_TIMEOUT Procedure	290-68
SET_WALLET Procedure	290-69
WRITE_LINE Procedure	290-70
WRITE_RAW Procedure	290-71
WRITE_TEXT Procedure	290-72



291 UTL_I18N

UTL_I18N Overview	291-1
UTL_I18N Security Model	291-2
UTL_I18N Constants	291-2
UTL_I18N Data Structures	291-3
CHARSET_RESULT_RECORD Record Type	291-4
LANGUAGE_CHARSET_RESULT_RECORD Record Type	291-4
LANGUAGE_RESULT_RECORD Record Type	291-5
CHARSET_RESULT_TABLE Table Type	291-5
LANGUAGE_CHARSET_RESULT_TABLE Table Type	291-5
LANGUAGE_RESULT_TABLE Table Type	291-6
Summary of UTL_I18N Subprograms	291-6
DETECT_CHARSET Procedure	291-7
DETECT_LANGUAGE Procedure	291-9
DETECT_LANGUAGE_CHARSET Procedure	291-11
ESCAPE_REFERENCE Function	291-14
GET_COMMON_TIME_ZONES Function	291-15
GET_DEFAULT_CHARSET Function	291-15
GET_DEFAULT_ISO_CURRENCY Function	291-16
GET_DEFAULT_LINGUISTIC_SORT Function	291-17
GET_LOCAL_LANGUAGES Function	291-17
GET_LOCAL_LINGUISTIC_SORTS Function	291-18
GET_LOCAL_TERRITORIES Function	291-19
GET_LOCAL_TIME_ZONES Function	291-20
GET_MAX_CHARACTER_SIZE Function	291-21
GET_TRANSLATION Function	291-22
MAP_CHARSET Function	291-23
MAP_FROM_SHORT_LANGUAGE Function	291-24
MAP_LANGUAGE_FROM_ISO Function	291-25
MAP_LOCALE_TO_ISO Function	291-26
MAP_TERRITORY_FROM_ISO Function	291-27
MAP_TO_SHORT_LANGUAGE Function	291-27
RAW_TO_CHAR Functions	291-28
RAW_TO_NCHAR Functions	291-30
STRING_TO_RAW Function	291-31
TRANSLITERATE Function	291-32
UNESCAPE_REFERENCE Function	291-34
VALIDATE_CHARACTER_ENCODING Functions	291-35



292	UTL_IDENT	
	UTL_IDENT Overview	292-1
	UTL_IDENT Security Model	292-2
	UTL_IDENT Constants	292-2
293	UTL_INADDR	
	UTL_INADDR Security Model	293-1
	UTL_INADDR Exceptions	293-2
	UTL_INADDR Examples	293-2
	Summary of UTL_INADDR Subprograms	293-2
	GET_HOST_ADDRESS Function	293-2
	GET_HOST_NAME Function	293-3
294	UTL_LMS	
	UTL_LMS Security Model	294-1
	Summary of UTL_LMS Subprograms	294-2
	FORMAT_MESSAGE Function	294-2
	GET_MESSAGE Function	294-2
295	UTL_MAIL	
	UTL_MAIL Security Model	295-1
	UTL_MAIL Operational Notes	295-2
	UTL_MAIL Rules and Limits	295-2
	Summary of UTL_MAIL Subprograms	295-2
	SEND Procedure	295-2
	SEND_ATTACH_RAW Procedure	295-3
	SEND_ATTACH_VARCHAR2 Procedure	295-4
296	UTL_MATCH	
	UTL_MATCH Overview	296-2
	UTL_MATCH Security Model	296-2
	Summary of UTL_MATCH Subprograms	296-2
	EDIT_DISTANCE Function	296-2
	EDIT_DISTANCE_SIMILARITY Function	296-2
	JARO_WINKLER Function	296-3
	JARO WINKLER SIMILARITY Function	296-4



297 UTL_NLA

UTL_NLA Overview	297-1
UTL_NLA Rules and Limits	297-2
UTL_NLA Security Model	297-2
Subprogram Groups	297-2
UTL_NLA BLAS Level 1 (Vector-Vector Operations) Subprograms	297-2
UTL_NLA BLAS Level 2 (Matrix-Vector Operations) Subprograms	297-3
UTL_NLA BLAS Level 3 (Matrix-Matrix Operations) Subprograms	297-4
UTL_NLA LAPACK Driver Routines (Linear Equations) Subprograms	297-5
UTL_NLA LAPACK Driver Routines (LLS and Eigenvalue Problems) Subprograms	297-6
Summary of UTL_NLA Subprograms	297-7
BLAS_ASUM Functions	297-13
BLAS_AXPY Procedures	297-14
BLAS_COPY Procedures	297-15
BLAS_DOT Functions	297-16
BLAS_GBMV Procedures	297-17
BLAS_GEMM Procedures	297-19
BLAS_GEMV Procedures	297-21
BLAS_GER Procedures	297-23
BLAS_IAMAX Functions	297-24
BLAS_NRM2 Functions	297-25
BLAS_ROT Procedures	297-26
BLAS_ROTG Procedures	297-27
BLAS_SCAL Procedures	297-27
BLAS_SPMV Procedures	297-28
BLAS_SPR Procedures	297-30
BLAS_SPR2 Procedures	297-31
BLAS_SBMV Procedures	297-33
BLAS_SWAP Procedures	297-34
BLAS_SYMM Procedures	297-35
BLAS_SYMV Procedures	297-37
BLAS_SYR Procedures	297-39
BLAS_SYR2 Procedures	297-40
BLAS_SYR2K Procedures	297-42
BLAS_SYRK Procedures	297-44
BLAS_TBMV Procedures	297-46
BLAS_TBSV Procedures	297-48
BLAS_TPMV Procedures	297-50
BLAS_TPSV Procedures	297-51
BLAS_TRMM Procedures	297-53
BLAS_TRMV Procedures	297-55



	BLAS_TRSM Procedures	297-56
	BLAS_TRSV Procedures	297-58
	LAPACK_GBSV Procedures	297-60
	LAPACK_GEES Procedures	297-61
	LAPACK_GELS Procedures	297-63
	LAPACK_GESDD Procedures	297-65
	LAPACK_GESV Procedure	297-67
	LAPACK_GESVD Procedures	297-69
	LAPACK_GEEV Procedures	297-71
	LAPACK_GTSV Procedure	297-73
	LAPACK_PBSV Procedures	297-75
	LAPACK_POSV Procedures	297-76
	LAPACK_PPSV Procedures	297-78
	LAPACK_PTSV Procedures	297-80
	LAPACK_SBEV Procedures	297-81
	LAPACK_SBEVD Procedures	297-83
	LAPACK_SPEV Procedures	297-85
	LAPACK_SPEVD Procedures	297-86
	LAPACK_SPSV Procedures	297-88
	LAPACK_STEV Procedures	297-90
	LAPACK_STEVD Procedures	297-91
	LAPACK_SYEV Procedures	297-93
	LAPACK_SYEVD Procedures	297-94
	LAPACK_SYSV Procedures	297-95
298	UTL_RAW	
	UTL_RAW Overview	298-1
	UTL_RAW Operational Notes	298-1
	Summary of UTL_RAW Subprograms	298-1
	BIT_AND Function	298-3
	BIT_COMPLEMENT Function	298-4
	BIT_OR Function	298-4
	BIT_XOR Function	298-5
	CAST_FROM_BINARY_DOUBLE Function	298-6
	CAST_FROM_BINARY_FLOAT Function	298-7
	CAST_FROM_BINARY_INTEGER Function	298-8
	CAST_FROM_NUMBER Function	298-8
	CAST_TO_BINARY_DOUBLE Function	298-9
	CAST_TO_BINARY_FLOAT Function	298-10
	CAST_TO_BINARY_INTEGER Function	298-11
	CAST_TO_NUMBER Function	298-11



	CAST_TO_NVARCHAR2 Function	298-12
	CAST_TO_RAW Function	298-13
	CAST_TO_VARCHAR2 Function	298-13
	COMPARE Function	298-14
	CONCAT Function	298-15
	CONVERT Function	298-16
	COPIES Function	298-17
	LENGTH Function	298-18
	OVERLAY Function	298-18
	REVERSE Function	298-20
	SUBSTR Function	298-20
	TRANSLATE Function	298-21
	TRANSLITERATE Function	298-23
	XRANGE Function	298-25
299	UTL_RECOMP	
	UTL_RECOMP Overview	299-1
	UTL_RECOMP Operational Notes	299-1
	UTL_RECOMP Examples	299-2
	Summary of UTL_RECOMP Subprograms	299-2
	RECOMP_PARALLEL Procedure	299-2
	RECOMP_SERIAL Procedure	299-4
300	UTL_REF	
	UTL_REF Overview	300-1
	UTL_REF Security Model	300-1
	UTL_REF Types	300-2
	UTL_REF Exceptions	300-2
	Summary of UTL_REF Subprograms	300-3
	DELETE_OBJECT Procedure	300-3
	LOCK_OBJECT Procedure	300-4
	SELECT_OBJECT Procedure	300-5
	UPDATE_OBJECT Procedure	300-6
301	UTL_RPADV	
	UTL_RPADV Overview	301-1
	DBMS_COMPARISON Security Model	301-1
	UTL_RPADV Operational Notes	301-1
	Summary of UTL_RPADV Subprograms	301-10



	COLLECT_STATS Procedure	301-12
	IS_MONITORING Function	301-13
	SHOW_STATS Procedure	301-14
	SHOW_STATS_HTML Procedure	301-16
	START_MONITORING Procedure	301-18
	STOP_MONITORING Procedure	301-20
302	UTL_SMTP	
	UTL_SMTP Overview	302-1
	UTL_SMTP Security Model	302-2
	UTL_SMTP Constants	302-2
	UTL_SMTP Types	302-2
	UTL_SMTP Reply Codes	302-4
	UTL_SMTP Operational Notes	302-5
	UTL_SMTP Exceptions	302-5
	UTL_SMTP Rules and Limits	302-6
	UTL_SMTP Examples	302-6
	Summary of UTL_SMTP Subprograms	302-7
	AUTH Function and Procedure	302-8
	CLOSE_CONNECTION Procedure	302-9
	CLOSE_DATA Function and Procedure	302-10
	COMMAND Function and Procedure	302-10
	COMMAND_REPLIES Function	302-11
	DATA Function and Procedure	302-12
	EHLO Function and Procedure	302-13
	HELO Function and Procedure	302-14
	HELP Function	302-15
	MAIL Function and Procedure	302-15
	NOOP Function and Procedure	302-16
	OPEN_CONNECTION Functions	302-17
	OPEN_DATA Function and Procedure	302-19
	QUIT Function and Procedure	302-20
	RCPT Function	302-20
	RSET Function and Procedure	302-21
	STARTTLS Function and Procedure	302-22
	VRFY Function	302-23
	WRITE_DATA Procedure	302-24
	WRITE_RAW_DATA Procedure	302-25

ALTER_MONITORING Procedure



301-11

303 UTL_TCP

UTL_TCP Overview	303-1
UTL_TCP Security Model	303-1
UTL_TCP Types	303-1
UTL_TCP Exceptions	303-3
UTL_TCP Rules and Limits	303-3
UTL_TCP Examples	303-3
Summary of UTL_TCP Subprograms	303-4
AVAILABLE Function	303-5
CLOSE_ALL_CONNECTIONS Procedure	303-6
CLOSE_CONNECTION Procedure	303-7
FLUSH Procedure	303-7
GET_LINE Function	303-8
GET_LINE_NCHAR Function	303-8
GET_RAW Function	303-9
GET_TEXT Function	303-10
GET_TEXT_NCHAR Function	303-11
OPEN_CONNECTION Function	303-12
READ_LINE Function	303-14
READ_RAW Function	303-15
READ_TEXT Function	303-16
SECURE_CONNECTION Procedure	303-17
WRITE_LINE Function	303-17
WRITE_RAW Function	303-18
WRITE_TEXT Function	303-18
304 UTL_URL	
UTL_URL Overview	304-1
UTL_URL Exceptions	304-2
UTL_URL Examples	304-2
Summary of UTL_URL Subprograms	304-2
ESCAPE Function	304-3
UNESCAPE Function	304-4
305 WPG_DOCLOAD	
WPG_DOCLOAD Constants	305-1
Summary of WPG_DOCLOAD Subprograms	305-1
DOWNLOAD_FILE Procedures	305-2



306 ANYDATA TYPE

	ANYDATA TYPE Restrictions	306-1
	ANYDATA TYPE Operational Notes	306-1
	Summary of ANYDATA Subprograms	306-2
	BEGINCREATE Static Procedure	306-3
	ENDCREATE Member Procedure	306-3
	GET* Member Functions	306-4
	GETTYPE Member Function	306-6
	GETTYPENAME Member Function	306-7
	PIECEWISE Member Procedure	306-7
	SET* Member Procedures	306-8
307	ANYDATASET TYPE	
	ANYDATASET TYPE Construction	307-1
	Summary of ANYDATASET TYPE Subprograms	307-1
	ADDINSTANCE Member Procedure	307-2
	BEGINCREATE Static Procedure	307-3
	ENDCREATE Member Procedure	307-3
	GET* Member Functions	307-3
	GETCOUNT Member Function	307-6
	GETINSTANCE Member Function	307-6
	GETTYPE Member Function	307-7
	GETTYPENAME Member Function	307-7
	PIECEWISE Member Procedure	307-8
	SET* Member Procedures	307-9
308	ANYTYPE TYPE	
	Summary of ANYTYPE Subprograms	308-1
	BEGINCREATE Static Procedure	308-2
	SETINFO Member Procedure	308-2
	ADDATTR Member Procedure	308-3
	ENDCREATE Member Procedure	308-4
	GETINFO Member Function	308-5
	GETATTRELEMINFO Member Function	308-6
	GETANYTYPEFROMPERSISTENT Function	308-7
309	Oracle Database Advanced Queuing (AQ) Types	
	Advanced Queuing (AQ)Types Security Model	309-1
	Oracle Database Advanced Queuing (AQ) Types —Summary of Types	309-1



	AQ\$_AGENT Type	309-2
	AQ\$_AGENT_LIST_T Type	309-2
	AQ\$_DESCRIPTOR Type	309-3
	AQ\$_NTFN_DESCRIPTOR Type	309-3
	AQ\$_NTFN_MSGID_ARRAY Type	309-4
	AQ\$_POST_INFO Type	309-4
	AQ\$_POST_INFO_LIST Type	309-4
	AQ\$_PURGE_OPTIONS_T Type	309-5
	AQ\$_RECIPIENT_LIST_T Type	309-5
	AQ\$_REG_INFO Type	309-6
	AQ\$_REG_INFO_LIST Type	309-8
	AQ\$_SUBSCRIBER_LIST_T Type	309-8
	DEQUEUE_OPTIONS_T Type	309-9
	ENQUEUE_OPTIONS_T Type	309-11
	QUEUE_PROPS_T Type	309-12
	SEEK_INPUT_T Type	309-13
	SEEK_OUTPUT_T Type	309-13
	SYS.MSG_PROP_T Type	309-14
	MESSAGE_PROPERTIES_T Type	309-16
	MESSAGE_PROPERTIES_ARRAY_T Type	309-19
	MSGID_ARRAY_T Type	309-20
310	DBFS Content Interface Types	
	DDBFS Content Interface Types Overview	310-1
	DBFS Content Interface Types Security Model	310-1
	DBFS Content Interface Types —Data Structures	310-1
	DBMS_DBFS_CONTENT_CONTEXT_T Object Type	310-2
	DBMS_DBFS_CONTENT_LIST_ITEM_T Object Type	310-2
	DBMS_DBFS_CONTENT_PROPERTY_T Object Type	310-3
	DBMS_DBFS_CONTENT_LIST_ITEMS_T Table Type	310-3
	DBMS_DBFS_CONTENT_PROPERTIES_T Table Type	310-4
	DBMS_DBFS_CONTENT_RAW_T Table Type	310-4
211	Database URI TYPEs	
311	- Database OTT TTT Es	
	Summary of URITYPE Supertype Subprograms	311-1
	UriType Supertype GETBLOB	311-2
	UriType Supertype GETCLOB	311-3
	UriType Supertype GETCONTENTTYPE	311-3
	UriType Supertype GETEXTERNALURL	311-3
	UriType Supertype GETURL	311-4



UriType Supertype GETXML	311-4
Summary of HTTPURITYPE Subtype Subprograms	311-4
HttpUriType Subtype CREATEURI	311-5
HttpUriType Subtype GETBLOB	311-5
HttpUriType Subtype GETCLOB	311-6
HttpUriType Subtype GETCONTENTTYPE	311-6
HttpUriType Subtype GETEXTERNALURL	311-7
HttpUriType Subtype GETURL	311-7
HttpUriType Subtype GETXML	311-7
HttpUriType Subtype HTTPURITYPE	311-8
Summary of DBURITYPE Subtype Subprogams	311-8
DBUriType Subtype CREATEURI	311-9
DBUriType Subtype DBURITYPE	311-9
DBUriType Subtype GETBLOB	311-9
DBUriType Subtype GETCLOB	311-10
DBUriType Subtype GETCONTENTTYPE	311-10
DBUriType Subtype GETEXTERNALURL	311-11
DBUriType Subtype GETURL	311-11
DBUriType Subtype GETXML	311-11
Summary of XDBURITYPE Subtype Subprograms	311-11
XDBUriType Subtype CREATEURI	311-12
XDBUriType Subtype GETBLOB	311-12
XDBUriType Subtype GETCLOB	311-13
XDBUriType Subtype GETCONTENTTYPE	311-14
XDBUriType Subtype GETEXTERNALURL	311-14
XDBUriType Subtype GETURL	311-14
XDBUriType Subtype GETXML	311-14
XDBUriType subtype XDBURITYPE	311-15
Summary of URIFACTORY Package Subprograms	311-15
UriFactory Package GETURI	311-16
UriFactory Package ESCAPEURI	311-16
UriFactory Package UNESCAPEURI	311-16
UriFactory Package REGISTERURLHANDLER	311-17
UriFactory Package UNREGISTERURLHANDLER	311-17
JMS Types	
JMS Types Overview	312-1
JMS Types Security Model	312-2
Java Versus PL/SQL Datatypes	312-2
More on Bytes, Stream and Map Messages	312-3
Upcasting and Downcasting Between General and Specific Messages	312-6



312

	JMS Types Error Reporting	312-6
	Oracle JMS Type Constants	312-7
	CONVERT_JMS_SELECTOR	312-8
	Summary of JMS Types	312-10
	SYS.AQ\$_JMS_MESSAGE Type	312-10
	SYS.AQ\$_JMS_TEXT_MESSAGE Type	312-16
	SYS.AQ\$_JMS_BYTES_MESSAGE Type	312-19
	SYS.AQ\$_JMS_MAP_MESSAGE Type	312-28
	SYS.AQ\$_JMS_STREAM_MESSAGE Type	312-37
	SYS.AQ\$_JMS_OBJECT_MESSAGE Type	312-46
	SYS.AQ\$_JMS_NAMEARRAY Type	312-46
	SYS.AQ\$_JMS_VALUE Type	312-46
	SYS.AQ\$_JMS_EXCEPTION Type	312-47
313	JSON Data Structures	
	JSON_ELEMENT_T Object Type	313-1
	JSON_OBJECT_T Object Type	313-4
	JSON_ARRAY_T Object Type	313-8
	JSON_SCALAR_T Object Type	313-10
	JSON_KEY_LIST Type	313-10
314	Logical Change Record TYPEs	
	Logical Change Record TYPEs Overview	314-1
	Logical Change Record Types Security Model	314-1
	Summary of Logical Change Record Types	314-1
	LCR\$_DDL_RECORD Type	314-2
	LCR\$_ROW_RECORD Type	314-10
	Common Subprograms for LCR\$_DDL_RECORD and LCR\$_ROW_RECORD	314-34
	LCR\$_ROW_LIST Type	314-44
	LCR\$_ROW_UNIT Type	314-45
315	MGD_ID Package Types	
	MGD_ID Package Types Security Model	315-1
	Summary of Types	315-2
	MGD_ID_COMPONENT Object Type	315-2
	MGD_ID_COMPONENT_VARRAY Object Type	315-2
	MGD_ID Object Type	315-3
	Summary of MGD_ID Subprograms	315-3
	MGD_ID Constructor Function	315-4



	GET_COMPONENT Function TO_STRING Function	315- <i>7</i> 315-8 315-9
	TRANSLATE Function	315-10
316	Rule TYPEs	
	Rule TYPEs Overview	316-1
	Rule TYPEs Security Model	316-1
	Summary of Rule Types	316-1
	RE\$ATTRIBUTE_VALUE Type	316-3
	RE\$ATTRIBUTE_VALUE_LIST Type	316-3
	RE\$COLUMN_VALUE Type	316-3
	RE\$COLUMN_VALUE_LIST Type	316-4
	RE\$NAME_ARRAY Type	316-4
	RE\$NV_ARRAY Type	316-4
	RE\$NV_LIST Type	316-4
	RE\$NV_NODE Type	316-7
	RE\$RULE_HIT Type	316-7
	RE\$RULE_HIT_LIST Type	316-8
	RE\$RULE_NAME Type	316-8
	RE\$RULE_NAME_LIST Type	316-8
	RE\$TABLE_ALIAS Type	316-8
	RE\$TABLE_ALIAS_LIST Type	316-9
	RE\$TABLE_VALUE Type	316-10
	RE\$TABLE_VALUE_LIST Type	316-10
	RE\$VALUE Type	316-10
	RE\$VALUE_LIST Type	316-11
	RE\$VARIABLE_TYPE Type	316-11
	RE\$VARIABLE_TYPE_LIST Type	316-13
	RE\$VARIABLE_VALUE Type	316-13
	RE\$VARIABLE_VALUE_LIST Type	316-13
317	SODA Types	
	SODA Types Overview	317-1
	SODA Types Security Model	317-1
	Summary of SODA Types	317-2
	SODA_Collection_T Type	317-2
	CREATE_INDEX Function	317-3
	CREATE_VIEW_FROM_DG Function	317-4
	DROP_INDEX Function	317-5



	FIND Function	317-6
	FIND_ONE Function	317-6
	GET_DATA_GUIDE Function	317-7
	GET_INDEX Function	317-7
	GET_METADATA Function	317-8
	GET_NAME Function	317-8
	INSERT_ONE Function	317-8
	INSERT_ONE_AND_GET Function	317-9
	LIST_INDEXES Function	317-9
	REMOVE_ONE Function	317-10
	REPLACE_ONE Function	317-10
	REPLACE_ONE_AND_GET Function	317-11
	SAVE Function	317-12
	SAVE_AND_GET Function	317-12
	TRUNCATE Function	317-13
SC	DDA_Document_T Type	317-13
	GET_BLOB Function	317-14
	GET_CLOB Function	317-14
	GET_CREATED_ON Function	317-15
	GET_DATA_TYPE Function	317-15
	GET_JSON Function	317-15
	GET_KEY Function	317-16
	GET_LAST_MODIFIED Function	317-16
	GET_MEDIA_TYPE Function	317-16
	GET_VARCHAR2 Function	317-17
	GET_VERSION Function	317-17
	SODA_Document_T Function	317-17
SC	DDA_OPERATION_T Type	317-18
	ACQUIRE_LOCK Function	317-20
	AS_OF_SCN Function	317-21
	AS_OF_TIMESTAMP Function	317-21
	COUNT Function	317-22
	FILTER Function	317-22
	GET_CURSOR Function	317-23
	GET_DATA_GUIDE Function	317-23
	GET_ONE Function	317-24
	HINT Function	317-24
	KEY Function	317-25
	KEYS Function	317-25
	LIMIT Function	317-26
	REMOVE Function	317-26
	REPLACE_ONE Function	317-26



	REPLACE_ONE_AND_GET FUNCTION	317-27
	SAMPLE Function	317-28
	SKIP Function	317-28
	VERSION Function	317-29
	SODA_CURSOR_T Type	317-29
	CLOSE Function	317-30
	HAS_NEXT Function	317-30
	NEXT Function	317-30
318	UTL Streams Types	
	UTL Streams Types Security Model	318-1
	Summary of UTL Binary Streams Types	318-1
	UTL_BINARYINPUTSTREAM Type	318-1
	UTL_BINARYOUTPUTSTREAM Type	318-2
	UTL_CHARACTERINPUTSTREAM Type	318-3
	UTL_CHARACTEROUTPUTSTREAM Type	318-4
319	XMLTYPE	
	Summary of XMLType Subprograms	319-1
	CREATENONSCHEMABASEDXML	319-2
	CREATESCHEMABASEDXML	319-2
	CREATEXML	319-3
	EXISTSNODE	319-5
	EXTRACT	319-5
	GETBLOBVAL	319-6
	GETCLOBVAL	319-6
	GETNAMESPACE	319-6
	GETNUMBERVAL	319-6
	GETROOTELEMENT	319-7
	GETSCHEMAURL	319-7
	GETSTRINGVAL	319-7
	ISFRAGMENT	319-7
	ISSCHEMABASED	319-7
	ISSCHEMAVALID	319-8
	ISSCHEMAVALIDATED	319-8
	SCHEMAVALIDATE	319-8
	SETSCHEMAVALIDATED	319-9
	TOOBJECT	319-9
	TRANSFORM	319-9



XMLTYPE 319-10

Index



Preface

This Preface contains these topics:

- Audience
- Related Documents
- Conventions

Audience

Oracle Database PL/SQL Packages and Types Reference is intended for programmers, systems analysts, project managers, and others interested in developing database applications. This manual assumes a working knowledge of application programming and familiarity with SQL to access information in relational database systems. Some sections also assume a knowledge of basic object-oriented programming.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Related Documents

For more information, see the following documents:

- Oracle Database Development Guide
- Oracle Database PL/SQL Language Reference

Many of the examples in this book use the sample schemas, which are installed by default when you select the Basic Installation option with an Oracle Database installation. Refer to *Oracle Database Sample Schemas* for information on how these schemas were created and how you can use them yourself.

Printed documentation is available for sale in the Oracle Store at

http://shop.oracle.com/

To download free release notes, installation documentation, technical briefs, or other collateral, please visit the Oracle Technology Network (OTN).

http://docs.oracle.com/



Conventions

This section describes the conventions used in the text and code examples of this documentation set. It describes:

- Conventions in Text
- Conventions in Code Examples

Conventions in Text

We use various conventions in text to help you more quickly identify special terms. The following table describes those conventions and provides examples of their use.

Convention	Meaning	Example
Bold	Bold typeface indicates terms that are defined in the text or terms that appear in a glossary, or both.	When you specify this clause, you create an index-organized table .
Italics	Italic typeface indicates book titles or	Oracle Database Concepts
	emphasis.	Ensure that the recovery catalog and target database do <i>not</i> reside on the same disk.
UPPERCASE	Uppercase monospace typeface indicates elements supplied by the system. Such elements include parameters, privileges, datatypes, RMAN keywords, SQL keywords, SQL*Plus or utility commands, packages and methods, as well as system-supplied column names, database objects and structures, usernames, and roles.	You can specify this clause only for a ${\tt NUMBER}$ column.
monospace (fixed-width)		You can back up the database by using the BACKUP command.
font		Query the TABLE_NAME column in the USER_TABLES data dictionary view.
		Use the DBMS_STATS.GENERATE_STATS procedure.
lowercase	Lowercase monospace typeface indicates executable programs, filenames, directory names, and sample user-supplied elements. Such elements include computer and database names, net service names and connect identifiers, user-supplied database objects and structures, column names, packages and classes, usernames and roles, program units, and parameter values. Note: Some programmatic elements use a mixture of UPPERCASE and lowercase. Enter these elements as shown.	Enter sqlplus to start SQL*Plus.
monospace		The password is specified in the orapwd file.
(fixed-width) font		Back up the datafiles and control files in the /disk1/oracle/dbs directory.
		The department_id, department_name, and location_id columns are in the hr.departments table.
		Set the QUERY_REWRITE_ENABLED initialization parameter to true.
		The ${\tt JRepUtil}$ class implements these methods.
lowercase	Lowercase italic monospace font represents placeholders or variables.	You can specify the parallel_clause.
<pre>italic monospace (fixed-width) font</pre>		Run old_release.SQL where old_release refers to the release you installed prior to upgrading.

Conventions in Code Examples

Code examples illustrate SQL, PL/SQL, SQL*Plus, or other command-line statements. They are displayed in a monospace (fixed-width) font and separated from normal text as shown in this example:

SELECT username FROM dba_users WHERE username = 'MIGRATE';



The following table describes typographic conventions used in code examples and provides examples of their use.

Convention	Meaning	Example
[]	Anything enclosed in brackets is optional.	DECIMAL (digits [, precision])
{ }	Braces are used for grouping items.	{ENABLE DISABLE}
I	A vertical bar represents a choice of two options.	{ENABLE DISABLE} [COMPRESS NOCOMPRESS]
•••	Ellipsis points mean repetition in syntax descriptions.	CREATE TABLE AS subquery;
	In addition, ellipsis points can mean an omission in code examples or text.	SELECT col1, col2,, coln FROM employees;
Other symbols	You must use symbols other than brackets ([]), braces ({}), vertical bars (), and ellipsis points () exactly as shown.	<pre>acctbal NUMBER(11,2); acct</pre>
Italics	Italicized text indicates placeholders or variables for which you must supply particular	enter password
	values.	DB_NAME = database_name
UPPERCASE	Uppercase typeface indicates elements supplied by the system. We show these terms in uppercase in order to distinguish them from terms you define. Unless terms appear in brackets, enter them in the order and with the spelling shown. Because these terms are not case sensitive, you can use them in either	<pre>SELECT last_name, employee_id FROM employees; SELECT * FROM USER_TABLES; DROP TABLE hr.employees;</pre>
	UPPERCASE or lowercase.	
lowercase	Lowercase typeface indicates user-defined programmatic elements, such as names of tables, columns, or files.	SELECT last_name, employee_id FROM employees; sqlplus user_id/password CREATE USER mjones IDENTIFIED BY ty3MU9;
	Note: Some programmatic elements use a mixture of UPPERCASE and lowercase. Enter these elements as shown.	,



Changes in This Release for Oracle Database PL/SQL Packages and Types Reference

This preface contains:

Changes in this Release

Changes in this Release

Review changes in this release of Oracle Database PL/SQL Packages and Types Reference.

- New Features
- Deprecated Features
- Desupported Features

New Features

This section lists the major new features in Oracle Database release 23ai *PL/SQL Packages* and *Types Reference*.

The following features are new in this release:

- DBMS_AUTOIM provides functions to manage the execution of the Automatic In-Memory feature.
- DBMS_SPM supports the SQL plan management feature by providing an interface for the DBA or other users to perform controlled manipulation of plan history and SQL plan baselines maintained for various SQL statements.
- DBMS_INMEMORY_ADVISE enables you to determine if a workload can benefit from Oracle's Database In-Memory feature.
- The DBMS_VECTOR package is a lightweight package that simplifies common operations with Oracle AI Vector Search, such as chunking and embedding data, generating text for prompts and images, or managing vector indexes.

DBMS VECTOR

 The DBMS_VECTOR_CHAIN package enables advanced operations with Oracle AI Vector Search, such as chunking and embedding data, generating text for prompts and images along with text processing and end-to-end similarity search.

DBMS VECTOR CHAIN

 The DBMS_HYBRID_VECTOR package enables you to search by both vectors and keywords against hybrid vector indexes.

DBMS HYBRID VECTOR

DBMS_DICTIONARY_CHECK is a read-only and lightweight PL/SQL package procedure that helps you identify database dictionary inconsistencies.

DBMS DICTIONARY CHECK

The UTL HTTP package supports digest SHA-256.

UTL HTTP

 The UTL_I18N package supports three new procedures that detect the most likely Oracle character sets and Oracle languages for a given data sample: DETECT_CHARSET, DETECT_LANGUAGE, and DETECT_LANGUAGE_CHARSET.

UTL I18N

• The DBMS_SAGA_ADM package provides a collection of saga administration functions and procedures to define and manage saga participants, coordinators, and brokers.

DBMS SAGA ADM

 The DBMS_SAGA package provides a collection of saga functions and procedures to initiate and finalize sagas.

DBMS_SAGA

- The DBMS_FLASHBACK_ARCHIVE package includes the GET_CURRENT_LIFESPAN_DIGEST Function that generates the current lifespan digest for the specified row in a user table, and the VERIFY_BLOCKCHAIN_LIFESPAN Procedure that verifies the contents of the current lifespans, historical lifespans, or all lifespans of the user table rows that are protected using blockchain Flashback Archive.
- The DBMS_KAFKA package provides a PL/SQL interface for enabling Oracle SQL access to topics in Kafka clusters.
- The DBMS_SEARCH package enables you to create, maintain, and query ubiquitous search indexes.

DBMS SEARCH

The DBMS SQL FIREWALL package enables users to administer SQL Firewall.

DBMS SQL FIREWALL

The DBMS CRYPTO package has the following new features.

DBMS CRYPTO

- New APIs for elliptic-curve Diffie—Hellman (ECDH) operations
 - * ECDH GENKEYPAIR: This function generates an EC public/private key pair
 - * ECDHDERIVE_SHAREDSECRET: This function derives shared secret using private key of local application and public key from the remote application.
- New PKENCRYPT/PKDECRYPT algorithm: PKENCRYPT_RSA_PKCS1_OAEP_SHA2
- New chain modes GCM CCM
- New DBMS CRYPTO block cipher suites AES CCM_NONE and AES_GCM_NONE
- New signature and verification algorithms:
 - * SIGN SHA224 ECDSA
 - * SIGN SHA256 ECDSA
 - * SIGN SHA384 ECDSA
 - * SIGN SHA512 ECDSA
 - * SIGN ECDSA



• The DBMS_SCHEDULER package has a new DUMP_IN_MEMORY_TRACE procedure that dumps the scheduler in-memory trace buffer of the specified process state object address into the current trace file of the requester process.

DBMS SCHEDULER

 The DBMS_SQL and DBMS_TF packages are updated to support the ISO SQL standardcompliant BOOLEAN data type.

DBMS_SQL

DBMS TF

• The DBMS_COMPRESSION package is updated to support the Advanced Low Index Compression for IOTs.

DBMS_COMPRESSION

The DBMS_SHARDING_DIRECTORY package is added to support the Oracle Globally
Distributed Database directory-based data distribution method.

DBMS_SHARDING_DIRECTORY

 The DBMS_AUTO_CLUSTERING package is added to support the automatic clustering and zone mapping.

DBMS_AUTO_CLUSTERING

 The DBMS_AUTO_INDEX package has a new parameter AUTO_INDEX_INCLUDE_DML_COST for the DBMS_AUTO_INDEX.CONFIGURE procedure.

DBMS_AUTO_INDEX

 The DBMS_BLOCKCHAIN_TABLE package has enhancements related to Blockchain Table User Chains, Blockchain Table Delegate Signer, and Blockchain Table Countersignature.

DBMS BLOCKCHAIN TABLE

- The DBMS DATA MINING package is enhanced to support the following settings:
 - IMPORT_ONNX_MODEL procedure. To learn more, see IMPORT_ONNX_MODEL Procedure.

Generalized Linear Model setting:

 GLMS_LINK_FUNCTION. See DBMS_DATA_MINING — Algorithm Settings: Generalized Linear Model.

XGBoost settings:

- xgboost interaction constraints
- xgboost decrease constraints
- xgboost_increase_constraints
- objective: survival:aft
- xgboost_aft_loss_distribution
- xgboost_aft_loss_distribution_scale
- xgboost_aft_right_bound_column_name
 See DBMS_DATA_MINING Algorithm Settings: XGBoost.

Explicit Semantic Analysis settings:

ESAS EMBEDDINGS



ESAS EMBEDDING SIZE

See DBMS_DATA_MINING — Algorithm Settings: Explicit Semantic Analysis.

Expectation Maximization setting:

EMCS OUTLIER RATE

See DBMS DATA MINING — Algorithm Settings: Expectation Maximization.

Exponential Smoothing settings:

- EXSM SERIES LIST
- EXSM INITVL OPTIMIZE

See DBMS_DATA_MINING — Algorithm Settings: Exponential Smoothing.

k-Means setting:

KMNS WINSORIZE

See DBMS_DATA_MINING — Algorithm Settings: *k*-Means.

Global settings:

- ODMS BOXCOX
- ODMS_EXPLOSION_MIN_SUPP

See DBMS_DATA_MINING — Global Settings.

The DBMS_USERDIAG package is a new package that allows you to perform a limited set of
diagnosis operations on the PDB, such as establish trace operations. Most of the regular
diagnostic mechanisms available in a CDB have been restricted out of security concerns.

See DBMS USERDIAG.

• The DBMS_PIPE package has been enhanced to support singleton pipes as well as persistent messaging using Cloud Object stores.

DBMS PIPE

The DBMS MLE package is updated to support the use of JavaScript modules.

DBMS MLE

The DBMS_AQMIGTOOL package simplifies migration from Oracle Database Advanced
Queuing (AQ) to Transactional Event Queue (TxEventQ) with orchestration automation,
source and target compatibility diagnostics and remediation, and a unified user experience.

DBMS AOMIGTOOL

The DBMS XMLSCHEMA UTIL package provides an interface for XML schema validation.

DBMS XMLSCHEMA UTIL

 The DBMS_SPACE package provides an interface for analyzing and shrinking a bigfile tablespace.

DBMS SPACE

- DBMS_CACHEUTIL has new TRUE_CACHE_KEEP and TRUE_CACHE_UNKEEP procedures to manage assignments to the KEEP buffer pool for Oracle True Cache.
- The following new procedures are introduced in the DBMS_APP_CONT package to enhance the Application Continuity functionality:
 - APPLY_REPLAY_RULE
 - GET REPLAY_RULES
 - RESET REPLAY RULES



- The following new procedures are introduced in the DBMS_APP_CONT_ADMIN package to enhance the Application Continuity protection check:
 - ENABLE_AC
 - ENABLE TAC
 - ACCHK SET FILTER
 - ACCHK SHOW FILTERS
 - ACCHK_CLEAR_FILTER
 - DISABLE FAILOVER
 - ENABLE RESET STATE
 - MODIFY_SERVICE
 - SET DRAINING
 - SET LOAD BALANCING
- The DBMS_CLOUD_AI package allows you to create AI profiles and configure them for access to a Large Language Model (LLM).

DBMS CLOUD AI

 The DBMS_CLOUD_NOTIFICATION package allows you to send messages or the output of a SQL query to a provider.

DBMS_CLOUD_NOTIFICATION

 The DBMS_CLOUD_PIPELINE package allows you to create data pipelines for loading and exporting data in the cloud.

DBMS CLOUD PIPELINE

 The DBMS_CLOUD_REPO package provides for use of and management of cloud hosted code repositories from Oracle Database.

DBMS CLOUD REPO

Deprecated Features

Review this list of deprecated features in Oracle Database release 23ai Oracle Database PL/SQL Packages and Types Reference.

Oracle recommends that you do not use deprecated features or values in new applications. Support for deprecated features is for backward compatibility only. For more information about deprecated features, see *Oracle Database Upgrade Guide*.

Deprecation of the mkstore wallet management command line tool

The mkstore wallet management command line tool is deprecated with Oracle Database 23ai, and can be removed in a future release.

To manage wallets, Oracle recommends that you use the orapki command line tool.

Deprecation of DBMS_RESULT_CACHE Function Names

Oracle is changing the names of several DBMS_RESULT_CACHE function names in Oracle Database 23ai.

The following functions and procedures are deprecated:

BLACK LIST function. Use BLOCK LIST function.



- BLACK LIST ADD procedure. Use BLOCK LIST ADD procedure.
- BLACK_LIST_CLEAR procedure. Use BLOCK_LIST_CLEAR procedure
- BLACK LIST REMOVE procedure. Use BLOCK LIST REMOVE procedure
- OBJECT BLACK LIST function. Use OBJECT BLOCK LIST function
- OBJECT BLACK LIST ADD procedure. Use OBJECT BLOCK LIST ADD procedure.
- OBJECT_BLACK_LIST_CLEAR procedure. Use OBJECT BLOCK LIST_CLEAR procedure.
- OBJECT_BLACK_LIST_REMOVE procedure. Use OBJECT_BLOCK_LIST_REMOVE procedure.

Deprecation of DBMS_XMLSTORE

The PL/SQL package DBMS_XMLSTORE is deprecated in Oracle Database 23ai. DBMS_XMLSTORE is a non-standard Oracle-proprietary package that enables you to store and manipulate XML data in Oracle Database. This package is deprecated, and can be desupported in a future release. Oracle recommends that you use regular SQL DML and with standard XQuery and SQL/XML to store and manage XML data. Using standard functionality provides future-proof way to store and manipulate XML data.

Deprecation of DBMS_XMLGEN PL/SQL Package

The PL/SQL package <code>DBMS_XMLGEN</code> is deprecated in Oracle Database 23ai. <code>DBMS_XMLGEN</code> is a non-standard Oracle-proprietary package that is provided to generate and convert XML documents from SQL queries or with PL/SQL. This package is deprecated, and can be desupported in a future release. Oracle recommends that you use SQL/XML operators to generate XML from relational columns instead. Using ANSI SQL/XML operators for any generation and modification of XML documents provides a standardized and future-proof way to work with XML documents.

Deprecation of XML DB Repository

The Oracle XML DB Repository is deprecated with Oracle Database 23ai. Oracle recommends that you replace any functionality used in XML DB Repository with alternative technologies. As a result of this deprecation, all XML DB Repository interfaces (for example Repository-specific Java classes oracle.xdb.servlet, oracle.xdb.event, and oracle.xdb.spi) are consequently deprecated as well.

Deprecation of DBMS_HANG_MANAGER Package

The DBMS_HANG_MANAGER package is deprecated in Oracle Database 23ai. Use DBMS_BLOCKER RESOLVER instead.

The DBMS_HANG_MANAGER package provides a method of changing some configuration parameters and constraints to address session issues. This package is being replaced with DBMS_BLOCKER_RESOLVER. DBMS_HANG_MANAGER can be removed in a future release.

Deprecation of Traditional Auditing Packages and Functions

Traditional auditing packages and functions are deprecated in Oracle Database 23ai.

With the desupport of traditional auditing, the PL/SQL packages and functions associated with traditional auditing are deprecated, This deprecation includes the packages and functions <code>INIT_CLEANUP</code>, <code>DEINIT_CLEANUP</code>, and <code>IS_CLEANUP_INITIALIZED</code>. While these packages or functions continue to operate in Oracle Database 23ai, you can neither add to or modify traditional auditing configurations.



Deprecation of Oracle OLAP

Analytic workspaces, the OLAP DML programming language, financial reporting, and the OLAP Java API continue to be deprecated in Oracle Database 23ai.

Be aware that OLAP will not be supported beyond the term of the current release (Oracle Database 23ai) premier support. Oracle strongly recommends that you do not start new projects using OLAP and begin migrating applications using OLAP to alternatives now. If your application requires an in-database dimensional model, then consider using Oracle Analytic Views. Analytic views provide a dimensional semantic model, calculations, and query semantics using data in Oracle Database. When used with columnar tables, analytic views provide query performance similar to the OLAP Option. If your application requires support for advanced dimensional analytics, what-if analysis, or forecasting, then consider Oracle Essbase. Oracle Essbase is a multidimensional database management system with support for complex dimensional business analytics.

Related Topics

 Oracle Database Changes Desupports and Deprecations in Oracle Database Upgrade Guide

Desupported Features

This section lists the desupported features in Oracle Database Release 23ai Oracle Database PL/SQL Packages and Types Reference.

For more information about desupported features in this release, see *Oracle Database Upgrade Guide*

The following features are desupported in this release:

Desupport of Oracle Enterprise Manager Database Express

Oracle Enterprise Manager Database Express (EM Express) is desupported in Oracle Database Release 23ai.

EM Express is a web-based database management tool that is built inside Oracle Database. It supports key performance management and basic database administration functions. EM Express was deprecated in Oracle Database 21c. Many of EM Express's capabilities are now available in Oracle Cloud Infrastructure (OCI) Database Management service, Oracle Enterprise Manager Cloud Control, or Oracle SQL Developer.

Desupport of Service Attribute Value SESSION_STATE_CONSISTENCY = STATIC Parameter

The service attribute values FAILOVER_TYPE = TRANSACTION with SESSION_STATE_CONSISTENCY = STATIC are no longer a supported service attribute combination.

In previous releases, you could use the service parameter <code>SESSION_STATE_CONSISTENCY</code> to manage session state automatically using Application Continuity by setting <code>SESSION_STATE_CONSISTENCY</code> to <code>DYNAMIC</code> or <code>STATIC</code>. However, starting with Oracle Database 23ai, you can no longer use the <code>STATIC</code> option. Instead, use one of the following failover options:

- FAILOVER TYPE = AUTO with SESSION STATE CONSISTENCY = AUTO
- FAILOVER TYPE = TRANSACTION with SESSION STATE CONSISTENCY = DYNAMIC

These configurations enforce session state tracking in Oracle Database, ensuring that session state is preserved at session migration and session failover.



Desupport of Oracle Wallet Manager (OWM)

Starting with Oracle Database 23ai, the Oracle Wallet Manager (OWM) is desupported. Oracle recommends using the \mathtt{orapki} command line tool to replace OWM.

Related Topics

 Oracle Database Changes Desupports and Deprecations in Oracle Database Upgrade Guide

